

"Ordinary online services left me flat..."

"With GEnie™ I discovered vast new horizons."





\$10+ per hour

There's only so far you can go with most ordinary online information networks. But with GEnie-the General Electric Network for Information Exchange—there's virtually no end to the exciting new interests you can explore. Discover the value of GEnie's vast range of services and explore new territory with guides from our Special Interest Groups.

Join the friendly crew with GEnie's Tandy† RoundTable™ Special Interest **Group** for exciting and informative discussions. Benefit from the expertise of experienced individuals. Compare notes on hardware, software, games or any other topic you choose. And, for the simple cost of downloading, collect hundreds of valuable public domain software programs for your personal computer. Over 1000 new programs are added to our libraries every month. And remember, UPLOADS ARE FREE on GEnie!

No extra charge for 1200 Baud.

Make new friends, schedule meetings, gather facts and figures, set up travel plans, get the news, be entertained and even shop online for a fraction of what other information services charge, because GEnie's non-prime rate for 300 or 1200 baud is only \$5 an hour. GEnie always comes out ahead of the competition in savings, in some cases by as much as 60%.

You get even more for your money.

In addition to user support groups, you can meet new people with GEnie's Live Wire TM CB Simulator. Exchange messages with electronic mail service. Find the best vacation

deals and make your reservations with American Airlines travel service. Shop at home with American Express Merchandise Shop. Learn the fun way with a subscription to Grolier's electronic encyclopedia. Play classic and

\$5 per hour

Backed in the GE Tradition

GEnie is brought to you by General Electric, whose reputation is built on attention to detail and customer satisfaction. We're continuing that tradition with GEnie.

Compare Save*	1,100		Service	ces	Pricing							
	Travel &	SIGs/User	CB &	Financial			Registration	Montbly	Non-prime time rates			
	Shopping	Groups	Mail	Services	News	Games	Fee	Minimum	300 baud	1200 baud		
The Source	X	X	X	X	X	X	\$49.95	\$10.00	\$8.40	\$10.80		
CompuServe	Х	X	X	Х	X	X	\$39.95	none	\$6.00	\$12.50		
GEnie†	X	X	X	X	X	X	\$18.00	none	\$5.00	\$5.00		

ates and services shown in effect 2/87. Non-prime time applies Mon.—Fri., 6pm—8am local time, all day Sat., Sun., and nai'l bolidays. Subject to vallability. Additional charges apply for 2400 baud and financial services.

multiplayer games. Use GEnie's Financial Services to track stock market quotes, check market indicators and maintain an automatically updated personal portfolio online. All this plus new services added each and every month!

Map out your own voyage of discovery with GEnie as your guide ... enrich your tomorrows by signing on with GEnie today.

Sign up from your keyboard today. 4 Easy Steps:

- Have your major credit card or checking account number ready.
- Set your modem for local echo (half duplex)-300 or 1200 baud.
- Dial 1-800-638-8369. When connected, enter HHH
- At the U# = prompt enterXJM11883, GEnie then RETURN.

Need help or more information? No modem yet? We can help. In U.S. or Canada call 1-800-638-9636.

Stay online longer, for less.



General Electric Information Services Company, USA

GEnie rates and services subject to change. Uploads are free during non-prime hours at 300 or 1200 baud. Some services offered on Genie may include additional charges.

† Tandy is a registered trademark of Tandy Corporation

COPS!

Instant Spelling Checker and Thesaurus

CHECKS YOUR SPELLING AS YOU TYPE...and much more!

The Choice Is Clear!

Spelling Checker Instant Proofing

Screen Proofing Disk File Proofing Word Count Add. Word Limit Correction Feature **Displays Dictionary** Displ. Hyphenation Safe Exit One Step Installation Copy Protected

Thesaurus

No. Lookup words Min. Disk Space

Price

Circle 245 on Reader Service card.

IBM PC @ IBM, Whoops @ Cornucopia

Whoops Lightning

Full	Partial
Dictionary	Dictionary
1	
1	No
50,000 15.000	80,000
15,000	300
V	-
1	No
-	No
	No
-	No
No	No

10,000	5,000
39K	98 K
\$49.95	\$99.95

Wordstar & MicroPro, DeskMate & Tandy, PFS: Write & Software Publishing Corp., PC-Write M Quicksoft,

Makes proofing easy. In addition to an on-line thesaurus, Whoops offers you all the benefits of a traditional spelling checker, plus the added convenience of an instant spelling checker. Whoops can work from within your word processing program, proofing each word as you type so you can always be confident that your text is correct. Whether you use Wordstar®, DeskMate®, PFS:®Write, LeScript™, PC-Write™, Microsoft® Word, or just about any other word processing, or spread sheet program, you'll find that Whoops makes your work a pleasure.

Acclaimed "Whoops! is a real buy at only \$49.95." PC Magazine 2/24/87

"Given the sophistication of this program, it is surprisingly easy to use. Especially impressive is the operating speed." Software Reports 4/23/86

Guarantee

If you aren't completely satisfied with Whoops, return it within 30 days for a full refund of the purchase price. Computer must be IBM PC compatible with at least 256K of RAM.

More Low Prices

ı	Lescript (TRS-DOS)	\$199.95	\$89.99
١	Lescript (MS/DOS))	\$129.95	\$139.99
i	Whoops (MS/DOS)	\$ 69.95	\$49.95

Circle 245 on Reader Service card.

Prices good thru 7/87. Add \$5 S&H

CALL NOW TOLL FREE


1-800-343-2432

(In CA, call 415-528-7002) Software Sales, P.O.Box 5028 Walnut Creek, CA 94596

- INTEGRATES into 11 different word processing programs incl.: Wordstar, Allwrite, Lescript, Superscripsit, Scripsit, Deskmate, Lazy Writer, and Electric Pencil (specify). Begins proofing at the stroke of a key; where possible, returns you to word processing w/ corrected text on screen.
- DISPLAYS CORRECT SPELLINGS: If you don't know the correct spelling, EW will look it up for you, and display the dictionary.
- VERIFIES CORRECTIONS: If you think you know the correct spelling of a word, EW will check it for you before making the corrections.
- HYPHENATES AUTOMATICALLY: (Optional). Inserts discretionary hyphens throughout text.
- GRAMMAR & STYLE CHECKER: (Optional). Identifies 22 types of com mon errors. Makes suggested corrections with the stroke of a key. Runs within EW
- 50,000 WORD DICTIONARY: Uses only 21/2 bytes per word; add as many words as you wish.
- FAST CORRECTING: In as little as 30 seconds, Electric Webster can return you to your Word Processing program, with your text fully corrected and on your screen.

Still #1

"Electric Webster, a fantastic spelling and grammar checker!" 80 Micro 4/85



"The Cadillac"

of spelling checkers 80 Microcomputing, 9/82

VOTED #1: For the second straight year, Electric Webster was voted the #1 spelling checker in the 80 Micro Reader's This dictionary not published by the original publishers of Choice Awards. (1/83, 1/84)

ACCLAIMED:

"Electric Webster is the best. Just read any review in any magazine and I don't believe that you will find even one disagreement to that statement." CINTUG, Cincinnati's Users Group Mag., 4/83

"Now there's a program called Electric Webster that would let me write to Presidents and Kings and never feel embarrassed. Miss Mulberry would give Electric Webster an A+, and so will you."

Computer User, 1/84

"The most helpful program I've found is Electric Webster. After looking at nine proofreading programs, I've settled on Webster ... "Creative Computing, 11/83

Special Prices!

TRS-80 Electric Webster \$ 89.95 - 59.95 w/Correcting Feature \$149.95 119.95 \$ 49.95 39.95 \$ 49.95 39.95 Hyphenation Grammar & Style THE WORKS \$249.85 179.95 MS/DOS or CP/M Electric Webster \$129.95 w/Correcting, Hyph., G.&S. \$5.00 DEMO for any of Above

> Prices good thru 7/87, so order now! Circle 45 on Reader Service card.

Cornucopia Software, Inc. (415) 524-8098 Box 6111, Albany, CA 94706

Webster's Dictionary or their successors.



2701-C W. 15th • SUITE 612 • PLANO, TX 75075 • (214) 680-8268

HI RESOLUTION GRAPHICS

THE GRAPHICS SOLUTION by Micro
Labs \$199.95
Run the best H-Res board on your Mod III or 44P- Far superior
to Rado Stacks board, this gem will open up a new world
of graphics applications. Graphics basic is included along with
30 other H-Res demos & applications and a detailed user
manual. All major operating systems are supported and the
H-Res soren can be printed on 20 popular printers. Instaltation is simple with a dipon internal board. H-Res, test &
Low-Res graphics can all be displayed simulaneously. This
board is the first H-Res modification on the market and
additional H-Res software is available. Call for their details.
Specify Mod III, Mod 4, 4P or 4D when ordering.
WAS \$209.95 REDUCED TO \$199.95 SALE
\$180.95
H-LRES SOFTWADE

HI-RES SOFTWARE

															٠								39.95
MAT	HPLOT					ì	Ī	ì					ĺ	i	ì							į,	39.95
BASI	CE					i	ì	Ī		ì			i	i	Ĺ	i		ì				Ċ	39.95
SLID	ESHO	N				i	ì							ì								·	19.95
	AR																						
DRA	W					į.	ì						ì	ì	į	ì				. ,			39.95
BIZG	RAPH										v	vs	ŁS	Û	9	A	0	O	ì	ne	w	v	75.00
	NCED																						
	D																						
OI IDI	TACE E											•			_								
																							39.95
G PA	SIC 3	21		×							ú	Ė	ir	i						٠			39.95
G BA	SIC 3.	0	F	ЭF	1	R	K	ò	Ε	X	у	١F	ľ)									49.95
G BA	SIC 3.	0	F	æ	H	E	S	ŝ	E	30)A	VF.								-			49.95 49.95
G BA	ISIC 3. RNAME RNAME	0 N N	FIT	X CR	HE	A E V	SEL	S	S	1)A	VF.											49.95 49.95 29.95
G BA TOUR TOUR 3-D	ISIC 3. RNAME RNAME TIC TAI	ONNC	FITT	X CRX	HE	REVI	SEI	SE	S	1)A	VF.								×			49.95 49.95 29.95 19.95
G BA TOUR TOUR 3-D T LIFE	ISIC 3. RNAME RNAME	ONNCR	FITTE	X CRER	HE	REVI	SEL	S	S											×			49.95 49.95 29.95 19.95 24.00

The TRS-80 **GRAB BAG**

If you own a TRS-80 (Mod I/III/4), and you are a chance taker, or a gambler and LOVE surprises, our GRAB BAG may just be for you. Send us just 39.95, along with our standard \$3.00 shipping, and we will comb the far reaches of our warehouse. We will ship you a surprise package worth more than \$200.00. It may be computer hooks life organized. may be computer books, disk programs, tape programs, other goodies or assortments of all. Programs will be guaranteed to run and replaced if they don't. Some items may be old, some current. that's the surprise

Refunds or exchanges are not allowed but we know that you won't be disappointed.

SCHOOL UTILITY AND EDUCATIONAL

Power Reading (Speed Reading) 6	4.50
Addtl courseware disk for above . 1	6.50
Test Question Data Bank III/MS 4	9.95
Test Generator/Drill III	4.95
Football Scouting III 4	9.95
Basketball Statistics III 3	9.95
Baseball Statistics III	9.95
Student Schedule Data Base III 4	9.95
Teacher Evaluation III	9.95
MACRO Typing Tutor I/III/4 3	9.95

SUPERDIRECTORY

Index all of your diskettes and disk files with SUPERDIRECTORY. This unique program will read all of your disk files, generate a master library sorted by file name or extension along with the appropriate disk number. Your master inpropriate disk number. Your master index can be sent to the printer or brought to the screen. We even include an editor so you can add one line of comments to each file in the library. While SU-PERDIRECTORY runs on the Model I or III (4/4P/4D in the MOD III mode), it will read and index Model 4 diskettes while in the Model III mode. When ordering, Model I or Model III must be specified. Also, please inform us if you are going to run it on the Model 4P as an additional file is needed. Retail \$49.95 SAVE 20% NOW \$39.95

GRAPHICS AND GAMES

Powerdraw I/III	1.95
PowerDot II Mod I/III Spec. Prntr 39	9.95
Meltdown (Nuclear Powerplant) I/III 19	.95
Gamepak-3 (Funnyface, Match, etc.) . 29	9.95
Mask Maker Model 4 38	9.95
Datagraph I/III/4	.95
Datagraph w/Pie Chart Option 109	
Leo's Greates Hits 19	9.95

OPERATING SYSTEMS

DosPlus	4A with M ZAL	129.95
	3.5 I/III Specify	
Multidos	Version 2 Mod I/III Specify	. 79.99
Multidos	80/64 Ver 2 Mod 4	. 89.95

MOD 4 BY JACK

A complete re-write of the Mod 4 manual in English! \$14.95

UTILITIES

Fast/CMD run TRSDOS 1.3 in 4 @ 4	mhz
	29.95
J&M Memory Minder Mod I	84.95
J&M Memory Minder Mod III/4	74.95
The Toolbox for LDOS I/III	44.95
The Toolbelt for TRSDOS 6	44.95
ALCOR C Complete System	64.95
ALCOR Multi-Basic Compiler	84.95
ALCOR Pascal	64.95
Superkeys (Keyboard Macros) Mod III	1
	19.95
AOS Utils (Varkeep & Screenpacker).	49.95
Pascal-80 I/III	59.95
AS Public Domain Disks	. 9.95
Zuess Editor/Assembler I/III/4	74.95
System Diagnostic I/III/4 Specify	69.95
Trashman VIII	
Faster I/III	
RPM Disk Drive Timer	24.95
DSMBLR III I/III	29.95
Pro-Duce Mod 4 Disassembler	29.95
Accel 3/4 Basic Compiler I/III	44.95
Dostamer Mod 4 or MSDOS	49.95
Pro-Warn (Mod 4 Window Mgr)	59.95
Z-Basic Compiler 3.0	79.95
Monitor 5 I/III/IV	19.95

ELECTRONIC **BULLETIN BOARDS**

RUN YOUR OWN BULLETIN BOARD

You too can be a sysop. Run your own BBS and open up your computer to the outside world.....Imagine a real time electronic message center in your own

COMPLETE SYSTEMS

INFOEX-80 I or	III (will	run on	hard	disk)
***********				99.9
FAST-80 for the				
BBS-PC IBM or	Compa	tibles .		250.00
Call	for addi	tional d	ietails	

BOOKS, WALL CHARTS & MISC

Using SuperUtility	17.95
Super Utility Tech Manual	13.95
Rom Routines Documented I/III/4	19.95
TRSDOS 6 Programmers Guide	
Green Screens I, III, 4/4P	16.95
Diskettes DSDD 10 in Plastic Bx	
Sentinel Color Disks in " "	14.95
Wall Charts, specify Profile, Visicalc,	Super-
Scripsit, Mod III or Mod 4 BASIC	. 4.00
TRS-80 For Kids 8 to 80 Vol 1	. 7.95
TRS-80 For Kids 8 to 80 Vol II	. 7.95
Maintain & Service your Computer	11.95
Comp. Communications Tech	10.95
Electronically Speaking	. 9.95
Practice Problems in Numbers/Logic.	
Inside your Computer	. 8.95
The World Connection	
IBM PC for Kids 8 to 80	
Annotated Basic Vol I or II	
The Compag Users Handbook	
ABPC a Kids Guide to the IBM PC .	

Send for Our **New Catalog TRS-80 MSDOS**

DOSTAMER

By the Babbage Patch

Just Reduced NOW \$49.95

Dostamer Mod 4/4P/4D

Dostamer for 1000, PC/MSDOS 49.95

You have heard of DOS manager type programs in the MS-DOS world. Now the Mod 4 has one too. Rated 4½ stars by 80 MI-CRO, it has 10 full user menu screens to customize your DOS. Help menus are included and now, for a first, you can compete all were disease. ment all your directory entries. Tag/Untag all files for mass copy/kill etc. Over 200 user defined keys. We highly recommend this outstanding software package.

APPLICATIONS

Infoscan I/III	ı	ı		ı	ı	ı.	ı		39.95
ENBASE (Data Base) I/III .	ì	Ç	i,	ĺ,	į,	i	ı.	į,	79.95
ST-80 III Terminal/Host I/III	١.	è	ě.	ı	ı	į,	ı	ú	69.95
SuperDirectory I/III specify	ı,	į,		i.	ú	ı	ı	i,	39.95
Ultraterm I/III	ı	i	,	ï	ú	ı	ī,	ı	44.95
Ultraterm 2.0 w/auto log-or	١	ı			ı	ŝ	į	ı	59.95
Modem 80 I/III									
Modem 80 Mod 4	į,	,		ú	ı,	ı	ı	ı	79.95

The Programmer's Guide To LDOS/TRSDOS6

Five star rated by 80 MICRO, The Programmers Guide is a must have book. 200 Pages-8% x 11 Sale 19.95 Retail 24.95

WORD PROCESSORS AND PRINTER DRIVERS

Lazy Writer I/III/4 Specify	. 119.95
Lazy Font I/III/4+3 Specify	44.95
M-Script I/III/4	
LeScript I/III/4	
LeScript MSDOS 1000/1200, etc	
PowerDrivers for SuperScripsit and	
sons, C. Itoh Prowriter, Starwriter a	nd Oki-
data 92 for I/III/4 specify Printer	29 95

SUPER UTILITY By POWERSOFT

VOTED AS THE OUTSTAND UTILITY BY 80-MICRO READERS

PROTECTED MEDIA

BUY SUPERUTILITY PLUS

3.2 FOR MOD I/III OR 4/4P FOR MOD 4/4P AT \$74.99 AND RECEIVE THE NEW BOOK USING SUPERUTILITY PLUS

FREE A \$100.00 VALUE FOR ONLY \$74.99

SUPERUTILITY/PC NOW \$84.95

BUSINESS SOFTWARE

FBN General Ledger Mod III 150.	Č
Powermail Plus I/III/4 Specify 79.	8
Powermail Plus w/Text Merge 99.	9
The Basic Checkbook I/III 64.	ŝ
Loan Amortization Mod III 29.	g
Inventory Control ICS Pro Mod I/III 89.	g
SPS Statistical Analysis (Call) 150.	0
The Home Accountant 69.	9
Lynn's Payroll System III or 4 49.	9
Lynn's Accounts Receivable Mod III 29.	g
Lynn's Easy Mail Mod III 29.	į

TRSDOS-MSDOS **Conversion Utilities**

TRSCROSS only 89.95

This program is a must for converting TRS-DOS type files to the PC/XT/AT and all true IBM compatibles. TRSCROSS runs on the PC's and Clone's and converts basic programs on the fly. All Model III and IV disk ormats are supported. NEWDOS 80, LDOS, MULTIDOS and TRSDOS. Model I diskettes must be in double density to be converted. TRSCROSS will also move files from IBM types back to the TRS-80's.


MSDOS SOFTWARE

Microsoft Word	200 05
Microsoft Word	140.05
Troine Tata III (0)	148.80
Typing Tutor III (Simon & Schuster)	34.95
Volkswriter Delux	149.95
Websters New World Spelling	
Checker	54.95
Websters New World Thesaurus	59.95
Volkswriter Delux Volkswriter Delux Websters New World Spelling Checker Websters New World Thesaurus Word Perfect 4.1	299.95
Multiplan	149.95
Multiplan	200 05
The Twin (1-2-3 Clone)	70 OF
Cornerstone (Infocom)	04.06
DEC Professional City	. 84.90
PFS Professional File (Includes Report) PFS 1st choice (Includes File,	-
(includes Heport)	199.95
PFS 1st choice (Includes File,	
Write, Plan and Access)	129.95
RBase 5000	389.95
Reflex	129.95
Reflex	. 29.95
DosTamer	40 05
Fast Back 5.1	140 05
Fast Back 5.1 Microsoft Windows	70.05
Norton Commander	FR 05
Norton Commander	. 56.95
Norton Utilities 3.1	. 79.95
1 Dir	. 79.95
PC Tools	
Printworks	. 59.95
SideKick (non-protected)	. 59.95
Sideways	. 54.95
Superkey	50 05
Traveling SideKick	50.05
Dollare & Sance 2.0	120 06
Donais a denied E.U	
The Home Accountant Dive	70.05
The Home Accountant Plus	. 79.95
The Home Accountant Plus Managing the Market	79.95 129.95
The Home Accountant Plus Managing the Market Managing Your Money	. 79.95 129.95 149.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp	. 79.95 129.95 149.95 . 79.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp	. 79.95 129.95 149.95 . 79.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft C Compiler	. 79.95 129.95 149.95 . 79.95 349.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft C Compiler	. 79.95 129.95 149.95 . 79.95 349.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher. Draw (Windows version by Microgra	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95 fx)
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95 fx) 169.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95 fx) 169.95 249.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 149.95 fx) 169.95 249.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 fx) 169.95 249.95 . 49.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Tression of Market The Print Shop	. 79.95 129.95 149.95 . 79.95 349.95 129.95 . 49.95 fx) 169.95 249.95 . 49.95 . 49.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting	. 79.95 129.95 149.95 . 79.95 129.95 129.95 . 49.95 fx) 169.95 249.95 . 49.95 . 49.95 . 49.95 . 49.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting	. 79.95 129.95 149.95 . 79.95 129.95 129.95 . 49.95 fx) 169.95 249.95 . 49.95 . 49.95 . 49.95 . 49.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft C Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Tression of Market The Print Shop	. 79.95 129.95 149.95 . 79.95 129.95 . 49.95 149.95 fx) 169.95 249.95 . 99.95 . 49.95 . 29.95 349.95 . 54.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster	. 79.95 129.95 149.95 149.95 129.95 . 49.95 149.95 (x) 169.95 249.95 . 99.95 . 49.95 . 29.95 349.95 54.95 54.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler	. 79.95 129.95 149.95 349.95 129.95 .49.95 149.95 fx) 169.95 249.95 .99.95 349.95 .54.95 .44.95 .29.95 .44.95 .29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler	. 79.95 129.95 149.95 349.95 129.95 .49.95 149.95 fx) 169.95 249.95 .99.95 349.95 .54.95 .44.95 .29.95 .44.95 .29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader Evelyn Wood's Dynamic Reader	. 79.95 129.95 149.95 349.95 129.95 49.95 (49.95 (54).95 (54).95 49.95 249.95 349.95 29.95 349.95 54.95 29.95 349.95 54.95 64.95 64.95 29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader Evelyn Wood's Dynamic Reader	. 79.95 129.95 149.95 349.95 129.95 49.95 (49.95 (54).95 (54).95 49.95 249.95 349.95 29.95 349.95 54.95 29.95 349.95 54.95 64.95 64.95 29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader Evelyn Wood's Dynamic Reader	. 79.95 129.95 149.95 349.95 129.95 49.95 (49.95 (54).95 (54).95 49.95 249.95 349.95 29.95 349.95 54.95 29.95 349.95 54.95 64.95 64.95 29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader Evelyn Wood's Dynamic Reader	. 79.95 129.95 149.95 349.95 129.95 49.95 (49.95 (54).95 (54).95 49.95 249.95 349.95 29.95 349.95 54.95 29.95 349.95 54.95 64.95 64.95 29.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader F-15 Strike Eagle Flight Simulator GATO Computer S.A.T. (H.B.J.)	. 79.95 129.95 129.95 . 79.95 349.95 149.95 . 49.95 149.95 (x) 169.95 249.95 . 29.95 349.95 . 54.95 . 7.95 64.95 . 29.95 . 349.95 . 7.95 64.95 . 349.95 . 349.95 . 349.95 . 349.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader F-15 Strike Eagle Filight Simulator GATO Computer S.A.T. (H.B.J.) Jet	, 79,95 129,95 149,95 , 79,95 349,95 149,95 (b) 169,95 249,95 99,95 349,95 29,95 349,95 44,95 44,95 44,95 29,95 349,95 349,95 44,95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader F-15 Strike Eagle Flight Simulator GATO Computer S.A.T. (H.B.J.) Jet Math Blaster	. 79.95 129.95 129.95 . 79.95 349.95 149.95 (A) 169.95 249.95 249.95 29.95 349.95 54.95 29.95 349.95 54.95 29.95 349.95 349.95 349.95 349.95 349.95 349.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader F-15 Strike Eagle Flight Simulator GATO Computer S.A.T. (H.B.J.) Jet Math Blaster	. 79.95 129.95 129.95 . 79.95 349.95 149.95 (A) 169.95 249.95 249.95 29.95 349.95 54.95 29.95 349.95 54.95 29.95 349.95 349.95 349.95 349.95 349.95 349.95
The Home Accountant Plus Managing the Market Managing Your Money Microsoft Quick Basic Comp Microsoft Compiler Microsoft Compiler Microsoft Macro Assembler Certificate Maker Click Art Personal Publisher Draw (Windows version by Microgra Prodesign II PFS Graph The Print Shop Graphics Library BPI General Accounting DAC Easy Alge Blaster Loderunner Infocom 4-in-one Sampler Evelyn Wood's Dynamic Reader F-15 Strike Eagle Filight Simulator GATO Computer S.A.T. (H.B.J.) Jet	, 79.95 129.95 149.95 , 79.95 349.95 149.95 169.95 249.95 99.95 54.95 29.95 349.95 54.95 64.95 29.95 349.95 79.95 34.95 39.95 34.95 39.95 34.95 39.95 39.95 39.95

214-680-8268 OPEN MON.-FRI. 10-7 CST


Send Cash, Check or Money Order. Please add \$3.00 for UPS Shipping or \$5.00 For US Postage & Insurance. COD's send an additional \$3.00 COD fee. All COD's will require cash or certified upon delivery.

Foreign orders are welcome. All shipping charges assumed by purchaser. When ordering by mail, please specify computer and model number. Phone Your Order In Today Or Mail To:





and VISA Cheerfully Accepted



With as many features as wordprocessors selling for 10

times the price, Electric Pencil PC was designed to be sophisticated enough for the professional user yet simple enough for the beginner. Our "Quick Start Guide" will have you writing, editing, and printing in less than 20 minutes. Once you have the basics, any of 500 functions are available with a simple key-stroke. The on-screen help and extensive tutorial windows are like having a manual on disk.

There may be only two methods left for writing: a no. 2 pencil or the power of Electric Pencil PC. You'll be impressed with this full-featured wordprocessing system at a revolutionary price . . . we guarantee it!

• Supports DOS 2.0 (or higher) directory structure • On screen underlining & bold with monochrome (colors on color monitor) · Set screen, text, underlined, bold & marker colors · All Definable function keys . All "wordprocessing keys" are used . Designed especially for the IBM PC & compatibles . Definable screen width • Embedded printer control commands • Automatic character translation • Repeat function • Chain disk files when printing • Append files in memory • Include files from disk within text • Verify option with load & exit . Centering . Conditional paging and page numbering . Remark command in text . Print any part of text or range of pages • Over 80 individual on line help windows • DOS or expanded keyboard buffer • Toggle between main/alternate text files • optional ASCII file save/load • Parallel & serial drivers (RS-232) • "Pause" command in text • Single word spell check • Customize dictionary • Auto-learn & correct misspellings • Build "specific" dictionaries • Auto hyphenation, user defined • Dvorak, French, German & Spanish keyboard drivers . Automatic file backup . Runs on floppy or hard disk . Keyboard macros . Automatic key entry files . Simple 1 or 2 key command structure . Multiple search & replace functions ● User timed auto-file save ● 270 page 2 color manual . Split screens (up to 6) . Right justification . • 3½ in. disk available •

- PRINT PREVIEW TO SCREEN
- FULLY MENU DRIVEN
- ✓ 100,000 WORD DICTIONARY
- EXTENSIVE ON SCREEN TUTORIAL WINDOWS
- NOT COPY PROTECTED
- WORKS WITH ANY PRINTER
- MULTI-LINE HEADERS & FOOTERS
- RE-DEFINE ENTIRE KEYBOARD

WINNER OF THE GOLD MEDAL & PROGRAM OF THE YEAR AWARD, CREATIVE COMPUTING MAGAZINE

MONEY BACK GUARANTEE

Electric Pencil PC is unconditionally guaranteed for 30 days (less shipping). There is a \$10.00 restocking fee if the disk envelope seal is broken.

For Texas Orders or Additional Information Call (214) 234-8466.

Mail in your order today or, for immediate shipment,

1-800-445-9004

\$69.95
Please Add
\$5.00 for
Shipping and
Handling

25,000 Word Medical Dictionary Optional \$19.95

COD's welcome. Please add an additional \$3.00 COD fee. On all foreign orders, shipping cost is assumed by the buyer.

DEALER INQUIRIES WELCOME









ELECTRIC SOFTWARE CORPORATION

9230 MARKVILLE DR. DALLAS, TEXAS 75243

MINIMUM HARDWARE REQUIREMENTS: IBM-PC/XT/AT or compatibles and Tandy 1000/1200, 128K memory, one disk drive, PC-DOS, MS-DOS 2.0 or higher. Color or monochrome monitor.

MS-DOS is a trademark of MicroSoft Corp. IBM and PC-DOS 2.0 are registered trademarks of International Business Machine Corp. Tandy is a registered trademark of The Tandy Corp. Electric Pencil PC, Pencil Tutor and PC Proofreader are registered trademarks of Electric Software Corp. Do you have a new MS-DOS™ computer or PC compatible? And do you have a LOT of data from your TRS-80™ (word processing, spreadsheet, database, etc.) that you'd like to keep using with MS-DOS, without having to re-type? How about BASIC programs you've written that you'd like to keep using? Or DeskMate™ files?

Psst. Over here. You are not alone. We can help you. It's easy with...
TRSCROSSTM 2.0

TRSCROSS runs in your PC or compatible, yet directly reads your double-density TRS-80™ diskettes, so that you may simply copy them over to MS-DOS. Converts while copying. Everything is done in ONE STEP! Easy and fast.

SCRIPSIT™ and SuperSCRIPSIT™ files are NO problem!

Exclusive! TRSCROSS converts SuperSCRIPSIT™ files to ASCII, while copying. This is a tremendous time-saver, as other transfer programs will force you to go back and convert your files before transferring to MS-DOS is even possible.

New Version 2.0 TRSCROSS supports RFT/DCA conversions, leaving special formatting intact!



FOUR STAR review in the 2/87 80-MICRO! Glowing review in the 1/87 COMPUTER SHOPPER!

TRSCROSS now supports copying from high-capacity drives (1.2MB), even more improved BASIC conversion and LS-DOS 6.3 and LDOS 5.3 are fully supported. If you have any questions, please write or call. - Only \$89.95.

We have hundreds of letters/comments on-file complimenting us on the ease of use in transferring files with TRSCROSS. Save yourself LOTS of time and trouble.

TRSCROSS cannot convert machine language (/CMD) - nor can any other conversion product.

SUPER UTILITY/PC™ is another of our products that you might like to have for your MS-DOS computer (combo-special with TRSCROSS at only \$49.95*). It allows you to restore deleted files, modify files or sectors, search for data, change file/directory/volume names and attributes, and more. This powerful utility is not protected, and runs from floppy or hard disk. Supports most PC's and compatibles, including the TANDY 2000. Normally SU/PC™ sells for \$89.95, but if you buy it at the SAME TIME as TRSCROSS*, it's only \$49.95!

Other PC/MS-DOS software we endorse, use, and sell:

Microsoft Word \$325, WordPerfect \$369, MultiMate \$359, Smartcom II \$99, Lotus 1-2-3 \$369, Symphony \$519, Framework II \$519, Multiplan \$139, R:BASE System V \$519, dBASE III + \$519, Reflex \$99, PFS:Prof. File \$179, Turbo Pascal \$69, Microsoft C \$329, QuickBASIC \$69, MS-Windows \$69, COPY II PC \$29, Fastback \$139, SideKick (NCP) \$59, SuperKey \$49, Crosstalk \$139, Managing/Money \$139, DoubleDOS \$39, Disk Optimizer \$39.

Prices subject to change. Call for latest info. Support is by the manufacturer only. Some programs require more than 128KB and more than one drive. Most programs require DOS 2.0 or later, and many products do not support the TANDY 2000. Opened packages cannot be returned. Most orders shipped within 24 working hours. Texas residents must add sales tax. Orders must be prepaid. Visa/MC OK.

Save 25% on most items! FREE UPS ground shipping on orders over \$100! (Otherwise add \$5 ground / \$10 air.)



POWERSOFT

17060 Dallas Parkway, Suite 114 Dallas, TX 75248 • (214) 733-4475 PUBLISHER Peter Hutchinson

EDITOR-IN-CHIEF

EXECUTIVE EDITOR Michael E. Nadeau

MANAGING EDITOR Karen E. Pope SENIOR EDITOR Paula Noonan REVIEW EDITOR Mark Reynolds COPY EDITOR John Kralchnan

TECHNICAL EDITORS Mare-Anne Jarvela Beverly Woodbury

DISK SERIES TECHNICAL EDITOR Keith Johnson

EDITORIAL ADMINISTRATION Whitney Karr ASSOCIATE EDITORS Hardin Brothers

Harry Bee John B. Harrell III David Goben Thomas L. Quindry

ADVERTISING SALES DIRECTOR OF SALES William J. Smith

ACCOUNT MANAGER Brenner K. Fuller 1-800-441-4403

WEST COAST OFFICE Suite #201 3350 W. Bayshone Road Palo Alto, CA 94303 415-328-3470 SALES MANAGER

Peter KJ Montross ACCOUNT MANAGER Diane Fuller

ADVERTISING COORDINATORS Judy Walker Lynn Lagasse

Lynn Lagasse
ADVERTISING SECRETARY

Georgianna Forest
BUSINESS MANAGER
Bradford N. Dixon

MARKETING/PROMOTION DIRECTOR Jane Butterfield



Article submissions from our readers are welcomed and encouraged, inquires should be addressed to: Submissions Editor, 80 Elm Street, Peterborough, NH 03458, include an SASE for a copy of "How to Write for 80 Micro." "TRS-80, Scripait, and TRSDOS are trademarks of Radio

*TRS-80, Scripelt, and TRSDOS are trademarks of Radio Shack, a division of Tandy Corp.

80 Micre (ISSN-0744-7868) is published monthly by CW Communications/Peterborough Inc., 80 Elm St., Peterborough NH, and additional malling offices. Subscription rates in U.S. are \$24.97 for one year, \$38 for two years, and \$53 for three years. In Canada and Mexico \$27.97—one year only, U.S. funds drawn on a U.S. bank. Nationally distributed by international Circulation Distributors. Foreign subscriptions (surface mall), \$44.97—one year only, U.S. funds drawn on a U.S. bank. Foreign subscriptions (air mall) please inquire. In South Africa contact 80 Micro P.O. Box 782815, Sandton, South Africa 2148. All subscription correspondence should be addressed to 80 Micro, Subscription Department, P.O. Box 981 Farmingdale, NY 11737. Please include your address label with any correspondence. Postmaster: Send address changes to 80 Micro, Subscription Services, P.O. Box 981, Farmingdale, NY 11737.

Entire contents ©copyright 1987 by CW Communications/ Peterborough Inc. No part of this publication may be reprinted, or reproduced by any means, without prior written permission from the publisher. All programs are published for personal use only. All rights reserved.

May 1987


80 micro



page 28



page 46



page 58

Features

- 28. Tandy 1000 EX by John D. Wolfskill
 This inexpensive MS-DOS computer is a bird of a different feather.
- **46. Quick Boot** *by Dave Rowell* Wait no longer for the 1000's memory test on a warm reboot.
- 58. Leave the Printing to Spooli by David A. Williams
 Create a buffer that feeds text to your printer while you use your 1000 for other purposes.
- 65. Caught in a Time Stamp by Lionel P. Tercler
 A utility that automatically time-stamps your Model 4 or
 Tandy 1000 Basic programs. (Disk Series)
- 69. A Quick Comparison by James L. Hawes
 Compare any two Model 4 text files on screen simultaneously. (Disk Series)
- 80. Data-Statement Generator by David Goben Convert Model I/III/4 or Tandy 1000 assembly code to Basic Data statements. (Disk Series)
- 84. Strip Your TRSDOS by Lance Wolstrup
 Remove all unprotected files from Model 4 TRSDOS disks
 in one step. (Disk Series)
- 90. Deskmate Printer Control by John Heenan
 Use ASCII characters to place printer control codes within
 Deskmate text.

Departments

- 6. The 80 Micro Disk Series (Load 80)
- 8. Side Tracks by Eric Maloney
- 11. Input
- 12. Feedback Loop by Mercedes Silver
- 19. Pulse Train by David Essex
- 22. Reader Forum
- 28. Reviews
 edited by
 Mark E. Reynolds
 Tandy 1000 EX
 ASP
 ASE
 E1
 The CMOS Expans
 - The CMOS Expansion RAMs The Data Transfer Utility Program
 - TT512P Modem
 A-Plus ETG

- 82. Tidbit #42
- 93. John's MS-DOS Column by John B. Harrell III
- 98. Public Works by Thomas L. Quindry
- 103. The Next Step by Hardin Brothers
- 112. Express Checkouts
 Autodos 2.0
 Omniscroll III/IV
 Moonmist
 Managing for Success
- 115. New Products compiled by Mark E. Reynolds
- 116. How to Use 80 Micro Program Listings
- 124. Fine Lines by Harry Bee

The 80 Micro **Disk Series**

(formerly Load 80)

he 80 Micro Disk Series gathers together selected programs from this issue of 80 Micro and puts them on a magnetic medium for your convenience. It is available on disk and runs on the Models I, III, and 4.

The 80 Micro Disk Series programs are ready to run, and can save you hours of time typing in and debugging listings. The Disk Series also gives you access to assembly-language programs if you don't have an editor/assembler. And it helps you build a substantial software library.

Using the Disk Series is simple. If you own a Model I or III disk system, you boot The 80 Micro Disk Series disk and transfer the files to a TRSDOS system disk according to simple on-screen directions. If you own a Model 4, copy the Model 4 programs from the Series disk to your TRSDOS 6.x disk using the Copy command.

Not all programs will run on your system. Some Model III programs, for instance, will run on the Model 4 in the Model III mode, but not in the Model 4 mode. You should check the system requirements box that accompanies the article to find out what system configuration individual programs require.

If you have any questions about the programs, call Keith Johnson at 603-924-9471. Yearly disk subscriptions to The 80 Micro Disk Series are \$149.95. Individual loaders are available on disk for \$17.95, including postage. To place a subscription order, or to ask questions about your subscription, please call us toll free at 1-800-343-0728 between 9 a.m. and 5 p.m. Or, you can write to The 80 Micro Disk Series, 80 Elm St., Peterborough, NH 03458.

Directory

Time Stamp

Article: Caught in a Time Stamp (p. 65).

System: Model 4, 64K RAM; Models I/III with changes.

Let TRS Stamp time-stamp your Basic programs for future reference.

Language: Basic.

Filespec: TRSSTAMP/BAS.

Quick Comparison

Article: A Quick Comparison (p. 69).

System: Model 4, 64K RAM, TRSDOS 6.2. Pro-Create editor/ assember (optional); Model III, 48K RAM, LDOS 5.x, EDAS editor/assembler (optional).

Compare Plus lets you display two text files simultaneously and compare them line by line. Filespecs: CED/ASM, CED/CMD; CED3/ASM, CED3/CMD.

Easy Conversion

Article: Data-Statement Generator (p. 80).

System: Models I/III/4, 32K RAM.

Use Datapoke to convert assembly code to Basic Data statements with checksums. Language: Basic.

Filespec: DATAPOKE/BAS.

File Removal

Article: Strip Your TRSDOS (p. 84).

System: Model 4, 64K RAM, TRSDOS 6.x, Pro-Create editor/ assembler (optional).

Remove unprotected files from your system disks in one step. Filespecs: REMOV4/ASM, REMOV4/CMD.

Pop-Up Printer Codes

Article: The Next Step (p. 103). System: Model 4, 64K RAM, editor/assembler (Pro-Create 4.3a or MRAS), Pro-Wam.

Use Pro-Wam pop-up utilities to access your printer's special features, such as double-strike mode and changeable fonts. Filespecs: PRSET/ASM, MA-CLIB/ASM.

Checksum

Article: How to Use 80 Micro Program Listings (p. 116). System: Models I/III/4, 32K RAM.

Use our checksum program to check the accuracy of the Basic listings you type in.

Language: Basic.

Filespec: CHECKSUM/BAS.

BAS = Basic, ASM = source code, CMD = object code

ART DIRECTOR Anne Fleming ASSISTANT ART DIRECTOR Robert T. Stave PRODUCTION MANAGER Bruce Hedin AD/GRAPHICS PRODUCTION Maurelle Godoy

DIRECTOR OF CORPORATE PRODUCTION MANUFACTURING MANAGER Susan Gross TYPESETTING MANAGER Linda P. Canale

> PRESIDENT VICE PRESIDENT/FINANCE Roger Murphy DIRECTOR OF OPERATIONS Matt Smith DIRECTOR OF CREDIT SALES AND COLLECTION William M. Boyer EXECUTIVE CREATIVE DIRECTOR Christine Destrempes

CIRCULATION DIRECTOR Frank Smith CIRCULATION MANAGER Bonnie Welsh DIRECT MARKETING MANAGER Paul Ruess SINGLE COPY SALES MANAGER Linda Ruth 1-800-343-0728 AUDITS AND STATISTICS MANAGER Cecile Giguere

SPECIAL PRODUCTS DIRECTOR Jeff DeTray SPECIAL PRODUCTS MANAGER Vivian Mattila

> FOUNDER Wayne Green

Cover sculpture by Phil Geraci Cover photo by Larry Dunn

80 Micro is a member of CW Communications/Inc. group, 80 Micro is a member of CW Communications/inc. group, the world's largest publisher of computer-related information. The gourp publishes over 80 computer publications in more than 28 major countries. Fourteen million people read one or more of the group's publications each month. Members of the CWCI group contribute to the CW international bers of the CWCl group contribute to the CW International News Service offering the latest domestic and international computer news. Members of the group include: ARGENTIN-A'S Computerworld Argentina, PC Mundo; SIAI'S Asian Computerworld; AUSTRIAL'S Computerworld Australia, Communications World, Australian PC World, Australian Macworld; AUSTRIA'S Computerwelf Osternich; BRAZIL'S DataNews, PC Mundo, Micro Mundo; CHILE'S Informatica, Computacion Personal, DENMARK'S Computerworld Den-mark, PC World Denmark FINI AND'S Telepulikh, Milton. mark, PC World Danmark; FINLAND'S Tietoviikko, Mikro; FRANCE'S Le Monde Informatique, Distributique, InfoPC, PC Hebdo,LM Telecom; GREECE'S Micro and Computer Age; HUNGARY'S Computerworld/SZT, Mikrovilag, Tudom any, INDIA'S Dataquest, ISRAEL'S People & Comp Weekly, People & Computers Monthly, ITALY'S Co world Italia; JAPAN'S Computerworld Japan; MEXICO'S Computerworld Mexico, Computundo; THE NETHER-LANDS' Computerworld Netherlands, PC World Netherlands; NEW ZEALAND'S Computerworld New Zealand: NORWAY'S Computerworld Norge, PC World Norge; PEOPLE'S REPUB-LIC OF CHINA'S China Computerworld, China Computer-world Monthly, SAUDI ARBIA'S Arabian Computer News; SOUTH KOREA'S Electronic Times/Computerworld, PC World; SPAIN'S Computerworld Espana, Commodore World, PC World Espana, Communications, Informatica Industria; SWEDEN'S ComputerSweden, Mikrodatorn, PC World; SWITZERLAND'S Computerworld Schweiz; UNITED KING-DOM'S Computer News, DEC Today, ICL Today, PC Busi-ness World, Lotus UK; UNITED STATES' AmigaWorld, Boston Computer News, CD-ROM, Computerworld, Com-puters in Science, Digital News, Federal Computer Week, 8 Micro, FOCUS Publications, inCider, InfoWorld, MacWorld, Micro Marketworld, Network World, PC World, Portable Computer Review, Publish!, PC Resource, RUN; VENEZUELA'S Computerworld Venezuela; WEST GERMANY'S Computer woche, PC Welt, Run, Information Management, PC Woche

Problems with Subscriptions: Send a description of the problem and your current and/or most recent address to: 80 Micro, Subscription Department, P.O. Box 981, Farmingdale, NY 11737.

Problems with Load 80 Circulation: Address correspondence.

NY 11737.

Problems with Load 80 Circulation: Address correspondence to Load 80, 80 Elm St., Peterborough, NH 03458.

Problems with Advertisers: Send a description of the problem and your current address to: 80 Micro, Rt. 101 & Elm Street, Peterborough, NH 03458. If urgent, call 1-800-441-402.

Street, Peterborough, NH 03458. If urgent, call 1-bu-4e: 4403.

Change of Address: Send old label or copy of old address and new address to: 80 Micro, P.O. 80x 981, Farmingdale, NY 11373. Please give eight weeks advance notice.

Microllim: This publication is available in microform from University Microllims International. United States address: 300 North Zeeb Road, Dept. P.R., Ann Arbor, MI 48106. Foreign address: 18 Bedford Row, Dept. P.R., London, WC1R4EJ, England.

Dealers: Contact Elizabeth R. Kehn, Retail Sales Manager, 80 Micro, Elm St., Peterborough, NH 03458. (800) 343-0728.

Named No.1 Choice in Word Processors!

80 MICRO Review, November 1985

Your Need

Your writing is important to you, and it should be. It is an expression of who you are. And how your documents look when they are read is as important as what you have to say.

When you need a word processor that can help you achieve the professional and sophisticated look that you want in your writing, two things are most important: 1.) The ability to present your ideas on paper in a sharp, crisp, and attractive manner, and 2.) The ability to accomplish this quickly.

The #1 Solution

LeScript has the power to handle all your most complex writing assignments with the ease and simplicity you never dreamed possible in an advanced word processing product.

Advanced Features

LeScript's features include Automatic Page Makeup, Automatic Multiple Columns, Automatic Form-Letter Mail-Merge, Automatic Footnotes, Automatic Outline Indenting, Automatic Key-Word Search Disk File Directories, Programmable Macro Keys, Proportional Printing, ability to change Font Styles and Sizes, Foreign Language Character support, over 250 Printers supported, Tandy 1000/2000 Keyboard support, and ability to handle files as large as 1 megabyte (with optional memory expansion).

The Professional Look Is Easy

Unlike other advanced software packages, LeScript is one of the easiest you'll ever use. One reason is, LeScript displays your text on the screen the way it is going to look printed - with headers, footers, indents, columns, footnotes, page numbers, line spacing, the works. LeScript even has the incredible ability to show you right on the screen the words that are italic, boldface, underlined.

subscripted. A feature that is so necessary, yet unheard of among the competition.

Also, LeScript's commands are intuitive. They work the way you think, not the way a programmer thinks. There is no faster, more efficient way to generate text files.

Learning Is Easy

The LeScript users manual is written in plain English to help you acquire advanced word processing skills quickly. With LeScript's on-line help screens, self-paced tutorial, quick reference cards, and the many sample files you will have no trouble learning and using LeScript the very first day you have it.

Ordering Is Easy

Call (305) 259-9397, if you are ready to make the move to the #1 rated word processor. We will be happy to answer your technical questions and assist you in placing your order. We take VISA, MasterCard, and C.O.D. orders right over the phone, and ship most orders the same day. Personal and company check orders are shipped after check clears

Name
Address State Zip
City
Tolonhone
Tune of computer
PLEASE RUSH ME:
PLEASE ROST To Demo Disk and Training Guide
Visa/MasterCard # Signature Signature P.O. Box 361136 • Melbourne, FL 32936 (305) 259-9397

Find out why Le Saint was named no. 1, mail this coupon today.

Games That Once Were

You newcomers to Tandy computers might not believe it, but there actually used to be a market for TRS-80 games. That was before low-end computers with color and higher-resolution graphics siphoned off all the game players and relegated the III/4 to a dark street where only serious users dwell.

In the halcyon years—from around 1980 to 1983—80 Micro took its games seriously. Game-playing was part of the staff's daily routine. We even once took a day off for a game decathalon.

The readers were as enthusiastic. Our annual games issue was the most popular of the year. We featured a monthly column called The Gamer's Cafe and were deluged with entries for our one-line game contest.

I stopped playing computer games when the TRS-80 game market went down the tubes. I'm sure my waning interest had something to do with maturity (one of the hazards of growing older). But also, I didn't like the fancier games that ran on the Apple, Commodore, and IBM machines.


Stripped to their essentials, all arcade games are the same. You control a clump of pixels that try to avoid or hit other clumps of pixels. You can call these clumps space ships or swamp monsters. You can make them move faster or slower. You can give the player different rewards for his dexterity. But they're still nothing more than glowing, moving phosphors.

Minimalist Gaming

TRS-80 games were closer to the pure essence of gaming. The machine's graphics weren't good enough to give you anything more than abstract representations of objects. A space ship didn't look like a space ship—it looked like two or three rectangles stuck together. You only knew it was a space ship because the program's author told you so. The rest was up to your imagination.

Games these days come with entire manuals that you have to study before you can play. The best TRS-80 games had one line of on-screen documentation: "Arrows to move, spacebar to fire." After that, you were on your own, learning the game's weaknesses, honing your maneuvering skills, and practicing your shot until you became good enough to make the high-score board.

80 Micro's one-line game contest in



1983 demonstrated the wonderful simplicity of TRS-80 games. In a quarter-K of Basic code, programmers wrote games that had all the elements of a 20K assembly-language program. I still occasionally boot one up. My favorite is a Model III Cram-like game called Snakearound, which you'll find in the Program Listing.

Arcade Archives

Of the 100-plus Model I/III games I collected, my favorite was Big Five's Galaxy Invasion (the original, not the Plus version). GI was typical of so many TRS-80 games. Rows of battleships swooped from the top of the screen and you shot them. There was a time when my sole object in life was to reach 1 million. I finally did it one Saturday afternoon. GI had no pause key, so it took me seven non-stop hours, the game ended in disappointment—at 1 million, the score counter simply started over. No flashing messages, no bonus points, no recognition of the achievement.

I also liked Adventure International's Armored Patrol, certainly one of the most surreal computer games ever made. You were the commander of a tank, the screen serving as your window. Your object was to fight enemy tanks in a flat, barren wasteland rimmed by craggy mountains (it looked a bit like parts of Utah). The landscape was dotted with houses that you couldn't drive or shoot through. Of course, you also had to fight off energy-sucking robots from outer space. And every once in a while something odd would happen, like one of your shots disappearing over the horizon and suddenly whizzing past you from behind.

Armored Patrol was a tough game until a reader notified us of a fatal bug. If you put your tank at a certain spot, the robots would come straight at you and let you mow them down. We leaned a coffee cup on the spacebar and broke the office record by 200,000 points.

Blasts from the Past

Other games that were hits at 80 Micro included Swamp War from Instant Software, Bable Terror from Funsoft, Eliminator from Big Five, and Sea Dragon from Adventure International. We've only added a few to that list in recent years. A Model II game called Wormy caught fire for a while until we ran out of room for the Model II. And Rapidynamic Software put out a cute little Model 4 game called Dog Catcher (Rapidynamic was the only company I know of that produced arcade games for the high-resolution board).

The TRS-80 was as suitable for games as a bus is for drag racing. But then, that was part of the I/III's appeal—making it do something it wasn't supposed to do. Too bad people can't stay satisfied with the simpler things in life; TRS-80 games might be more than just dusty bytes on a shelf.

Program Listing. Snakearound.

- 10 N=128:F=16:X=64:Y=24:CLS:FORT=1TON*N:SET(RND(127),RND(47)):A=(PEEK(14400)AND120)/4:F=-(A=0)*F+A:D=FAND6:C=(FAND24)/4:X=X+C+3*(C>0):Y=Y+D+3*(D>0):X=X+N*((X>N)-(X<0)):Y=Y+48*((Y>47)-(Y<0)):IPPOINT(X,Y)CLS:PRINT"SCORE: "PELSESET(X,Y):P=P+1*NEYT"
- 20 REM SNAKEAROUND BY BILL PETERS
- 25 REM 2470 CAMELBACK ROAD, SALT LAKE CITY, UT 84121
- 30 REM ARROW KEYS TO MOVE--AVOID OBSTACLES AND YOUR TRAIL
- 40 FROM NOVEMBER 1983 80 MICRO

nd

Your family will love your new secretary

Allwrite /
You'll love your

Allwrite Word Processor from Prosoft. It's like having a personal secretary at home and in your growing business, and it saves time, too.

- Reads 10 printed pages from a disk in SIX SECONDS.
- Does a global search-and-replace in under FOUR SECONDS.

Allwrite makes it easy for you to produce top-quality, professional letters and reports. Teachers can use it to generate multiple choice exams and answer keys. (Ask us for free instructions when ordering.) Your kids will write better term papers and reports because Allwrite easily handles footnotes, table of contents, and indexes. That's why your whole family will love Allwrite!

It's the premier word processor for the TRS-80

"Allwrite is a professional system that sets a new standard in word processing. It's powerful and easy to learn and use. . .4-1/2 star rating."—80 Micro, November, 1984.

"With its speed, power, and comprehensive features, Allwrite makes an impressive argument for keeping your TRS-80 instead of buying into the 16-bit marketplace. . .check-rated Best Buy."—Consumer Guide, 1986 Computer Buying Guide.

ALLWRITE helps reduce errors

ALLWRITE quickly flags formatting errors. Its Preview feature shows page breaks and where you forgot to turn off underlining, boldface, etc. It gives you more time to improve the quality of what you want to say.

Superb State-of-the-Art File Handling

- No upper limit on document size chain chapters and disks together.
- Switch between chained files in six seconds, safely!
- Include stock paragraphs when printing.
- Never lose a file! Skips bad sectors reads the rest, shows you where lost text belongs.

Easy to learn, reduces typing time

- Store up to 22 phrases/commands at a time.
- Cue Card templates fits on keyboard.
- Natural English commands: "CE" for "Center", "Search" for "Search".
- 50 on-line HELP screens.
- Includes beginner's tutorials, hundreds of examples.
- Learn Advanced topics only when you need them.

- Comprehensive Index (over 1,000 references).
- Works with all major DOS's on Models I, III, 4, 4P, and 4D

Unmatched customer support

Perhaps the best reason for using Allwrite is the friendly, expert support available from Prosoft. We've supported the TRS-80 since 1980 and have worked with computers since 1962.

HALF-PRICE SALE

\$199.95 \$99.95

(818)764-3131

Circle 30 on Reader Service card.

PROSOFT.

P.O. Box 560 N. Hollywood, CA 91603



How to Order:

Please specify computer (TRS-80 Model I, III, or 4, 48K, at least two disk drives), and your printer(s). The sooner you order, the sooner you will begin to benefit from the ALL-WRITE! Word Processor.

Terms: VISA, MC, checks, C.O.D. Please add \$3.00 shipping in U.S. or Canada. Sales tax in CA. Most orders filled within one day.

LSI DELIVERS

THE NEXT GENERATION OPERATING SYSTEM

FOR YOUR TRS-80 Model 4/4P/4D

FROM THE ORIGINAL AUTHOR OF THE MODEL 4 OPERATING SYSTEM LS-DOS 6.3x

LS-DOS 6.3 is an update to the TRSDOS 6.x operating system for Tandy TRS-80 Model 4 computers. Due to the continuing popularity of the TRS-80 Model 4, this update was deemed necessary to extend the useful life of the computer through the 1990's. At the same time, many other useful features have been added.

- Upward compatible with TRSDOS 6.x versions.
- Expanded date range, 1980 through 1999.
- Files now have a modification Time Stamp as well as a date.
- The directory display shows file dates and times.
- New SVCs for screen print and decimal display.
- All new, easy to use full screen ASCII text editor.
- Conversion program for pre-6.3 version disks adds new time/date information.
- Automatic date/time conversion when copying from TRSDOS 6.x to version 6.3.
- One pass format and disk duplication program.
- Variable and line number cross reference utility for BASIC programs.
- Many "user requested" changes/additions/enhancements have been made.
- Several changes to increase "user friendliness."
- Many enhancements to BASIC:

- including -- Line copy and block move with automatic line reference renumbering.
- Search and display variable, line numbers, and keywords.
- Selective block renumbering.
- High speed load and save.
- Direct access to DOS SVCs.
- List next or previous line(s) with a single key-
- Single letter abbreviations for Auto, Delete, Edit, and List.

TRSDOS 6.2x DATE HANDLING WILL END DEC. 31st, 1987

A documentation update describes all new features and utilities. and contains technical information changes and additions.

Since this is an update to TRSDOS 6.2, all customers are expected to have purchased or received and have in their possession a legitimate copy of the TRSDOS 6.x DOS and documentation.

To provide support only to legitimate owners, all LS-DOS 6.3 master disks contain an individually encoded customer service ID and serial number. This entitles customers to support directly from LSI.

Ordering information:

To save COD, handling and shipping charges, send a check or money order for \$39.95 to:

> Logical Systems, Inc. PO Box 55235 Grand Junction, CO 81505

Credit card and COD orders call: (303) 243-7070

Mastercard and Visa cards are accepted. Credit card and COD orders are \$44.95, including shipping and handling. No COD orders accepted outside the United States. No purchase orders or on account orders will be accepted. Orders will be shipped post paid inside the U.S. Canada and Mexico please add \$5.00 for airmail shipping. All other foreign orders, please add \$10.00 for air postal shipping. All funds must be in U.S. dollars. Allow 2-4 weeks for delivery. LS-DOS is available for American keyboards only. Not available for French or German keyboards.



OGICAL

SYSTEMS

TRS-80 and TRSDOS are Registered Trademarks of Tandy Corporation

The Latest on TRSCross

While we appreciate David Engelhardt's four-star review of our product, TRSCross (February 1987, p. 98), we want to clarify a few points.

Mr. Engelhardt reported that TRSCross does not convert Basic programs accurately. We do not claim 100-percent conversion accuracy. We have, however, improved the accuracy of our later versions of TRSCross, the current version being 1.30.

Mr. Engelhardt also reported that you must convert Superscripsit files to ASCII format before TRSCross will accept them. Although our early advertisements and manuals stated that you had to perform the conversion, we removed the restriction before we introduced the program. TRSCross is, as far as we know, the only program on the market that performs the conversion automatically during a copy.

We found that the additional conversion step that Mr. Engelhardt stated was necessary to convert Model 4 disks is only required with TRSDOS versions older than 6.2.1.

Dennis Brent, President Powersoft Products Dallas, TX

Checking Out Memcheck

I read Mark Goodwin's review of our Memcheck 'utility (February 1987, p. 101) with great interest. I want to correct a few misunderstandings regarding the program.

Mr. Goodwin assumed that a computer's memory is installed by a technician. Many less-qualified people are trying to save money by installing their memory boards themselves and often encounter problems soldering the connections. Memcheck can help these people find the bad connections.

Mr. Goodwin claims that once you correct the connections, you will not have further use for Memcheck. Hardin Brothers pointed out in his review of Supermem (January 1986, p. 35) that moving a computer that has memory upgrades can loosen connections to the main memory board. If this happens, you will be glad to have a diagnostic utility like Memcheck on hand.

I regret that I neglected to note in the



Memcheck documentation that the utility is only compatible with the Alpha Technology Supermem expansion. Mr. Goodwin tested it with a Seatronics upgrade.

We have released a revised version of Memcheck that only supports memories of 256K or more using Alpha Technology's Supermem upgrade. The new version is faster and should correct the problems of the earlier version.

Michael Snyder RSI Software/ Rattan-Snyder Investments Deltona. FL

Stepping Out

Would you consider publishing a compendium of Hardin Brothers' The Next Step column? I am sure that many of your readers refer to the columns as often as I do and would appreciate such a convenience. I would also be grateful for a series of articles (not reviews) on LSDOS 6.3 and LDOS 5.3.

R. Hollenbeck El Paso, TX

We have no plans to compile Hardin's columns, but we do have material on LS-DOS 6.3 and LDOS 5.3 in the works.

80 Micro's BBS is open 24 hours a day. It offers programs you can download, special-interest groups, and a classified section. You can reach the board at 603-924-6985; UART settings are 300/1,200 baud, 8-bit words, 1 stop bit, no parity.

Emulator Boards?

In your Side Tracks column of November 1986 (p. 8), you mentioned that several manufacturers are considering making a Model 4 emulator board for MS-DOS machines. We have over 1,000 Model I/III/4 programs and hope to avoid the task of converting them to MS-DOS. Please keep us posted.

Robert Ledee, Treasurer Orange County TRS-80 Users Group Lake Forest, CA

Warehoused Wonders

In the February 1987 issue, you said that Multidos is no longer available (p. 96). Diskcount Data advertises Multidos on p. 2 of the same issue.

Robert Hales Albion, NY

Thanks for pointing out our mistake.—Eds.

Continued Support

I have renewed my 80 Micro subscription because my Model III is being supported less and less as MS-DOS machines continued to gain popularity. My Model III does what I want, and I see no reason to upgrade.

George Phillips Sun City, AZ

Printer/Typewriters?

I have seen several new typewriters in office equipment and department stores that can be interfaced with computers and used as printers. I have not, however, seen any mention of these machines in 80 Micro. Would you consider publishing an article or series of reviews focused on printer/typewriters?

Gerald Siegfried Reading, PA

Early printer/typewriters were slow and expensive. Perhaps it is time we took a look at what's available now. Thanks for the idea.—Eds.

Send your correspondence to Input, 80 Micro, 80 Elm St., Peterborough, NH 03458. We reserve the right to edit letters.

120 driver. Such a driver does not support separate data- and word-processing modes. Your DMP130/CTL driver is automatically setting up your printer for NLQ each time you select a manuscript task. No Access

Q: I have Scripsit for the Model I, which I have converted to run on my Model III. I can run it on my Model 4 in Model III mode, but I can't get it to print on my Okidata Microline 80. (Delbert Roberts, Mason City, IA)

One of the easiest ways is to use a

printer driver that supports a printer

without NLQ mode, such as the DMP

If you have simply copied Scripsit/ LC from the Model I disk to your Model III disk, the program runs but cannot access the printer ports. You must convert all sequences of 32E837 hexadecimal (hex) to D3F800 hex within the program.

Model I Scripsit sends all data out to its printer-interface address at 37E8 hex, but Model III sends data to the printer via port F8 hex with the command OUT (F8H),A.

Put C9 hex at address 4203 hex to prevent the break vector from crashing the program.

Address Change

Q: I have a copy of the Radio Shack Assembly Language Tutor on tape and am trying to use it with my 48K Model III and four Tandon double-sided disk drives.

The program works fine on tape, and I have successfully converted the first part to disk with TRSDOS 1.3's tape-todisk utility. I cannot, however, copy the rest using either TRSDOS or Basic. The program works in Level II Basic, but it loads as ALTC/CMD in TRSDOS. When I try to run it, it immediately reboots TRSDOS.

I've unsuccessfully tried to load the other parts of the tape into Disk Basic. In TRSDOS, the Tape function starts, but gives me an error 11 (illegal function call). If I try to load ALTC/CMD file from Basic, I get the message "Direct statement in file."

Can I convert this program to disk? I have a hunch that it occupies the same place in memory as TRSDOS. (Ron Folkert, Benton Harbor, MI)

A: It looks like the program operates in the DOS area (4000-41FF hex) or con-

Send your questions or problems dealing with any area of Tandy/Radio Shack microcomputing to Feedback Loop, 80 Micro, 80 Elm St., Peterborough, NH 03458. Please include a selfaddressed, stamped envelope and daytime phone number.

What a Character

Q: How can I use the European characters of my DMP 200 printer with Disk Scripsit on my Model 4P? (Klaus P. Winter, Fort Worth, TX)

The best way to access these characters is to use a word processor that supports extended codes. Both LeScript and Superscripsit support user-defined character codes. Another way is to use Clifford Knight's Scripaid program ("Model 4 Scripsit the Write Way," January 1985, p. 60), with which you can assign control codes to output desired characters on Model 4 Disk Scripsit.

Printer Support


Loading Superscripsit into my Models 4P and 4D somehow eliminates any print-mode commands to my printers (an Okidata 82A and a Gemini 10X). I cannot use the double-width, condensed print, or any other modes on either printer. I contacted the printer manufacturers and the printer-driver company. They all tell me that there is something in Superscripsit that overrides my commands for changes in print mode. Since I use these machines to prepare manuscript materials, this is a serious problem for me. (George Manolakes, Westfield, NJ)

You can alter Dan Robinson's "MX-80 Driver" (May 1983, p. 125) to support the Gemini 10X and 15X printers with changes that Kenneth D. Grimm provided in the April 1984 Reader Exchange (p. 30).

Out of Control

Q: I have Superscripsit 1.01.00. and a DMP 130 printer. Occasionally, when I am typing a document, the program spews a jumble of words onto the screen. Another peculiar thing is that sometimes the printer starts feeding the paper backwards when I try to print a document. Each new line prints above the last.

The printer also seems stuck in elongated print mode when I use Superscripsit. I have the user keys programmed to



change type modes. Clear-shift-1 is the command to change the modes. If I don't use it when I call a document or create a new document, the characters print in elongated mode. (Robert Rowe, Port Charlotte, FL)

Are you using the DMP130/CTL driver with Superscripsit? It is available to registered Superscripsit owners at no charge from Radio Shack (catalog no. 700-2294). If you are, your copy of Scripsit or one of its support modules might be defective. You can go to Radio Shack with your original disks and copy the files from one of the store's disks onto yours to ensure that the software is not the problem. (The latest version is 1.1.3-check Radio Shack's update book if you have an older version.)

You should also run a memory-test program to ensure that you do not have a faulty RAM chip. Memtest/CMD on the TRSDOS 1.3 system disk should do the job. If these methods do not reveal your problem, check your cable connectors for corrosion. Use a pencil eraser to clean the contacts.

Be careful not to accidently hit the control key or type too fast. If you type very fast, the TRSDOS 6.x keyboard driver might interpret a multikey combination as another single-key code or a control sequence. Similar problems arise if you accidently hit control.

Escape from NLQ

Q: I am using Superscripsit with a Model 4P and a DMP 130 printer. I often want to print without using the near-letter-quality (NLQ) mode because it is slow. There is no option in Superscripsit to disable NLQ. Can you tell me how to do it? (W.M. Staudenmaler, Wakarusa,

FOR YOUR

SALE PRICE

VM4 Monitor (1020)



8am Til 6pm Central Time

1-817-481-S.A.L.E

XT A-1 256K-1.D.D. .

AT-8-1 512K-1.D.D. .

XT P-1 256K-1.D.D. . . TAWAN XT A-2 640K-2.D.D. . . .

XT P-3 640K-2.D.D. PRICES

TEXAS RESIDENTS ADD 6.25% SALES TAX. 10 MEG HARD DRIVE(1025) 505.00 1000SX (1051) 699.00 10 MEG BACKUP(1245) 1524.00 20 + 20 MEG BACKUP ...(4066) 2337.00 2000HD (5104) 20 MEG HARD CARD (1029) 565.00 3000HL (4070) 20 MEG H.D. KIT (4062) 3000HD.......2929.00 * ALL UPGRADES AVAILABLE. * MODEL 4D (1070) 843.00 * INSTALLATION AVAILABLE. * **EPSON Printers**

TANDY CM5 Monitor (1023) COMPATIBLE AT-8-3 1 MEG-2.D.D. + 20 MEG H.D. . . 1700.00 CM11 Monitor (1024) . PRICES SUBJECT TO CHANGE WITHOUT NOTICE.—TEXAS RESIDENTS ADD 6.25% SALES TAX

BELTRON

Computers

NOT

"World's CLOSEST* independent authorized computer dealer."

Closest to the Tandy warehouse-means faster, cheaper, safer delivery.

M CHECK OUR

OWEST PRICES

DFW COMPUTER CENTER 326 Main St., Grapevine, TX 76051

FEEDBACK LOOP

tains code within that area. To load it from a DOS disk, you must relocate it to a higher memory address, out of the way of DOS. That way, the program does not overwrite the DOS when it loads. You must append a small subprogram that disables DOS, loads the program down into its operating environment, and executes it as though it had been loaded from tape.

Newdos/80 has a program called LMOffset, and LDOS has one called CMDFile, both of which do those operations for you.

Hung-Up on Fortran

Q: Our high school recently purchased Fortran IV from Radio Shack. I use the TRSDOS 6.2.1 operating system. Logical variables do not seem to work. The computer hangs up, and I can't do anything except reset. Can Fortran sort strings easily and effectively?

When I format my read statement as A4 hex, it sorts on the fourth character (A8 hex sorts on the eighth character). I'm sure the routine is correct. Can I add Set, Reset, and Point to Model 4 Basic? Is there a graphics sheet for the Model 4? (David Meier, Reedsville, WI)

Where are you getting your samples and instructions for logical variables? Most instructional materials and tutorials are geared toward Fortran 77. whereas the Radio Shack (Microsoft) version is an implementation of Fortran IV. Make sure to set up your logical operations to satisfy your compiler's requirements. I have not had problems working with logical operators.

String manipulation in Fortran is possible, though difficult. Fortran was primarily designed to solve complex mathematical equations, not to manipulate text strings. Strings are better handled by such languages as Lisp and Basic.

You can regain Set, Reset, and Point on the Model 4 by using Alan D. Smith's program in "Upgraded Graphics" (August 1985, p. 76). There is a sample graphics sheet in appendix G of the Model 4's Disk Systems Owners Manual for TRSDOS 6.x. Note that you can break each block into six pixels.

Date Update

Q: I use a Model 4D with Deskmate and TRSDOS 6.02.01. I am distressed that the only sign-on dates allowed are from Jan. 1, 1980, to Dec. 31, 1987. Is there a patch to disable the check of validity of the year, even if it means calculating the wrong day of the week? I keep records on Deskmate and am concerned about maintaining my sequence of date references in the directory after 1988 begins. I also write programs in Basic and want

to keep track of my program updates with the directory. (Thomas McClellan, Fort Worth, TX)

A: A new version of TRSDOS, called LS-DOS 6.3, is available from Logical Systems Inc. (LSI), P.O. Box 55235, Grand Junction, CO 81505, for \$29.95. Unfortunately, a patch to TRSDOS 6.2.1 is not enough. To make room for the new dates from Jan. 1, 1988, through Dec. 31, 1999, LSI removed the user password. LS-DOS 6.3 date- and time-stamps files when you create or update them.

Out of Line

Q: I use Superscripsit 1.3.1 on a Model III. If I adjust the margins after opening a file and then print out text that is supposed to be justified left and right, the first line of each paragraph prints ragged right. How can I correct this? (Gideon Oren, Milwaukee, WI)

I duplicated your problem by assigning the pitch setting in the Open Document Options field to a value other than P, such as 10 or 12, which indicates monospace mode rather than proportional spacing. I then made sure that the method of justification in the Print Text Options field was set to P for proportional spacing.

The odd justification in the first line is due to a conflict between the two settings. If your printer can do proportional space printing, then change the opendocument option to P. If it cannot print proportional spaces, then set the printtext option setting to M for monospace printing.

You can set these options to user-defined defaults by going to the systemsetup menu from the main menu when you first enter Scripsit. You must set the print-text option to M if you use the specified-pitch-value setting. The print-text option must be P if you use proportional spacing.

Scripsit Indent

Resetting the paragraph-indentation parameter each time I use Model III Disk Scripsit is boring. What patch sets the default indentation? (Richard Yoder, Redding, CA)

Scripsit sets the paragraph indentation during initialization. The following are patches for the Model I/III/4 versions of Disk Scripsit:

For the Model I running TRSDOS, use the Program Listing. For Model I LDOS, use:

PATCH SCRIPSIT/LC (D = 00,B1 = 00)

For Model III Scripsit, use:

PATCH SCRIPSIT/CMD (ADD = 5373, FIND = 05.CHG = 00)

For Model 4 Scripsit, use:

PATCH SCRIPSIT/CMD (D00,C8 = 00:F00, C8 = 05)

Change the 00 assignment value to any hex value you want from 00-84 (zero-132 decimal).

Incompatible Keys

As a relatively new Tandy 1000 user, I am still learning much about this fine computer. I use many PC-compatible programs that the 1000's keyboard does not seem to fit. Can I use another PC-type keyboard with the 1000? Can I use another PC-compatible mouse with the 1000 instead of Tandy's? (Mike Bean, Fayetteville, AR)

Most keyboards designed for the IBM PC do not work on the Tandy 1000. However, you can temporarily redefine the incompatible keys with the ANSI.SYS extended-screen and keyboard driver. The Tandy 1000 Programmer's Reference Manual (catalog no. 25-1503), appendix A, describes how to do

You can use a PC-compatible mouse driven by the serial port.

Superscripsit System Files

Q: I own a Model III and a Model 4. A few months ago, you listed the functions of all the Model 4 system files (January 1987, p. 70). I found the list very helpful. Please do the same for the Model III Superscripsit files. (Don Johnson, Carson City, NV)

Model III Superscripsit 1.3.x, is almost a reflection of the current Model 4 version. The disk files that Tandy supplies fall into four groups. The first group is the Superscripsit program and its overlays. The second group holds the printer drivers, such as DW2/CTL, DMPxx/CTL, and S/CTL. The third group comprises document files without extensions, such as Demo100, Catalog,

Program Listing. Model I routine to set paragraph indentation for Scripsit running under TRSDOS.

```
10 'Model I Default Indent fix
20 FL$;eq"SCRIPSIT/LC" 'change to SCRIPSIT/UC if needed
30 OPEN"R",1,FL$:FIELD 1,1 AS 177, 1 AS T$
40 GET 1,1
50 LSET T$; eqCHR$(&H00)
```

60 PUT 1.1:CLOSE 1:END

The Amazing A-BUS



An A-BUS system with two Motherboards A-BUS adapter (IBM) in foreground

Plug into the future

With the A-BUS you can plug your PC (IBM, Apple, TRS-80) into a future of exciting new applications in the fields of control, monitoring, automation, sensing, robotics, etc.

Alpha's modular A-BUS offers a proven method to build your "custom" system today. Tomorrow, when you are ready to take another step, you will be able to add more functions. This is ideal for first time experimenting and teaching.

A-BUS control can be entirely done in simple BASIC or Pascal. and no knowledge of electronics is required!

An A-BUS system consists of the A-BUS adapter plugged into your computer and a cable to connect the Adapter to 1 or 2 A-BUS cards. The same cable will also fit an A-BUS Motherboard for expansion up to 25 cards in any combination.

The A-BUS is backed by Alpha's continuing support (our 11th year, 50000 customers in over 60 countries).

The complete set of A-BUS User's Manuals is available for \$10.

About the A-BUS:

BASIC). Card address is jumper selectable.

- All the A-BUS cards are very easy to use with any language that can read or write to a Port or Memory. In BASIC, use INP and OUT (or PEEK and POKE with Apples and Tandy Color Computers)
- They are all compatible with each other. You can mix and match up to 25 cards to fit your application. Card addresses are easily set with jumpers.
- . A-BUS cards are shipped with power supplies (except PD-123) and detailed manuals (including schematics and programming examples).

Relay Card RE-140: \$129 Includes eight industrial relays, (3 amp contacts, SPST) individually controlled and latched. 8 LED's show status. Easy to use (OUT or POKE in

Reed Relay Card Same features as above, but uses 8 Reed Relays to switch low level signals (20mA max). Use as a channel selector, solid state relay driver, etc.

Analog Input Card AD-142: \$129 Eight analog inputs. 0 to +5V range can be expanded to 100V by adding a resistor. 8 bit resolution (20mV). Conversion time 120us. Perfect to measure voltage, temperature, light levels, pressure, etc. Very easy to use.

12 Bit A/D Converter AN-146: \$139 This analog to digital converter is accurate to .025%. Input range is -4V to +4V. Resolution: 1 millivolt. The on board amplifier boosts signals up to 50 times to read microvolts. Conversion time is 130ms. Ideal for thermocouple, strain gauge, etc. 1 channel. (Expand to 8 channels using the RE-156 card).

Digital Input Card The eight inputs are optically isolated, so it's safe and easy to connect any "on/off" devices, such as switches, thermostats, alarm loops, etc. to your computer. To read the eight inputs, simply use BASIC INP (or PEEK).

24 Line TTL I/O Connect 24 input or output signals (switches or any TTL device) to your computer. The card can be set for input, latched output, strobed output, strobed input, and/or bidirectional strobed I/O. Uses the 8255A chip.

Clock with Alarm CL-144: \$89 Powerful clock/calendar with: battery backup for Time, Date and Alarm setting (time and date); built in alarm relay, led and buzzer; timing to 1/100 second. Easy to use decimal format. Lithium battery included

Touch Tone® Decoder Each tone is converted into a number which is stored on the board. Simply read the number with INP or POKE. Use for remote control projects, etc.

A-BUS Prototyping Card PR-152: \$15 31/2 by 41/2 in. with power and ground bus. Fits up to 10 I.C.s











Smart Stepper Controller sc-149: \$299

World's finest stepper controller. On board microprocessor controls 4 motors simultaneously. Incredibly, it accepts plain English commands like 'Move arm 10.2 inches left". Many complex sequences can be defined as "macros" and stored in the on board memory. For each axis, you can control: coordinate (relative or absolute), ramping, speed, step type (half, full, wave), scale factor, units, holding power, etc. Many inputs: 8 limit & "wait until" switches, panic button, etc. On the fly reporting of position, speed, etc. On board drivers (350mA) for small steppers (MO-103). Send for SC-149 flyer. Remote Control Keypad Option RC-121: \$49 To control the 4 motors directly, and "teach" sequences of motions

Power Driver Board Option PD-123: \$89 Boost controller drive to 5 amos per phase. For two motors (eight drivers). **Breakout Board Option** BB-122: \$19

For easy connection of 2 motors. 3 ft. cable ends with screw terminal board. Stepper Motor Driver

Stepper motors are the ultimate in motion control. The special package (below) includes everything you need to get familiar with them. Each card drives two stepper motors (12V, bidirectional, 4 phase, 350mA per phase). Special Package: 2 motors (MO-103) + ST-143: PA-181: \$99

Stepper Motors MO-103: \$15 or 4 for \$39 Pancake type, 21/4" dia, 1/4" shaft, 7.5°/step, 4 phase bidirectional, 300 step/sec, 12V, 36 ohm, bipolar, 5 oz-in torque, same as Airpax K82701-P2.

Current Developments

Intelligent Voice Synthesizer, 14 Bit Analog to Digital converter, 4 Channel Digital to Analog converter, Counter Timer, Voice Recognition.

A-BUS Adapters for:

IBM PC, XT, AT and compatibles. Uses one short slot. Tandy 1000, 1000 EX&SX, 1200, 3000. Uses one short slot. AR-133...\$69 AR-133...\$69 Apple II, II+, IIe. Uses any slot. AR-134_\$49 TRS-80 Model 102, 200 Plugs into 40 pin "system bus". AR-136...\$69 Model 100. Uses 40 pin socket. (Socket is duplicated on adapter). AR-135...\$69 TRS-80 Mod 3,4,4 D. Fits 50 pin bus. (With hard disk, use Y-cable). AR-132...\$49 TRS-80 Model 4P. Includes extra cable. (50 pin bus is recessed). AR-137...\$62 AR-131...\$39 TRS-80 Model 1. Plugs into 40 pin 1/0 bus on KB or E/I. Color Computers (Tandy). Fits ROM slot, Multipak, or Y-cable AR-138..\$49

A-BUS Cable (3 ft, 50 cond.) CA-163: \$24 Connects the A-BUS adapter to one A-BUS card or to first Motherboard. Special cable for two A-BUS cards: CA-162: \$34

A-BUS Motherboard MB-120: \$99 Each Motherboard holds five A-BUS cards. A sixth connector allows a second Motherboard to be added to the first (with connecting cable CA-161: \$12). Up to five Motherboards can be joined this way to a single A-BUS adapter. Sturdy aluminum frame and card guides included.

Add \$3.00 per order for shipping. Visa, MC, checks, M.O. welcome. NY and CT: add sales tax. C.O.D. add \$3.00 extra.



(203) 656-1806 Orders only 800 221-0916 (718) 296-5916 New York orders: All lines open weekdays 9 to 5 Eastern time

FEEDBACK LOOP

and Lectures. The fourth group holds system support programs, such as the Install/BLD and Harddisk/JCL files, which configure the optional Superscripsit Dictionary disk and set up the system for operation on a hard disk.

The program core is Scripsit/CMD and its overlays. These fall into three groups: word processing, spelling checking, and word-processing system configuration. They are as follows.

- Scripsit/CMD: Remains resident at all times but reloads after you use the spelling checker, which overwrites parts of it.
- System/CTL: Stores the default and user-defined configuration formats, such as tab lines, user-defined keys, and custom printer codes.
- Help/CTL: Provides the on-line help option for the control keys. You can remove it.
- Errors/CTL: Displays Scripsit errors.
 This is a text file. The system won't crash without it, but errors will appear as incomprehensible garbage on the status line.
- Proof/CTL: A major portion of the spelling checker. You can remove it if you do not use the Scripsit Dictionary.
- Words/CTL: Stores user-defined words. Remove it if you remove Proof/ CTL.
- SCR16/CTL: Handles headers, footers, tab settings, and block controls.
- SCR17/CTL: Displays the main menu and executes the other modules that support Scripsit. It also contains the directory-read function.
- SCR18/CTL: Handles file-format structuring.
- SCR19/CTL: Like SCR18/CTL, but also handles queries and compares. This and SCR18/CTL are the system's workhorses.
- SCR32/CTL: Handles block action commands.
- SCR33/CTL: Handles the global-find, delete, and replace commands. Contains the search and replace portions of the proofreading program.
- SCR34/CTL: Controls the ASCII conversion and compression utilities. You can remove it.
- SCR35/CTL: Displays the system setup menu and handles the verify-deletion function and the text-mode user-key-storage option.
- SCR36/CTL: Controls the rest of the system-setup functions, such as user-defined-key editing, printer codes, alignment, and character setting.
- SCR50/CTL: Support program for the proofreader. You can remove it.

Requesting Backup

Q: I have a Model 4 with a hard disk. How can I back up the hard disk to floppies? (Darrell A. Sherrin, Kelowna, BC)

A: The Radio Shack Hard Disk Utilities has a back-up feature. Also, Powersoft (17060 Dallas Parkway, Suite 114, Dallas, TX 75248, 214-733-4475) has a back-up program (Backrest, \$99.95) that is more flexible and faster. If you just need to back up a few data files, use the TRSDOS Backup command.

More Superscripsit Tips

Q: I am using Superscripsit 1.00.01 with TRSDOS 6.01 on a Model 4 and have access to three printers: the DMP 420, 120, and 105.

My first question concerns using the block-action print command in a multipage document. Due to poor typing and screen proofreading, I frequently find an error in a document after I have printed it, and, invariably, the error is on page 2, 3, and so on. I correct the error, block the page, press B for block-action, P for print, and enter when the print options appear, and the page is printed. The problem is that the printer feeds blank pages until it gets to the blocked page—a waste of paper. Is there a way to prevent this?

My second question concerns using the underline command with the superscript and subscript commands. I teach algebra and prepare my tests with Superscripsit. If I don't stop the underline before issuing the superscript command, the underline appears under the exponent. If I stop the underline before the superscript command and begin it again after subscript, I get a blank space in the underline. How can I continue the underline without the break? (Dick Breaktron, Myrtle Beach, SC)

A: Superscripsit 1.01.00 is an upgrade of 1.00.01 that fixes the page-feed problem. You should have been notified of a free upgrade by Tandy if you sent in the Superscripsit registration card. If they missed you, consult your local Radio Shack computer dealer.

The fastest solution to your second problem is to set up a special printer code. From the initial Superscripsit menu, select S (system-setup utility) and from that menu select C to enter printer codes.

Assume you want to use the numeral 9 as the special indicator. Use the down-arrow key to align yourself with the first space of the units column after "9," type zero, and press the down arrow once to get to the sequence column. Type 27,28.8, 95,27,30. Press the down arrow again, type BACKLINE, press the enter key twice, then press the break key. You are now back at the main menu.

Whenever you type a document, after each superscripted character under which you want to print the line, press the clear key (producing a copyright symbol) followed by the 9 key.

The 27,28 sequence performs a half-line feed, 8,95 backs up the printer head and types an underscore character, and 27,30 performs a reverse half-line feed, returning you to your previous position. Check the printer manual for the proper codes.

Readers Respond

Thomas R.W. Longstaff (Waterville, ME) offers a fix for the extra line feeds that printers configured for use with older Tandy computers insert when used with PCs and newer Tandy machines. As Mr. Longstaff explains, the line feeds occur because Tandy computers and software expected printers to supply a line feed with each carriage return. His fix is for the Radio Shack Line Printer VI.

"To disable the unwanted extra line feed, I use the following technique:

- Unplug the printer and remove the knob at the right end of the platen (do this by removing the small screw in the center of the knob and gently sliding the knob off).
- Remove the tractor feed, paper bail, cover, and the gray case that encloses the mechanism (do this by removing seven screws, two at each side, two at the back and one inside the printer cabinet at the front center, and lifting off the case)
- Find the small block with four DIP switches at the back of the mechanism where the printer cable connects. The second switch controls line feeds. When the switch is open, the printer generates a line feed with each carriage return. Close the switch to disable the line feed.
- Reassemble the printer. You must reactivate the line feed to use the printer for graphics."


Seeking Help

- ► Michael D. Scheehle (19 Oak Meadow Court, Charlotte, NC 28210) is looking for the PFS:File program for the Model III. Radio Shack is unable to supply it and Software Publishing Corp. no longer supports the PFS series for the Model III.
- ► Wilson Fletcher (4117 Bird Drive, Erie, PA 16510) is looking for a Model 4P Modem Board (catalog no. 26-1084). Radio Shack has discontinued it.
- ▶ Julius Gianakos (P.O. Box 993, Peoria, IL 61601) is looking for instructions on how to add his Shugart 801 drives (8 inch) to his Model I with a double-density controller, LDOS 5.1, and 5 1/4-inch drives.
- ►S. Goldhor (1014 B St., Hayward, CA 94541) is looking for a schematic of the Holmes disk-controller board for the Model III. He needs information on setting the board's DIP switches.

Tandy Is Dandy

. . Until You Want More Memory!

USER INSTALLABLE BOARDS FOR TANDY 1000/3000



MEMORY EXPANSION

Model 1000 provides DMA and additional 256K or memory bringing your 128K Tandy 1000 to 384K or 640K. Clock calendar with 20 year battery is optional.

2002 256K-\$109

2003 512K-\$149

Free clock \$49 value with any memory expansion or multifunction card.

Model 1000EX speeds up computer by adding DMA and an additional 256K or 384K of memory, bringing your 256K Tandy 1000EX to 512 or 640K.

Clock calendar with 20 year battery is optional.

2025 256K-\$99


2026 348K-\$119

Model 1000SX additional 256K of memory bringing your 384K Tandy 1000SX to 640K. Clock calendar with 20 year battery is optional.

2006 256K-\$129

Model 300HL & HD additional 128K of memory bringing your 512K Tandy 3000HL & HD 640K.

VIDEO PRODUCTS AVAILABLE TOO!







235 Santa Ana Court • Sunnyvale, CA 94086 • (408) 720-1942 • CA (800) 654-2212 • US (800) 222-4920

Dr. Dr. Zucker

ZUCKERBOARD is a registered trademark of Advanced Transducer Devices Inc.



World's Greatest Independent Authorized Computer Dealer

COMPUTER SUPPLY

All Radio Shack **Products**




Radio Shack **Products**

THE SAVING PLACE FOR ALL TANDY® COMPUTERS & PRINTERS

Full Manufacturer's Limited Warranty—Nationwide





- 111	mannininini	
	14945466666644444	Milli -
100		
		B
-		

SAMPLE	PRICES -	CALL	FOR	LATEST
2001		41		1104)

<u> </u>	
(All prices	include freight and insurance, contiguous USA)
EPSON	LX 86 219.00
Printers	FX 86e 389.00
	FX 286e 559.00
	EX 800 459.00
TANDY	1000 EX (25-1050) 458.00
Computers	1000 SX (25-1051) 711.00
	3000 HD (25-4010) 2950.00
	3000 HL (25-4070) 1150.00
	6000 HD (26-6022) 2659.00
TANDY	DMP 130 (26-1280) 252.00
Printers	DMP 430 (26-1277) 498.00
	DWP 230 (28-2812) 294.00

	BELTRON	
4	ADDRESS OF THE STATE OF THE STA	7

	XTP-1 256K, 1 D.D., PRNTR PORT		
Computers	XT A-2 840K, 2 D.D		. 585.00
	AT-8-1 512K, 1 D.D. HD CTRLR .		1211.00

DWP 520 (26-2800) 698.00 DMP 2110₍₂₆₋₂₈₁₀₎ 919.00

(Prices: Subject to change without notice/freight paid)

IBM COMPATIBLE—TAIWAN PRICES—US STANDARDS

TERMS: Payment with Order

NATIONAL COMPUTER SUPPLY, DEPT M, 377 PLAZA, GRANBURY, TX 76048.

TRSDOS's Bittersweet Reality

Tandyland

Poke a dedicated Model I. III. or 4 owner and you'll find a self-reliant individualist who is not given to following fads. When the fad turns into a monolithic standard. however-and who nowadays doesn't know that means IBM compatibles and MS-DOS-you wonder how long even the most stubborn devotee can hold out. Do Tandy's 8-bit machines have any future?

I asked a handful of people closely involved with the TRS-80 hardware and software business for their impressions of the patient's

health. The consensus seems to be that the TRS-80 line looks remarkably well for an old coot who can only do a few things as well as his youthful counterparts, but the retirement home can't be far away.

Missing from most debates about TRS-DOS's fate is an appreciation of its continued usefulness to thousands of satisfied customers. Bill Schroeder, president of Colorado-based Logical Systems Inc., the original developer of TRSDOS 6.x, said businesspeople and the media are so eager to jump on the latest bandwagon that they tend to dismiss older technology long before the public is ready to give up on it. "We are guilty of trying to prod them into a new computer when they don't need one," Schroeder said, later adding, "The users have a lot less gloomy picture of their situation than we try to paint for them."

It's hard to know how many people actively use TRS-80s. Recent figures from International Data Corp., a market-research firm, estimate the installed base of the Model 4, 4P, and 4D alone to be 325,000 worldwide. Tandy still sells somewhere between 500 and 4,000 Model 4Ds a month.



Even when it was introduced in 1983, the Model 4 was seen as a last gasp for the TRS-80 line.

The handful of remaining software firms continue to sell enough TRSDOS software to avoid having to drop it for a total commitment to MS-DOS. Roy Soltoff, president of Misosys Inc. in Sterling, VA, said he sold 600 units of TRSDOS 6compatible LDOS 5.3 between Jan. 5 and mid-February, and he expects to sell 5,000 by the middle of next year. In February, Soltoff released eight utility programs, some of them repackaged products acquired from Logical Systems in a marketing deal. Sales of Schroeder's LS-DOS 6.3, which Tandy supports through letters to registered Model 4 owners, could reach 100,000 units by fall 1988, and Schroeder might release upgrades of existing utilities if the demand warrants.

User's groups and Compuserve's TRS-80 special-interest group (SIG) remain active.

According to Wayne Day, a sysop (system operator) for the SIG, "In general, I'd say that there's a very active and dedicated core of folks that are still using the TRSDOS machines, but some of them seem to be leaning towards the MS-DOS world."

In addition, TRS-80 users continue to represent the largest proportion of 80 Mt-

cro readers. In a reader survey last year, the Models I, III, and 4 filled three of the top four positions in a ranking of computer ownership. The users are out there, but they are getting increasingly worried whether any company—including Tandy—will support them.

For their part, Tandy officials insist they plan to provide service to TRS-80 owners indefinitely. Spokesperson Fran McGehee said Tandy will keep the Model 4D "in the line" but has no plans to introduce any new hardware or software. She emphat-

ically denied rumors that the company has plans to introduce a Model 4 upgrade.

The \$1,199 price tag on the Model 4D has some people wondering about Tandy's commitment to this machine in a time when many IBM compatibles are selling for hundreds of dollars less. (Tandy's own successful clone, the 1000 SX, is priced at \$999 without a monitor.) "How are they going to sell it?" Soltoff asked, adding that the remaining Model 4 business may consist mostly of residual sales to schools and businesses that already own several of the machines. Schroeder said, "The Model 4D should be \$699-\$799. You practically have to hog-tie the salesmen to get them to sell you one."

In a rare interview last July, Tandy Chairman John Roach shared his thoughts on the TRS-80 line with Jan Lewis in the Computer Insider newsletter. When Lewis asked why Roach referred to TRS-80 in the past tense, he replied, "Well, we continue to sell those kinds of machines, but there will be a minimum of new products offered in those lines. Our primary thrust is in the PC-compatible, MS-DOS world."

Where does that leave users? With perfectly utilitarian machines they can probably have fixed at Radio Shack, and for which practically no new software will be written in 1987 and beyond.

Schroeder has a formula he uses to gauge the health of the TRS-80 market, which today essentially involves only the Model 4. With a minimum of 250,000 computers in active use, a secondary market tends to support itself through magazines, mail-order retailing, and advertising. If a few more of those 250,000 end up in closets, however, the "critical mass" is lost and the secondary market dies.

Schroeder said he fears the Model 4 may slide past the point of no return this year, but he still wants to focus on its good points, "You can buy a used one dirt cheap, there is good existing software that is cheaper than IBM software, and it contains good, refined hardware. There are many strong points."

Dennis Brent, president of Dallasbased Powersoft, agreed with Schroeder's grim prediction for 1987, saying this is probably the last year for TRS-80 software developers to introduce new products. But, he said, "We're not jumping into MS-DOS with both feet. . . The Model III/4 is an excellent computer. . . We're still going to be here, and we will support you."

In a cost-cutting move, Tandy began converting 106 of its 490 Radio Shack Computer Centers (RSCCs) to Plus Computer Centers starting Feb. 1. The new Plus Centers will still carry the full line of Tandy computers but will not have training or repair service. Tandy will transfer "outbound" salespeople working with business accounts to nearby RSCCs.

Ed Juge, Tandy's director of market planning, said the need for business-oriented stores has diminished with the growth of the outbound sales force, now estimated at 1,900 nationally. "We expect the net result of these changes to be improved coverage for walk-in customers," Juge said. "Customers served by the outbound sales organization should notice no difference. Conversion should also result in cost savings to Radio Shack."

Tandy closed down 24 stores completely and established Plus Centers in nearby Radio Shack retail stores but had no plans to lay off employees, according to another spokesperson.

If sheer quantity is what impresses you, consider that in 1986 Tandy spent an estimated \$8.7 million on print advertising alone, compared with \$4 million the previous year. Now consider that Tandy's budget is dwarfed by others in

a list of 8,950 hightech advertisers topped by AT&T, which spent \$60 million on 3,556 pages of advertising in 92 publications last year. And I haven't mentioned television and radio.

The latest semiannual HiTAP (High Tech Ad Placement) report from C Systems Ltd. of Ridgefield, CT, shows that Tandy placed more ad pages in 80 Micro than in any other publication. One hundred forty-two Tandy pages costing an estimated

\$592,000 appeared here; in second place was Rainbow, with 42 pages worth \$88,000. Page counts don't tell the whole story, however. In dollars, a page in 80 Micro is to a page in Business Week what a used, low-mileage Honda is to a shiny, new BMW. Business Week was thus the chief beneficiary of Tandy's promotional urges, carrying 30 pages worth an estimated \$1.18 million. The Wall Street Journal followed, with 29 pages at \$986,600.

The total number of pages taken out by the companies included in the HiTAP report was down about 9,000 from the previous year's total of 160,000. Expenditures, however, rose about 6.6 percent to \$1.28 billion.

Tandy's 595 pages in 48 publications may seem piddling next to those of AT&T or second-place IBM, which ran 2,173 pages worth \$44 million in more than 70 periodicals. Xerox, Hewlett-Packard, and Compaq all spent more than Tandy. But \$8.7 million is more than many companies take in all year, giving us an idea of just how big the big players are. (Tandy said that its advertising expenditures for fiscal 1986, including print, television, radio, and catalogs, totaled \$221.2 million.)

Update

A May 1984 Pulse Train report rhetorically asked whether 3½-inch floppy disks would someday replace 5½-inch disks as the standard storage medium for microcomputers. Now, after three years of technology's inexorable march comes the answer: probably.

Disk/Trend Inc., a Los Angeles based



According to predictions, microfloppies will become standard replacing the 5½-inch disks by 1989.

market-research firm, predicts so-called microfloppies will become standard by 1989. Quoted in *Infoworld*, Disk/Trend Vice President Robert Katzive said IBM will lead the trend this year by putting smaller drives in its long-awaited "clone-buster" PCs. Meanwhile, disk and drive developers will introduce products offering several megabytes (MB) of storage—on disks of both sizes—for use with higher-powered machines.

Projected 1986 sales of 3½-inch drives were up 71 percent over the 3.3 million units sold the year before. The number could rise to 14 million units by 1989, according to Disk/Trend. Already, microfloppies account for 26 percent of the floppy-disk market. What are the benefits?

For one, smaller drives are helpful in producing "small-footprint" PCs designed to economize on desk space. Metal sleeves protect the disks themselves, reducing the likelihood of data loss. And there are substantial gains in storage capacity.

Toshiba America Inc. of Tustin, CA, has begun showing a prototype of a 4MB microfloppy drive to original-equipment manufacturers (OEMs), according to *Infoworld*. The drive could go into production in 1988. Mountain View, CA, based Kao Corp. of America is testing microfloppies that hold up to 7MB.

The technology for 5½-inch disks isn't standing still either. Kao Corp. and several other companies are working on floppies with capacities as high as 50MB, and Konica Technologies Inc. of Sunnyvale, CA, has released a floppy-disk drive that could appeal to current users of low-capacity hard disks.

"When" has now replaced "if" as the operant word.

From Computer Plus to YOU...

PLUS after PLUS after PLUS



Tandy 200 24K \$649 Model 600 32K \$1269 Tandy 102 32K \$395



Tandy 3000 HD \$2499 Tandy 3000 HL \$1229









BIG SAVINGS ON A FULL COMPLEMENT OF RADIO SHACK COMPUTER PRODUCTS

COMPUTERS		TANDY 1000 ACCESSORIES		**COMPUTER PLUS SPECIALS**
Tandy 1000 EX 1 Drive 256K	479.00	Tandy 1000 Disk Drive Kit	159.00	The PBJ MFB-1000 Multi-Function Board with
Tandy 1000 SX 2 Drive 384K	759.00	Tandy 1000 EX External Drive	199.00	512 Ram, DMA, RS-232 Serial Port, Clock
Tandy 3000 HL 1 Drive 512K	1229.00	Tandy 1000 20 Meg. Hard Card	649.00	Calendar with Battery Backup, and Ram
Tandy 3000 1 Drive 512K	1599.00	256K Memory Plus Expansion Brd.	179.00	Disk Software
	3179.00			
Model IVD 64K w/Deskmate	889.00	PBJ Multi-Function Board (512K)	229.00	The PJB XRAM Expanded Memory Board
		PBJ Mini I/O (RS-232, Clock, Par.)	99.00	with 256K Ram, Upgradable to 2 Mega-
PRINTERS		128K Ram Upgrade Kit (NEC)	78.00	bytes of Additional Memory, EMS Com-
Radio Shack DMP-130 100 CPS	269.00	256K Ram Upgrade (for 1000SX)	69.00	patable, with Ram Disk Software 249.00
Radio Shack DMP-430 180 CPS	559.00	Summa RS-232 Serial Mouse	99.00	
Radio Shack DWP-230 Daisy Whee	310.00	1200 Baud Modem Board	179.00	Tandy 1000 20 Megabyte Internal Hard
Silver Reed EXP-550P Daisy Wheel	339.00	Plus 300 Baud Modem Board	85.00	Drive Kit with Controller, Cables and
Star LV-1210 120 CPS	199.00	Plus RS-232 Serial Board	69.00	Mounting Hardware 499.00
Star NX-10 120 CPS	249.00	Digi-Mouse/Clock Board	89.00	
Star SG-15 CPS	410.00			Tandy 1000 20 Megabyte External Hard
Panasonic P-1080i 120 CPS	239.00	TANDY MONITORS		Drive with Controller, Cables, Case and
Panasonic P-1091i 160 CPS	299.00	Tandy VM-4 Green Monitor	99.00	Power Supply
Panasonic P-1092 180 CPS	339.00	Tandy CM-10 RGB Color Monitor	379.00	
Okidata 292 200 CPS	559.00	Tandy CM-5 RGB Color Monitor	249.00	
Okidata 192 200 CPS	365.00	Tandy VM-3 TTL Green Monitor	179.00	
Okidata 182 120 CPS	269.00	Tandy CM-8 Analog Color Monitor	249.00	
Epson LX-80 100 CPS	275.00	Tandy 1200 Deluxe Display Adapt.	229.00	
Epson FX-80 160 CPS	419.00	Tandy 1200 Dual Display Adapt.	210.00	
The state of the s				

CALL TOLL FREE 1-800-343-8124

- LOWEST POSSIBLE PRICES
- BEST POSSIBLE WARRANTY
- KNOWLEDGEABLE SALES STAFF
- TIMELY DELIVERY
- SHOPPING CONVENIENCE







P.O. Box 1094 **480 King Street** Littleton, MA 01460

IN MASSACHUSETTS CALL (617) 486-3193

Got a hot tip you'd like to share with our readers? Send it to Reader Forum. c/o 80 Micro, 80 Elm St., Peterborough, NH 03458. We pay \$10 for each tip we use. Sorry, but we cannot return or acknowledge Reader Forum submissions.

Recovering "Lost" **Memdisk Files**

If you accidentally press reset and wipe out your Memdisk, you haven't really lost the files there. Just repeat the Memdisk initialization:

SYSTEM (DRIVE = n, DRIVER = "MEMDISK")

Do not, however, format the Memdisk. A directory of the Memdisk drive should show that all your files are still there. Mark Hershberger

Using Shell18/CMD with LS-DOS 6.3

The public-domain, Model 4 DOS shell program, Shell18/CMD, doesn't work with LS-DOS 6.3. Attempts to execute it result in the message, "TRSDOS 6.2 is required for this program."

A simple POKE 133,98 from Basic cures the problem. This Poke might work with other programs incompatible with LS-DOS 6.3.

> **Bob Littlepage** Hattlesburg, MS



Newdos to MS-DOS Via Supercross

Powersoft's Supercross/ XT III utility will not convert Model III Newdos/80 MU-type sequential files to MS-DOS format. According to Powersoft, Supercross/XT III only supports files created by TRSDOS 1.3's Open "I" statement and containing ASCII characters with each line ending in a carriage return. It moves that data to an MS-DOS disk and adds a line feed after the carriage return.

I did get around the problem, however. I changed one of my Newdos/80 file-maintenance programs so that it read the files into memory using its normal Disk Basic input/output (I/O) instructions and then wrote it back to disk using TRSDOS's Disk Basic sequential I/O instructions.

First, I replaced: OPEN "O",1,"filespec","MU" with:

OPEN "O",1,"filespec"

Then I replaced:

PUT 1,..A!(I),A\$(I),B\$(I),C\$(I),D\$;

PRINT#1,A!(I),K\$,A\$(I),K\$,B\$(I), K\$,C\$(I),K\$,D\$(I)

You must also include the statement K\$ = "," to serve as delimiters

After I converted and transferred the original Newdos/80 programs that created and maintained the sequential files. I replaced the Put and Print# statements with Write# statements to automatically insert the delimiters.

> Mark Morris Pueblo, CO

Update: Loose-Leaf Listings

I've made some enhancements to Kenneth Frith's program (Reader Forum, February 1987, p. 25) that prints out listings for placement in loose-leaf binders. My version (Program Listing 1) pages past perforations, stops for single-sheet use, and lets you use different printers and operating systems.

Line 130 lets you indent the left margin to allow

enough space for you to punch holes. Line 140 prompts for the type of paper you are using. If you use single sheets, the printer stops and waits for you to change the paper.

Line 150 sets the variable values for the indent and the number of dashes in the header and footer. It also places the date at the right of the header line.

By changing the date format in line 180, the program will work with any Model III or 4 operating system. For the Model III use:

LEFT\$(TIME\$,8)

For the Model 4 use:

DATES

Line 180 also puts the date on page 1 only. Line 350 halts the printer when using single sheets. Line 410 skips perforations when using tractorfeed paper and advances to the top of form when finished printing.

Important variables are F, the number of dashes for the header and footer; P, the date placement; and ID, the number of spaces to indent the left margin.

> M.H. Brigas Walla Walla, WA

Program Listing 1. Utility to print out Basic listings for storage in loose-leaf binders. See p. 116 for information on using the checksums.

100	' Model III/IV version Up-grade of Kenneth		
	M. Frith Basic Program Lister,		
110	by M.H. Briggs		
110	CLEAR 300:CLS:O=1:DEFINT I-L 'CLEAR only		1973
120	for Model III		19/-
120	PRINT" BASIC PROGRAM LISTER WITH HEADER AN	1+	5028
120	D FOOTER, PAGE NUMBERS": PRINT	-	3020
130	PRINT" Enter Left Margin Indent (ENTER=0)" :PRINT:INPUT ID:F=80:PRINT	1.	5332
140			3332
140	PRINT" Tractor Feed Pages, or Single Sheet Feed (T/S) (ENTER=T)";:PRINT:INPUT H\$:PRI		
	NT	1.4	6763
	F=F-ID:P=79 'Limits number of dashes for u		0,00
130	nderline and date placement	1.6	886
160	PRINT" Enter Program Filename (ASCII only)		00.
100	":PRINT:INPUT FIS	14	4895
179	OPEN"I", 1, FIS	1+	947
	IF O>1 THEN LPRINT TAB(ID) "Program: "FIS T		
200	AB (P-LEN(FIS)) ELSE LPRINT TAB (ID) "Program		
	: "FIS TAB (P-LEN(FIS)) LEFTS (TIMES, 8)	1*	8051
198	LPRINT TAB(ID) STRING\$(F, "="):LPRINT	1#	2522
	IF IS="" THEN LINE INPUT #1, IS	1 *	1956
	IF LEN(I\$) <=F THEN J=LEN(I\$) ELSE J=F	1#	2446

230	K=0:0=2 'O allows date printing on page			
	one only	1*	613	
240	FOR I=1 TO J	1 *	929	
250	IF ASC(MID\$(I\$,I,1))=10 THEN J=I:K=1:GOTO			
	270: NEXT	1 *	3217	
278	JS=LEFT\$(I\$,J-K):I\$=RIGHT\$(I\$,LEN(I\$)-J):L			
	=L+1	1 *	2894	
300	LPRINT TAB(ID)J\$	1#	1231	
320	IF EOF(1) THEN FOR I=L+1 TO 50:LPRINT:NEXT			
	:GOTO 348	1 *	3426	
330	IF L<50 THEN 210	1 *	1108	
340	LPRINT:LPRINT '2 lines before page number	1 *	1187	
	LPRINT TAB(ID) STRINGS(F, "="):PG=PG+1	14	2502	
	LPRINT TAB(ID) TAB(36) "PAGE - " USING "##			
	": PG:LPRINT CHR\$(12)	14	3857	-
390	IF HS="" OR HS="T" THEN 410 ELSE PRINT "Pr			
1	ess ENTER when ready ";	1 *	4581	
400	IS=INKEYS:IF IS="" THEN 400	14	1756	
	FOR X=0 TO 7:LPRINT: NEXT'Skip perforation	14	1831	
	L=0:IF NOT EOF(1) THEN 188	1#	1741	
	PRINT "Press (ENTER) to run another listin			
	q, (BREAK) to quit."	1#	5296	
450	INPUT QS:IF QS="" THEN RUN	14	1825	
-	The second secon			End

Program Listing 2. Hash-code-generating routine for the Models I/III/4 (in III mode).

1150	; FOR MO		7000H	(IN MOD III MODE)
		DI		
160	om s pm	CALL	CLS	
170	START	CALL	HL,MSG1 DSPLY	; INP 11 BYTE FILE NAME
90		CALL	SKIP	
200		CALL	INPUT	
10		LD	HL, BUFFER	;FILE NAME & EXTENSION
28		LD	B,11	;11 BYTES TO HASH
30		XOR	A	; ZERO OUT 'A'
	HASH	XOR	(HL)	; MODULO 2 ADDITION
50		INC	HL	; NEXT BYTE TO HASH
60 70		RLCA	ua cu	ROTATE A LEFT THRU CARR
80		DJNZ OR	HASH	; JP HASH TILL 'B' = ZERO : CHECK FOR ZERO HASH COD
90		JR	A NZ, HASH1	; NOT ZERO GOTO HASHI
00		INC	A	; IF ZERO, CORRECT IT
LØ	HASH1	LD	(HASH2),A	; STASH HASH IN BINARY
Ø		CALL	HEX8	CONVERT HASH TO HEX
0		CALL	SKIP	
0		LD	HL, MSG2	; AND DISPLAY HEX VALUE
0		CALL	DSPLY Ø49H	
0		CP	1	; BREAK KEY PRESSED? IF SO
Ø		JP	Z,402DH	GOTO MODEL III DOS READ
90		CALL	SKIP	, 111 000 Numb
0		JP	START	
0	MSG1	DEFM	'Input 11 byte	filename/extension. Use '
0		DEFM	spaces to fil	l if needed. Do not input
10		DEFM	the (/) symbo	1 if used.'
0	MSG2	DEFB	'The hash code	ie i
0		DEFW	o nash code	10
g		DEFM	' Hexadecimal.	
ø		DEFB	0	
90	DSPLY	LD	A, (HL)	
0		CP	Ø	; END MESSAGE DELIMITER
LØ		RET	Z	
20		CALL	Ø33H	; DISPLAY BYTE ON VIDEO
10		INC	HL DSPLY	
	HASH2	JP DEFB	Ø	
	INPUT	LD	A,11	;11 BYTES TO HASH
Ø	111101	LD	(COUNT),A	, 11 bilbb to made
0		LD	HL, BUFFER	
0	INI	CALL	Ø49H	; AWAIT KEYBOARD INPUT
90		CP	32	
10		JP	M, INPUT	
0.0		CP	91	
10		JP	P, INPUT	
0		INC	(HL),A	
Ø		CALL	Ø33H	; DISPLAY BYTE ON VIDEO
Ø		LD	A, (COUNT)	
Ø		DEC	A	
0		RET	Z	;11 BYTES IN = ALL DONE
0		LD	(COUNT),A	20110
ø		JP	INI	
	SKIP	LD	A,13	;TWO VIDEO CARRIAGE RET
0		CALL	033H	
Ø		LD	A, 13	
0		CALL	Ø33H	
0	COUNT	RET DEFB	0	BYTE COUNTER
	CLS	LD	HL,15360	BEGIN VIDEO MEM
90		LD	(16416),HL	; MOD I & III CURSOR
30		LD	DE, 15361	, I I I I COMPON
LØ		LD	BC, 1023	
20		LD	(HL),32	;FILL VIDEO SPACES
30		LDIR		
40	прус	RET	Am .	COMMISSION SALVES
0	HEX8	PUSH	AF ut upv	CONVERT BINARY TO HEX
		LD RRA	HL, HEX	; CONVERTED HEX STASH
0				
0		RRA		
5 Ø 6 Ø 7 Ø 8 Ø		RRA RRA		
60 70 80 90				
60 70 80 90 90		RRA RRA CALL	BINHEX	GENERATE FIRST BYTE
50 70 80 90 10 20		RRA RRA CALL POP	AF	GENERATE SECOND BYTE
30	BINHEX	RRA RRA CALL POP AND	AF ØFH	GENERATE SECOND BYTE AND IMMEDIATE WITH 'A'
9 9 9 9 9 9 9	BINHEX	RRA RRA CALL POP AND ADD	AF	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A'
9 9 9 9 9 9 9 9 9	BINHEX	RRA RRA CALL POP AND ADD DAA	AF ØFH A,9ØH	GENERATE SECOND BYTE AND IMMEDIATE WITH 'A' ADD TO 'A' CONVERT 'A' TO BCD
9 9 9 9 9 9 9 9	BINHEX	RRA RRA CALL POP AND ADD DAA ADC	AF ØFH	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A'
99999999999	BINHEX	RRA RRA CALL POP AND ADD DAA ADC DAA	AF ØFH A,9ØH A,4ØH	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A' ;CONVERT 'A' TO BCD ;ADD IMMED W/CARRY 'A'
000000000000000000000000000000000000000	BINHEX	RRA RRA CALL POP AND ADD DAA ADC DAA LD	AF 0FH A,90H A,40H (HL),A	GENERATE SECOND BYTE AND IMMEDIATE WITH 'A' ADD TO 'A' CONVERT 'A' TO BCD
	BINHEX	RRA RRA CALL POP AND ADD DAA ADC DAA	AF ØFH A,9ØH A,4ØH	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A' ;CONVERT 'A' TO BCD ;ADD IMMED W/CARRY 'A'
	BINHEX	RRA RRA CALL POP AND ADD DAA ADC DAA LD INC	AF 0FH A,90H A,40H (HL),A	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A' ;CONVERT 'A' TO BCD ;ADD IMMED W/CARRY 'A'
999999999999999999999999999999999999999		RRA RRA CALL POP AND ADD DAA ADC DAA LD INC RET	AF 8FH A,98H A,48H (HL),A	;GENERATE SECOND BYTE ;AND IMMEDIATE WITH 'A' ;ADD TO 'A' ;CONVERT 'A' TO BCD ;ADD IMMED W/CARRY 'A' ;STASH HEX VALUE

Slinging Hash

Program Listing 2 is a short assembly-language routine that generates any Model I/III/4 filespec's hash code. It runs on the I, III, and 4 in the III mode, and the hash codes are valid for TRSDOS 2.3, 1.3, and 6.2.

The file names can be up to eight characters long with up to three-character extensions. Do not enter the slash (/) symbol.

To get the hash code for a file, Test/BAS, execute the routine and enter TEST (four spaces) BAS for a total of 11 characters. You must always enter 11 characters with the extension as the last characters. If you use no extension, enter spaces to fill the 11 bytes.

Dick Robertson Chautauqua, NY



The Old Character Switcheroo

The following code switches between the Model 4's space-compression and special characters from Basic:

10 CLS:PRINT CHR\$(200);:IF POS(X)>5 THEN PRINT CHR\$(21);

This line turns on the special characters. Changing the greater-than (>) sign to a less-than (<) sign turns on the space-compression characters.

If clearing the screen is inconvenient at the point where you wish to make the switch, change the CLS to:

PRINT@(L,0),CHR\$(200);

where L is any convenient line on the screen. The semicolon (;) after CHR\$(200) is necessary; otherwise the computer sends a line feed, and POS(X) will always be zero.

> Patrick P. Brown San Francisco, CA

Update: Vitamin E Poke for 4 in III

I've found a way to incorporate Wayne Culbreth's speedup Poke for the Model 4 in III mode (Reader Forum, February 1987, p. 25) in a Do file:

BUILD SPEED/BLD BASIC

.Press enter three times. POKE 16912.200

.Press enter three times. CMD"S" SCRIPSIT

.Press enter once and then break

The additional enter keystrokes are sometimes necessary to give the computer some "breathing" room.

Setting up my example as an autoload file (AUTO DO SPEED/BLD), allows your Model 4 to automatically boot in the program specified, Scripsit in this case. By omitting the program name, the computer returns to DOS in the faster mode.

Robert N.L. Forman Monmouth, IL

Uncompromising performance at an incredible price



The Tandy Color Computer 3

More colors, superb graphics, greater power for only \$21995

Our most powerful Color Computer

Finally, the ideal computer for your family: the most advanced version of our famous Color Computer ever. The Color Computer 3™ (26-3334) is great for popular home and small business applications such as budgets, word processing, graphics, entertainment and more. You get the advantages of a high-priced computer—without the high price!

A rainbow at your fingertips

With an optional CM-8 High-Resolution Color Monitor (26-3215), the Color Computer 3 lets you create razor-sharp charts, graphs, or just-for-fun doodles and sketches with a palette of 64 brilliant colors. The special graphics mode lets you paint 160×192 or 320×192 resolution graphics using 16 colors, or 640×192 resolution with 4 colors.

The Color Computer 3 comes with 128K memory (expandable to 512K), giving you greater programming and data-processing power. And its built-in Extended BASIC programming language features 21 new commands that allow



you to alternate screens, colors, and backgrounds at a higher resolution and in a greater variety of colors than any previous Color Computer.

Compatible and expandable

Best of all, the new Color Computer 3 is compatible with the great software and accessories designed for the Color Computer 2. This means you can choose from a wide selection of personalmanagement, educational and game programs.

It's easy to expand with a printer, telephone modem, and more. Even add a disk drive to turn your Color Computer 3 into the heart of a sophisticated disk sys-

tem. Open the door to a library of advanced disk software.

Come in today!

So when you're looking for a machine that will handle the powerful jobs at a great low price, remember the Color Computer 3. It's your affordable alternative. Come see it today at your nearby Radio Shack.

Circle 75 on Reader Service card.

	RSC-17B Comp	
Mail To: P	Radio Shack, Dept. dy Center, Fort Wo	87-A-1021 rth. TX 76102
Address		
City		
State		
ZIP		



Battle Stations! Battle Stations!

A sure-fire arsenal of more than 50 specially selected subroutines designed to help you—pro or beginner—write better Basic programs for the Models I, III and 4!

Bring your periscope up and focus on NUCLEAR SUBROUTINES, a hot, new collection of the best Model I, III and 4 subroutines ever published in 80 Micro, many never before published on disk!

From scrolling to graphics,...screen handling to sorting, you'll write the smoothest running programs ever, REGARDLESS OF YOUR LEVEL OF SKILL! Here on this atomic-powered "flippy" disk are literally dozens of the neatest subroutines in every size and shape. Some are in Basic, ready for merging with your own programs. Others are in machine language, to be loaded from DOS and called by Basic. Either way, your Basic programs will never be the same again!

Model I & III programs are on one side, and Model 4 programs on the other. Documentation is right on the disk. Just boot up NUCLEAR SUBROUTINES, and you're set for unparalleled programming power! Space is too tight to list them all, but here's a sampling of what awaits you on this once-in-a-lifetime disk, divided into six major categories:

MATHEMATICS

<u>Double Precision</u>—Make your Basic programs more accurate with routines that calculate values with up to 16 significant digits.

<u>Calculator</u>—A two line calculator that gives you the four basic math operations in double precision and exponentiation in single precision.

<u>Random Number Generator</u>—Enter fractions as input, which are converted to decimal values for computation, and output as fractions.

AND MOREL ..

5-87NS

YES! I want to get 8 working on my Model ects! Please send my continuous apparents and the selections.	I, III and Model 4 disk at \$21.45 for	f programming more than 50	proj- subrou-	
tines, specially selected			MC	
☐ Payment enclosed	☐ AMEX	□ Visa	LI IVIC	
Card#		Exp. Date		
Signature				
Name (print)				
Address				
City	Stat	e Zip		
Mail to: LOAD 80 • Elm	St. • Peterborous	gh, NH 03458		

Models I, III, and 4 are registered trademarks of Radio Shack, a division of Tandy Corp.

SCROLL

<u>Horizontal Scroll</u>—Scrolls messages horizontally across the screen. <u>Window Scroll</u>—Reserves a block portion of the screen (the window) in which information can be viewed, moving new information into the window and shuffling the old out.

SCREEN

Screen Border—Draw a border around your screen.

<u>Screen Locator</u>—Use PEEKs and POKEs to locate screen positions when speed is a necessity.

<u>Screen PRINT</u>—Use the arrow keys to move a nondestructive cursor while each PRINT location is displayed.

<u>Screen Dump</u>—Model I/III graphics screen dump program for an Epson MX-80 with Graftrax Plus or an RX-80.

Screen Fill-Fill the screen in assorted ways to create the effect you desire.

Screen Save and Restore—Save and restore the screen contents whenever you wish.

Screen Invert-Reverse the content of your Model I or III screen.

AND MORE...

SORTS

<u>VisiCalc Sort</u>—Sort alpha or numeric data in ascending order, and numeric data in descending order.

Model 4 Sort—A lightening-fast string sort for Model 4 Basic that has the feature of Model III Basic's CMD "O".

PLUS MANY MORE!.

GRAPHICS

<u>Upgraded Graphics</u>—Add the Point, Set and Reset commands to Model 4 Basic.

Better Graphics—Run Model I/III Basic graphics up to eight times faster than normal using the LSET and RSET commands.

AND MANY OTHERS!..

GENERAL USE

Input Routine—A user input routine.

Menu Routine-Add some life to your menus with this routine.

Paint Routine—Draw any shape on your Model I or III screen and fill it in with a touch of the space bar.

Sound-Enhanced sound for the Model 4.

Word Processor—A two line word processor.

PLUS MORE, MORE, MORE!

Complete the coupon or card and mail today.

Or, for immediate service, **CALL TOLL FREE 1-800-258-5471**(in NH, dial 1-924-9471) and charge it to your credit card!

NP-10



- 100 cps draft, 25cps NLQ Friction and push tractor
- 2K buffer
- Parallel interface
- IBM graphics
 Single sheet auto-feed

NX-15

- . 120 cps draft, 30 cps NLQ · Friction and push tractor
- 5K buffer

NX-10

- Parallel interface
- IBM graphics
- · Single sheet auto-feed

ND-10



- 180 cps draft, 45 cps NLQ
- Friction and push tractor
- 12.6K buffer
- · Parallel interface • IBM graphics
- . Single sheet auto-feed

NB24-15

- 216 cps draft, 72 cps NLQ
- 24 wire print head
- · Friction and push tractor
- 5K buffer, expand to 16K Parallel interface

• IBM Graphics

Single sheet auto-feed
 Epson LQ1500 compatible

. 240 cps draft, 60 cps NLQ

Friction and push tractor

 Single sheet auto-feed · Epson FX compatible


12.6K buffer

IBM graphics

Parallel interface

NR-15

Easy front panel operation



- 300 cps draft, 100 cps NLQ
 24 wire print head
- · Friction and push tractor
- 16K buffer, expand to 32K Parallel interface
- IBM graphics
- Single sheet auto-feed
 Epson LQ1500 compatible
 Easy front panel operation

ZEN

MICTONI



MSP-10 MSP-15 MSP-20 MSP-25

PREMIERE 35





- . 120 cps draft, 25 cps NLQ
- Bottom or back feed
- 4K buffer
- IBM graphics
- Epson compatible Tractor included

- . 160 cps draft, 40 cps NLQ 1K buffer, 8K optional
- · Push tractor built-in IBM graphics
- Epson compatible • 18 month warranty
- - IBM graphics

 - 18 month warranty
 - · Push tractor built-in
 - . 200 cps draft, 50 cps NLQ
 - · 8K buffer

 - Epson compatible

- · 35 cps daisy wheel 8K buffer
- Push tractor built-in
- Diablo 630 compatible
- NEC 3550 compatible
- Qume Sprint 11 + compatible
- Diablo Hyplot control codes
- 136 column print width
 Auto push-feed paper loading
- Diablo 630 printwheels
- . LCD display of print functions
- · Dual-bin sheet feeder optional

Add \$10 shipping and handling. Texas residents add State sales tax. No tax collected on shipments delivered outside Texas. 30 day guarantee of satisfaction or your money-back (less shipping and ribbons). No extra charge for American Express, MasterCard or Visa, Your card is not charged until the day we ship your order. Call for instructions prior to returning anything. We maintain a large stock of ribbons, cables, tractors, sheet-feeders, switch boxes, paper and hundreds more.

CALL TOLL FREE 800-527-0347 Customer service call



2544 W. Commerce St. P.O. Box 224767 Dallas, Texas 75222 214-631-7900

(c) 1987 Montezuma Micro. All rights reserved. Prices and specifications subject to change without notice. Citizen and Star are trademarks of their respective companies.







Tandy 1000 EX

by John D. Wolfskill

The Tandy 1000 EX comes with 256K RAM, one disk drive, and three expansion slots. Tandy Corporation, Fort Worth, TX 76102. Catalog no. 25-1050, \$599.

The 1000 EX is one of Tandy's new line of hybrid computers designed to appeal to a wide range of users. Categorizing the EX is not easy. Its built-in keyboard and side-facing disk drive give it the appearance of a home computer. Tipping the scales at a mere 11 pounds and being small enough to tuck under your

arm make it highly transportable.

Toss in a dual-speed 8088 CPU capable of running most PC software and the EX becomes a somewhat PC-compatible machine. Add features like a multivoice sound chip, headset connector, 16-color graphics, and network expansion adapter, and the computer seems a natural for the school and educational market.

Standard features include a slim-line. 54-inch, 360K internal floppy-disk drive; 256K RAM (expandable to 640K); a parallel printer port; dual joystick ports; and a 90-key, full-stroke keyboard with numeric keypad. The EX can drive RGBI, color, or monochrome composite monitors or a standard color-television receiver via an optional radio-frequency modulator. Other features include an internal speaker with adjustable volume control and an %-inch headset connector. A rear-mounted, IBM plug-compatible expansion port attaches an optional 360K, 5%-inch or 720K, 3%-inch external disk drive.

The EX can accommodate up to three Tandy Plus expansion modules for adding memory (catalog no. 25-1062, \$129.95), an RS-232C serial port (catalog no. 25-1014, \$79.95), a 1,200-baud modem (catalog no. 25-1018, \$199.95), a mouse/clock calendar (catalog no. 25-1015, \$99.95), or a network adapter (catalog no. 25-1019, \$299.95).

You must install the Plus memory



module before other expansion modules. It provides a direct-memory-access (DMA) controller, boosts memory to 384K, and provides empty sockets for an additional 256K of RAM.

Bundled software includes MS-DOS 2.11.24, GW-Basic 2.02, and Personal Deskmate, an extensive desktop application manager similar in design to Microsoft's Windows operating environment.

Setup

The start-up and installation documentation is well written and easy to understand. MS-DOS and Basic coverage is adequate, but you must purchase additional manuals for other than casual use. Setting up the 1000 EX is simple. Separate manuals and reference guides move you quickly through equipment setup to installation of the Deskmate software. Adding the Plus memory-expansion

The Star Ratings

80 Micro's star ratings reflect our reviewer's impression of a product.

The stars mean:

- **** Superior
 - *** Excellent
 - * * * Good
 - ** Fair
 - * Poor

module takes only a few minutes due to the handy top-mounted, slide-off, expansion-slot cover.

An optional stand (catalog no. 26-210, \$29.95) holds a monitor and optional second disk drive above the keyboard. The 1000 EX works with all Tandy RGBI color monitors, except the high-resolution CM-1. Text quality and color reproduction are excellent with the CM-10, good with the CM-5, and only fair with the machine plugged into a composite color monitor or color TV.

Spacewise, the unit's small footprint is deceptive. The sideways-mounted in-

ternal disk drive requires 9 to 12 inches of free desk space to the keyboard's immediate right to comfortably insert and remove disks.

In addition, the drive-activity light isn't visible from the normal operating position, making a reassuring glance for proper drive operation difficult. The unsettling honk of the Teac 55B disk drive provides the only indication that a disk access is in progress. However, the ultraquiet cooling fan helps balance the overall noise level.

Under the Hood

The computer is heavily shielded for radio-frequency interference (rfi) and produces negligible television interference when operating directly atop and sharing the same line outlet as a television receiver. This effort to reduce stray radiation is a noteworthy improvement over earlier versions of the Tandy 1000. Inside, you'll find a 48-watt power supply adequate to power the expected load of the computer and its three expansion slots.

Keyboard feel and response is good. All keys provide adequate resistance and solid tactile feedback. The keyboard is identical to the original 1000, except for the relocation of the caps—and number-lock indicator lights and the addition of a power-on light in a cluster above the numeric keypad. Unfortunately, the EX

IS GETTING THE ANSWER TO SOFTWARE PROBLEMS A BIGGER PROBLEM THAN THE PROBLEM?

Don't stay on hold when there's help online from CompuServe* Software Forums.

The new upgraded version of your software locks up.
And every time you reboot,

you get stuck in the same place in the program.

You've chucked the manual, because you've done exactly what it tells you to do six times already. So you call the software company.

Now you spend half a day beating your head against a brick wall of busy signals, ranting at recorded messages, hanging around on hold. And you still don't get the solution to your problem.

Meanwhile, progress is stopped

and your profits are dribbling away. But wait. There's help...

Several prominent, progressive software publishers recognize this problem, and working with Comp

working with CompuServe, have developed a solution— CompuServe Software Forums.

Now you can go online with experts from the companies that produced your software and get

prompt, written answers to your specific problems. You can even talk with software developers.

Aldus, Ashton-Tate, Autodesk, Borland International, Creative Solutions, Digital Research, Living Videotext, Lotus Inc., Microsoft, MicroPro, Misosys Inc. and Software Publishing all have CompuServe Software Forums.



CompuServe's large subscriber base also puts you in touch with thousands of other, often more experienced, users of the same software. You'll find they can give you lots of creative ways to get the most out of your software.

And software forums are the best way to learn about product updates, new product announcements, new ways to expand the uses of your software, and offer free uploads of your own programs.

Our online electronic magazines

frequently publish software reviews. And you can find help for many other software products in our other computer-related forums for IBM, Tandy, Atari, Apple, Commodore, TI* and others.

The last thing you need when you've got a software problem is a bigger problem getting answers. So, from now on, get prompt, informed answers on CompuServe Software Forums.

To buy your CompuServe Subscription Kit, see your nearest computer dealer. Suggested retail price is \$39.95.

To order direct or for more information, call 800-848-8199 (in Ohio, 614-457-0802).

If you're already a CompuServe subscriber, just type GO SOFTWARE at any! prompt.



CompuServe[®]

Information Services, P.O. Box 20212 5000 Arlington Centre Blvd., Columbus, OH 43220

An H&R Block Company

REVIEWS

suffers the same keypad mapping problems that make all Tandy 1000s inconvenient to use with many software packages written for the IBM PC.

Performance

The EX's dual-speed Intel 8088-2 CPU normally runs at high speed (7.16 megahertz [MHz]). However, you can press the F4 function key just before loading DOS to toggle the clock to slow speed (4.77 MHz). You cannot change the clock speed from within an application without returning to DOS or the Deskmate shell.

The EX scored a consistent 1.4 on the Norton Utilities system-information test while running at high clock speed, indicating that the machine operates approximately 40 percent faster than the original IBM PC.

The 8088-2 and Phoenix Software Associates ROM basic input/output system (BIOS) chip successfully navigated every application I tested, including Lotus's 1-2-3, Multiplan, PFS:File, Quickbasic 2.0, and graphics-oriented applications such as Flight Simulator, Jet, and Prodesign II CAD.

However, the EX won't run color software designed for the IBM Enhanced Graphics Adapter (EGA). An EGA-compatible expansion board to fit the 1000 EX proprietary expansion bus is not currently available. The EX accepts only Tandy Plus (and third-party) expansion modules.

Personal Deskmate

Personal Deskmate comes as part of the bundled software package. The massive two-disk package

provides productive start-up software covering a variety of home and personal applications. It acts as a memory-resident manager for controlling the Deskmate modules. It also doubles as a DOS file manager and provides a way to run almost any program directly from the Deskmate core.



Inside the Tandy 1000 EX.

The package consists of six program modules. Text is a graphics-driven text processor. Worksheet is a 99-row by 99-column spreadsheet. Filer is an all-purpose information storage and retrieval system. Paint adds an excellent graphics painting program, while Calendar lets you keep track of schedules and appoint-

Circle 214 on Reader Service card.


FORT WORTH COMPUTERS

STATEMENT OF HONESTY

Beltron parts are not compatible and will-not function with Tandy products.

EPSON PRINTERS

LX 86\$219.00 FX 86e389.00 FX 286e559.00 LQ800489.00



TAIWAN PRICES U.S. STANDARDS

IBM COMPATIBLE





CALL FOR MORE PRICES

Texas Residents PLUS 5.25%

CUSTOMER SERVICE/QUESTIONS ABOUT YOUR ORDER and in TEXAS 1-817-573-4111 (9 am-5 pm TEXAS TIME MONDAY-FRIDAY)

Fort Worth Computers 377 Plaza Granbury, Texas 76048

TO SAVE BY MAIL . SEND CHECK WITH YOUR ORDER.

RUSH-&-SAVE-USE OUR ORDER HOT-LINE



REVIEWS

ments. Telecom provides a full-function telecommunications program when the optional Plus serial or modem modules are installed.

A mouse-oriented, point-and-click application manager called the Tandy Desktop manages the Deskmate modules. Its features include a calculator, five-page notepad, phone list, and DOS file manager. You can define any application program (and its accompanying data files) as a module. You can create, display, resize, delete, and shuffle a module around the Desktop screen, then run it as a stand-alone application with return to memory-resident Desktop.

Navigating through Personal Deskmate is a snap using the keyboard, a joystick, or a mouse. The documentation recommends using the Tandy Digi-Mouse (catalog no. 26-1197, \$99.95) and Plus clock/

The 1000 EX offers quality in materials and workmanship.

mouse expansion board. If you don't need a clock/calendar, you can get the same results by installing the joystick device driver and using the Tandy Color Mouse (catalog no. 26-3025, \$49.95).

The Desktop accessory option lets you redefine screen colors and communications parameters, customize printer setups for most any printer, and much more. Although you'll rarely need them, excellent context-sensitive help screens are a keystroke or double mouse click away.

The only problem with Personal Deskmate is its behemothic size. You need at least 384K RAM to load the entire package into memory without dispersing the modules onto individual disks. In this configuration, you must load modules from separate disks to make them available to the Desktop core. Single-drive users will find frequent disk accesses and disk swaps the order of the day.

Summary

At \$599, the 1000 EX is an exceptional value. It bespeaks quality in materials and workmanship. The low base price, solid documentation, and ability to run IBM PC software make it an excellent computer for home or school. Fol-



The application manager lets you work with Deskmate's modules.

lowing earlier mediocre attempts at providing productive bundled software (Deskmate I and II), Tandy has done it right this time. Personal Deskmate is unquestionably the best application manager currently available for a personal computer.

However, the EX is not a "something for everyone" computer. If your plans include expanding the EX into a high-powered, PC-compatible machine later on, you'll find its lack of internal expansion and its proprietary system bus a road-block.■

Circle 214 on Reader Service card.

World's Best Independent Authorized Computer Dealer



Tandy_®



Radio Shack

COMPUTERS PRINTERS Telephones, etc.

Think About It

If a retailer is willing to
MEET OR BEAT OUR PRICE
can you trust him? Doesn't it
mean he will take you for more,
if he can, and only give you a
better price IF YOU
CATCH HIM AT IT...?

IN STOCK **NOW**



3/1/87

3.0



FOR LATEST PRICES & CREDIT CARD ORDERS 8AM-6PM TEXAS TIME CALL FREE (1-800)-433 - S-A-V-E

Subroutines to Go by David A. Williams



ASP runs on the Tandy 1000/1200/3000. Aspen Systems, P.O. Box 1163, Grand Junction, CO 81502, 303-245-3262. \$130.

ASE runs on the Tandy 1000/1200/3000. Aspen Systems. \$99.

Program development is easier when you have ready-made sub-routines on hand to insert where needed. If your subroutine collection is lacking, Aspen Systems has two offerings that you might consider. ASP is a group of 139 subroutines in a single library file. Its functions include simple arithmetic, sorting, display, and disk input/output (I/O). ASE is a subroutine editor that helps you design custom data-input screens with windows and verification of user input.

You can use both packages with Microsoft Basic, Fortran, Cobol, and Pascal compilers; with the IBM Basic interpreter; or in assembly-language programs. Aspen Systems does not require royalties if you display an acknowledgment on the final program.

I evaluated both products on a Tandy 1200 HD with Microsoft's Basic compiler, Bascom, and Macro Assembler.

ASP

The ASP subroutines were originally written for CP/M. Aspen Systems has updated and expanded the CP/M version, but modern MS-DOS-based compilers need less assistance than their CP/M predecessors. Still, the package provides some functions you might find useful. The subroutines enhance Fortran's string-manipulation capability and provide large-number, decimal arithmetic for Basic. If you use assembly, which has few built-in functions, ASP could be a great time-saver, but the documentation provides limited help for the assembly programmer.

The functions fall into the categories of data formatting and conversion, screen and keyboard I/O, disk I/O, arithmetic, and sorting. Some are trivial. One merely sends a carriage return to the display, and many of the disk I/O routines duplicate BIOS and DOS functions.

The 300-page manual is the weakest part of this package. It was reproduced from the output of a poor-quality dot-matrix printer, but the manual's poor legibility is exceeded by its lack of clarity. It contains interesting historical and tutorial information, but it is of little

practical help in the application of the subroutines. The installation and configuration instructions are especially confusing; information contained in a Readme file supersedes many of the manual's instructions. The documentation has numerous errors and program sequences that don't work.

Fortunately, sample programs illustrate the application of some of the subroutines. ASP provides Fortran, Pascal, and Basic source code for these programs, all of which ran and performed.

Except for the arithmetic functions, ASP's performance is disappointing.

Between the sample programs and a great deal of experimentation, I did get several routines working in test programs. Except for the arithmetic functions, performance was disappointing. ASP routines did not improve Bascom's screen-display times, an area sorely in need of improvement. Even compiled Basic is much slower than those snappy assembly programs that write directly to the display buffer. The memory-sort routine showed a small performance improvement. A program to sort a 1,000record, six-element array took 5.3 seconds using the ASP routine, but only 5.9 seconds with Bascom using a standard sort procedure. The EXE files for my test programs were about 15 percent larger when I used the ASP routines.

ASP should yield a substantial performance improvement when used with the Basic interpreter, but Quickbasic would be a better investment.

The arithmetic subroutines will be of interest if you program in Basic and write financial packages or programs requiring exact results when handling large numbers. ASP uses decimal arithmetic on strings of ASCII digits that can be up to 65,535 digits. It is impressive to multiply two 30-digit numbers and see the result appear instantly. The routines are limited to simple arithmetic functions; they don't include scientific functions.

ASE

ASE provides complete screen-management and data-input functions in two major subroutines. The package also includes several supporting routines for moving data around in memory, reading and writing files, data conversion, and simple screen display.

Don't expect to write a word processor or even a reasonably capable text editor with this product. ASE's primary mission is to provide sophisticated data entry for forms-oriented applications. The programmer has complete control over display and record formats and can design the format to change in response to user input. The usual cursor movements are present, including block functions.

You can tightly control the length and content of user input. The input-validation scheme checks for length, range, and format, and you can display error messages to tell the operator what is wrong. ASE also provides select inputs, giving a choice of several options.

The ASE manual, a considerable improvement over ASP's, is clearer and more readable. Still, ASE is a complex program, and you can expect to spend a substantial amount of time reading the manual and studying the single programming example.

The demonstration program is a comprehensive example of an ASE application. It includes well-annotated source code in all the supported languages except assembly. The key assignments used in the demo seem a little odd (delete and backspace perform the same function), but you can change them to your liking.

ASE uses a Map file to control display formats. Each window requires a different file, and the program can dynamically change them. The Map file conveys no actual visual impression of what the display will look like. Prepared with a text editor, Map consists of a string of command mnemonics and parameters. The order of the commands determines the order in which the items will appear in the final display.

The available command parameters are many and complex. In fact, ASE is a mini-programming language that includes conditional statements and loops. You can use conditionals to change the format of the form as a function of user response. For example, the Option command, performing like the Basic On. . .Goto statement, branches to one of a number of command strings.

The Bottom Line

While I can't recommend these packages for the novice, they might interest the serious or professional programmer. Of the two, the editor is more useful. The problem with this type of package is that it has to be flexible enough to meet a wide variety of requirements. This leads to larger code and poorer performance than is possible with a custom design. I would find the products more useful if they included source code that I could modify to suit my application.

Upgrading to MS-DOS?

LET'S
GET
SERIOUS.

THE COMPUT FUNNY NAME

THE CLONE™

Frankly, this is the best computer value in America. Better than IBM. Better than Tandy. Complete MS-DOS™ compatibility. . .lightning fast processing. . .tons of RAM. This machine has everything the Boys in Blue promise. . .and more. All at a price you can afford.

WE DIDN'T NAME IT "CLONE" FOR NOTHING.

What we have here is a computer that is truly IBM PC/XT compatible. The Clone computer is completely MS-DOS compatible and it has all the hardware capability of the IBM PC/XT (except cassette) plus some and comes with MS-DOS 3.2 (the latest version), GW-BASIC and reference manuals (manuals are extra cost on the Tandy 1000!). With the Clone you get eight IBM compatible expansion slots, seven of them a full 13" long. You have six additional slots available; something a Tandy 1000 owner can only dream about.

IBM COMPATIBLE? YOU BET.

Flight Simulator, one of the classic tests of compatibility, runs perfectly. Lotus 1-2-3® can't tell it's not running on an IBM. In fact, we have not discovered an off-the-shelf MS-DOS software package that wouldn't run properly on the Clone. The ability to run standard, off-the-shelf, software is important because it allows you to obtain software from any number of sources.

STANDARD FEATURES:

The Clone computer comes complete, ready to run, with lots of standard features. Like the maximum 640K of system memory installed. Like an IBM standard parallel printer port, a clock/calendar with automatic battery backup, a speaker, two serial ports (one populated), a game adapter/joystick port, a light pen port, a 2-drive floppy disk controller, and the newest AT style keyboard. The video output is IBM standard color graphics with a special port that allows you to view color software on a monochrome monitor as well as 80 x 25 text. A 360K ultra-reliable floppy drive is included with space for three additional halfheight floppy or hard disk drives. The 135 Watt power supply runs cool and assures you of adequate power for future expansion.

PC-DeskMates, a powerful multi-function memory resident utility, is included so you can start using the Clone when you receive it. You get an alarm, clock, calculator, calendar, notepad, phone dialer, typewriter, and access to DOS level commands. The Clone also comes with Qmodem, the famous modem program which enables you to access the world of telecommunications. PC-Write, probably the best shareware word processor available, is also furnished. Your Clone comes ready to work for you.

WHAT'S MISSING? The Big Blue price tag



For serious users only.

OPTIONAL FEATURES:

The Turbo Clone is equipped to run at the standard 4.77mHz clock rate or at a blazing 8mHz. That's almost 70% faster processing than a standard IBM. Front panel lights indicate Turbo operation, power status and hard disk activity. A keylock switch allows the keyboard to be electrically "locked out" for unattended security. Imagine a lengthy Lotus 1-2-3 spreadsheet recalculation with an 8mHz processor! It's awesome.

HOW TO BUY A COMPUTER WITHOUT LEAVING YOUR CHAIR.

Zero effort required. Just pick up your phone and call us toll-free.



Your American Express, MasterCard and Visa are welcome at no extra charge as well as your check, money order, or COD order. Your Clone ships right away. In just a few days the UPS man delivers it to your door.

Too long to wait? Ask for our Expedited Service. Our distribution experts will get you a Clone OVER-NIGHT, almost anywhere. (Some restrictions apply).

A WORD OF EXPLANATION.

We sell Clones exclusively by mail. And there's a good reason why. Supporting the expensive overhead of a chain of retail stores is not our idea of keeping costs down. You're buying the Clone computer at wholesale prices, directly from the manufacturer. Your Clone comes with an ironclad guarantee that exceeds most other manufacturers'. We guarantee your satisfaction or we'll refund your purchase price within thirty days, no questions asked. Our guarantee is backed by a reputation earned in years of experience in the mail order business. Think about it. Repeat orders come from satisfied customers. This makes us work very hard to get it right the first time.

US VS. THEM

FEATURES Microprocessor: Intel 8088 @ 4.77mHz Power Supply Rating IBM Standard Bus: Operating System: Disk BASIC: MS-DOS and BASIC Ref. manuals: Standard System RAM: Cost to Expand RAM: Keyboard: Video Monitor: (composite) Video Outputs:	CLONE YES 8mHz Optional 150 WATT YES MS-DOS 3.2 YES YES 640K -0- 'AT' STYLE INCLUDED BW/NTSC/RGB	IBM PC/XT YES NO 63.5 WATT YES EXTRA IN ROM EXTRA 256K \$\$ STD EXTRA EXTRA	TANDY 1000 EX (SX) YES 7.16mHz STD 54 WATT NO MS-DOS 2.11 (3.2) YES EXTRA 256K (384K) \$259 (\$129) NON-STD EXTRA NTSC, RGB	LEADING EDGE Model D YES NO 130 WATT YES MS-DOS 3.1 YES YES 512K \$ STD INCLUDED
Disk Drive Capacity: Max Number of Internal Drives: Internal Expansion Slots: Accepts Standard IBM Cards: 8087 Math Co-Processor Option: Sturdy Steel Case: Standard Parallel Ports: Standard Joystick and Light Pen Ports: Standard Serial Ports: Warranty Clock/Calendar	1-360K 4 8 YES YES YES 1 YES 2 (1 Optional) 1 YEAR YES	1-360K 4 5 YES YES YES 0 NO 0 90 DAYS	1-360K (2-360K) 1 (2) 1 (5) NO (10" Only) NO (YES) PLASTIC 1 J (J/LP) 0 90 DAYS	B/W, RGB 2-360K 2 4 YES YES PLASTIC 1 NO 1 15 MONTHS YES
Cost Ready-to-Run 8mHz Option	\$699 \$799	\$3,063	\$1,398 + (\$1,683 +)	\$1,295

Add \$35 for ground delivery; \$70 for air.

IBM XT cost figures*: Video Display Adapter \$250; Video Display \$275; IBM XT computer \$2,145; Additional Ports, serial port, game port, parallel port, 640K RAM \$308; DOS 3.2 and BASIC \$85; Total \$3,063. Does not include the battery back-up clock calendar. No light pen port.

Tandy 1000 cost figures*: DOS 2.11 and BASIC reference manuals \$29+; Memory Plus Expansion Board (to 384K) \$129+; 256K Additional RAM \$129+; One serial Port \$79+; Battery Back-up Clock Calender \$99+; Composite Monochrome Monitor \$129+; Model 1000 EX Computer \$799; Model 1000 EX Computer \$799; Model 1000 EX Computer \$199; We were not able to equip the Tandy 1000 to directly compare with the Clone because of the 1000's Inherent design limitations.

*The above prices are list prices as best we could determine. Both the IBM and Tandy are

straightforward as our warranty. So here's the fine print.

CLONE OPTIONAL EQUIPMENT AND FEATURES

2nd 360K TEAC Half-height Floppy Drive\$99	HiRes RGB Color Monitor 640 x 200 \$299
20mb 65ms Seagate Internal HD399	HiRes Mono Graphics Card 720 x 348129
30mb 40ms Seagate Internal HD699	HiRes Mono Monitor 720 x 348
80286 SpeedKit. Makes XT faster than AT399	5339 Accounting Keyboard89
300-1200 Internal Modem & Software	300 Watt Uninterruptable Power Supply 299

Simply, if anything is wrong with your Clone or any of its peripherals, we'll fix it free for up to one year after you've received your Clone. You have probably read other manufacturers' warranties, and gotten confused, suspicious or even mad. You're probably skeptical about anything as simple and

You can void your warranty by failing to exercise normal care when hooking up or operating your Clone. Or trashing the guts with a hammer. Or running it over with something. Or burning it up.

You have thirty days after receipt of your Clone to see if you and it are going to be compatible. If you are not satisfied with your Clone for any reason within that time you may return it to us for a full refund, less shipping charges. Just don't write in the manuals or lose anything that was in the original container as it all has to be intact.

The other guys only give a 90 day guarantee. Ever wonder why? Ever try to get a refund? Complete warranty details are available on request.

NO ORPHANED CUSTOMERS

We have been supplying serious customers with high quality hardware and software since 1980. Sound engineering, high performance, quality construction, outstanding warranties and a reputation for doing the right thing have been our way of doing business since Day One. As the manufacturer of Clone computers, we stand behind each computer sold with a 100% commitment to our customers' satisfaction. Price, Performance, Value. . .Clone is the clear choice for serious computer users. To order, call us today. REMEMBER. . .YOUR BEST FRIEND MAY BE A CLONE!

Clone Computers; 2544 W. Commerce St; Dallas, Texas 75212; 214-637-5400; Telex 882761; FAX 214-634-8303;

800-527-3582 U.S.A Clone 9nol 9

©1986 by Clone Computers. IBM is a registered trademark of International Business Machines. MS-DOS is a trademark of Microsoft. PC-DeskMates a trademark of Alternative Decision Software. Qmodem is a trademark of the Forbin Project. PC-Write is a trademark of Quickoft. Lotus 1-2-3 is

REVIEWS

Smart, But Not Wise by Mark D. Goodwin



E1 runs on the Models I/III/4 (48/64K) and the Tandy 1000/1200/3000 (128K) and requires TRSDOS 6.2 and two disk drives. Pittman Associates, Suite 272, 7837 Greenback Lane, Citrus Heights, CA 95610, 916-966-7769. \$149.95.

L1 is an artificially intelligent database program; it makes relationships among data that you enter in the form of keywords and phrases, along with their definitions. The way in which E1 makes these relationships depends on the questions you ask it.

The system handles information through four operational modes: Learn, Request, Forget, and Dump.

The first step in using E1 is entering concepts and dictionary items in its Learn mode. Figure 1 presents the five grammatical structures E1 can use to learn new concepts. Figure 2 illustrates how these grammatical structures link concepts. Dictionary items are keywords or phrases that require lengthy definitions. You enter these items into the data base by telling E1 the specific keyword or phrase and then entering its explanatory text.

Once the E1 data base has absorbed data, you can access it by asking E1 questions in the Request mode. Some questions can generate a yes or no response. Therefore, E1 lets the operator request a reason for the resulting response. You prompt E1 for an explanation by asking "How?," "Why?," or "How Do You Know?," or simply by demanding that E1 prove it.

You can also access the E1 data base through the Dump mode. It generates a complete listing of the data base's concepts, keywords, and phrases. The Dump mode's listings can be particularly useful for learning whether the data base contains information relating to a specific piece of data.

As with all data bases, an E1 data base will eventually hold a great deal of unnecessary data. You can purge it from the data base through E1's Forget mode. The Forget mode lets you purge data by a statement, a specific keyword or phrase, or a concept. When you use a statement for purging, you use the Learn mode's grammatical structures. Whenever you purge a concept from the data base, E1 automatically deletes all references to it.

The E1 documentation is a poor, 39page manual. While the manual presents an overview of the system, its lack of detail is confusing. For example, the manual doesn't give a step-by-step procedure for executing E1. Although execution is



DED86[®] — A powerful sector-oriented disk and file editor as well as a page-oriented memory editor. Position by cylinder/head/sector, logical sector, or cluster on floppies or hard drives. Jump around subdirectories. Edit any sector in hexadecimal or ASCII. Designate sectors to "keep" in a list for dumping to a disk file. Examine/alter memory and dump a RAM "keep" list to a disk file. Great for a text recovery after a program crash. Requires DOS 2.x or higher . \$59.95 + \$5 S&H



MISOSYS, Inc. PO Box 239 Sterling, VA 22170-0239

Sterling, VA 22170-0239 703-450-4181 MC, VISA, CHOICE Orders Only! 800-MISOSYS 1P-5P EST M-F VA residents add 4½% sales tax S&H: Canada add \$1; Foreign use S&H times 3

MS-DOS is a trademark of Microsoft Corporation

X is a Y For equality

X has Y For inclusion (X contains Y)
X is Y Where Y is a quality of X
X can Y Capability, capacity,

facility of

X is like Y Similarity, analogy,

approximation

Fig. 1. Learn-mode grammatical structures.

ORANGE

is a
CITRUS FRUIT
has
VITAMIN C

can is
PREVENT SCURVY WATER SOLUBLE
STATEMENTS:

ORANGE IS A CITRUS FRUIT CITRUS FRUIT HAS VITAMIN C VITAMIN C CAN PREVENT SCURVY VITAMIN C IS WATER SOLUBLE

Fig. 2. Sample structures.

simple, simple procedures are often the most confusing to novices. The manual's only bright spot is its sample program runs.

E1 has many other problems, as well. Although it is a compiled Basic program, it is excruciatingly slow. Other problem areas include insufficient error trapping of keyboard entries, non-recognition of lowercase letters, and erratic performance by the Forget mode.

E1 needs an enormous amount of disk space. Besides the programs on the system disk in drive zero, the data disk in drive 1 is completely filled with program overlays. Therefore, only a minimal amount of space is left on the system disk for the data base's files.

Finally, the programming techniques used to implement E1 are second rate. For example, the Basic Input statement is used throughout the program for data entry. Although Input is acceptable for personal programming efforts, it is unacceptable for commercially produced programs and gives E1 a shoddy appearance.

Conclusions

Although I applaud the idea of producing an artificially intelligent business program, it's hard to get excited about E1. Its complete lack of speed and amateur implementation reduces E1 to an almost useless program. I can't think of even one task that couldn't be done better manually or with a more traditional data-base program. With an improved manual, a great deal more speed, and a few bells and whistles, E1 could have limited use.

Stuffed Model 100 by Thomas L. Quindry

The CMOS Expansion RAMs increase the Model 100's memory capacity to 64K, 128K, or 224K. PG Design Electronics Inc., 37560 Thirty-one Mile Road, Richmond, MI 48062, 313-727-2744. \$300, \$425, and \$575, respectively.

The Data Transfer Utility Program runs on a 32K Model 100. PG Design Electronics Inc.

PG Design introduced the concept of adding an extra bank of 32K memory to the Model 100. This first breakthrough doubled the 100's user RAM. Now PG Design offers 64K, 128K, and 224K expansion RAM modules that increase your Model 100's user RAM to three, five, and eight times, respectively.

Although the 100's CPU allows access of only 32K of user RAM at a time (in addition to the 32K ROM), it also permits switching out the Tandy 32K RAM or ROM bank and substituting other, higher-capacity RAM or ROM.

Not only can you upgrade your 100 to 224K of extra RAM (seven 32K banks), but, due to its design, you can still use the ROM socket where programs on a chip can add extra utility without sacrificing RAM.

I had been using PG Design's 64K expansion RAM for the past year before installing the 224K RAM bank. The hardware looks the same, and the quality is excellent. I've had no problems.

The expansion RAM has a U-shaped circuit board that connects to the expansion bus in the cavity on the bottom your Model 100. You cannot use these expansion RAMs on the Model 102 because it doesn't have this expansion-bus cavity. A 3-volt lithium battery with a six-year shelf life provides back-up power for the expansion RAM.

A simple, one-line bank-select program is included to let you change from the original Tandy memory to any of the PG Design memory banks. This small program also allows you to select and cold-start any memory bank if a problem occurs, freezing the bank.

Since each 32K bank of memory simulates a separate computer, your programming efforts are limited to 32K for the code, all operations, and computations associated with it. Using the 224K RAM module, for example, would be like switching to one of eight different computers, each with its own set of programs. PG Design includes software to allow you to transfer data or programs from one bank to another.

The Data Transfer Utility Program

The included Data Transfer Utility Program uses about 1,600 bytes, comes on cassette, and has a loader that places it at the right memory address; you then customize it for the particular RAM-expansion module you have.

You get three other useful functions all under function-key control. You can kill or rename a file and select a forced line feed with carriage return when printing text files. The lack of a forced line feed is one of my biggest complaints about the Model 100.

The program provides two other useful bits of information: the size of each file you select by cursor and a notation on which bank you are in. Although the Data Transfer Utility Program is meant to be resident, you can disable it with a function-key command. Residency offers an advantage over PG Design's nearest competitor, who includes an expansion ROM for data transfer. Since the program is resident, you can install other ROMs without losing other functions.

I found only one problem with the Data Transfer Utility Program. Its operation is timing sensitive, and it requires that your primary 32K RAM bank be original Tandy or of the identical specifications. PG Design sells 8K RAM modules that work as well as the Tandy RAM, but 8K RAMs from some other distributors fall short of the mark.

Before PG Design's latest software update, the company recommended using Purple Computing's 8K RAM. I have used the previous Data Transfer Utility Program with my 64K RAM module and a Purple Computing 8K module with no trouble. With the updated software, the Purple Computing 8K module doesn't work, even with the 64K module. PG Design has made its timing tolerances too tight. However, for a small fee, the company does offer a trade/replacement for incompatible RAM.

I've found that the best way to use the extra RAM banks is to store programs or backups of important files. When I want to run a program or two, I use the Data Transfer Utility Program to copy the program to the first bank, much as I would from a disk drive. Then I run the program from there. If it generates a data file, I copy the data to another bank for safekeeping.

Summary

Although I recommend a disk drive for complete and efficient storage of your prized files, I find that the extra 224K holds more than I would ever use at one time. It frees me from taking my disk drive on trips.

PC - SPRINT 1000

SPEED FOR THE T1000!

PC-Sprint 1000 is the latest product from Exec-PC, the PC speedup specialists. Our newest product is designed exclusively for the Tandy® 1000. Why buy a faster PC when you can run your T1000 at 7.38 megahertz?


- Run your T1000 at 7.38 mhz.
- 280% speedup (Norton SI rating)
- Speeds up all software you can see the difference
- "Slotless" plug-in installation
- External speed switch
- Change speed "on the fly"
- Includes two microprocessors, select the one best for your installation.

Includes: PC-Sprint circuit card, NEC V20 and 8088-2 microprocessors, cables, instructions, warranty, tool, remote mount switch, free BBS subscription.

P.O. BOX 11268 Exec-PC, Inc. Shorewood, WI 53211 ORDER HOTLINE ORDER BY MODEM (414) 242-2173 (414) 964-5160




Circle 449 on Reader Service card.



PROFESSIONAL HANDICAPPING SYSTEMS

PROFESSIONAL SERIES TO SOFESSIONAL HANDICAPPING TOOLS from PROF. JONES



LOTTERY:

Advanced statistical analysis programs with Hard's 6-Digit Permutation, Dimitrov, and of Statistical Lottery Analysis¹⁰. Enhanced Lottery/Loto Analysis¹⁰. Professional Lottery Analysis¹⁰.

FOOTBALL: Complete football statistical prognosis of game scores, points spread, best bet, etc. Winfoss power ratings, previous four game analysis, multiple prediction results, and

Football Predictor* Football Addition** Professional Series Footbal™. Bookie Buster™ Football Analysis. BASKETBALL:

BASNET PALL:

Prodict game results based on team strength ratings, past games stats analysis, etc.

Evaluates any points scored, any points given up, wins-losses, point spreads, wild

cards. & more!

NBA Basketball Analysis¹⁰

\$9

Basketbal Addison¹⁰

\$141

And many more programs available, call for a copy of our catalog!

Handicapper's Bulletin Board now available. The Prof's NFL & NBA weekly picks¹ Call for his. & Ph. #. / Master Handicapper™ VHS training tapes available. Learn handicapping faster and easier! / Portable PC's wrbuilt-in handicapping software available. Call for more information.

Terms: Free shipping all software. Add \$6.00 COD / \$6.00 UPS Blue / \$9.00 International delivery / ID residents add 5%. Allow 3 weeks when paid by personal check. Prices above are for cash or money order only. Add 3% for Visa, MasterCharge, and AMEX. Prices subject to change.



PRO-CREATE - The "standard" macro assembler used by professionals and novices alike. Nested macros, nested includes, nested conditionals. Full screen editor; cross reference. \$74.95 + \$3 S&H

PRO-DUCE — A 2-pass labeling Z80 disassembler from disk or memory with screening input for data areas. Generates /ASM files. \$29.95 + \$2 S&H

PRO-MRAS - Powerful relocating macro assembler development system REL module compatible with Microsoft! Includes full screen text editor, REL librarian, VM linker with overlay capability \$74.95 + \$3 S&H

UNREL-T80 - Converts MRAS or M-80 REL object files to /ASM. Use on your own REL modules, FORLIB, GRLIB, BASCOM, BASRUN, etc. \$39.95 + \$2 S&H

PRO-EnhComp - An enhanced BASIC compiler with a built-in assembler for Z80 in-line code mixed with BASIC. LOGO-like turtle graphics, strings to 32767 chars, multi-line functions, keyed/tagged SORT, REPEAT-UNTIL, structured IF-ENDIF, labeled statements, double precision functions.

\$124.95 + \$3 S&H

LS-TBA - A structured BASIC translator. Labeled statements, Conditional translation, pseudo global and local variables, 14-char var names \$24.95 + \$3 S&H

PRO-MC - A full K&R C compiler with nearly 200 functions. Structs, unions, bitfields, enum, dp floats and functions. Wildcards, I/O redirection, args, overlay support. Requires PRO-MRAS or M-80 \$124.95 + \$4 S&H

PRO-HartFORTH - A full 1979 standard FORTH compiler using indirect threaded code. Runs under the DOS. Has floating point, access to DOS files, screen editor, block graphics \$74.95 + \$3 S&H

RATFOR-M4 - A professional implementation of RATional FORtran. Provides stucture and greater portability to FORTRAN programs. Fully documented with tutorial user manual. Requires FORTRAN compiler \$99.95 + \$3 S&H

Note: Model I/III products may be available on request.



MISOSYS, Inc. PO Box 239

Sterling, VA 22170-0239 703-450-4181 MC, VISA, CHOICE Orders Only! 800-MISOSYS 1P-5P EST Monday-Friday

VA residents add 41/2 % sales tax. S&H: Canada add \$1; Foreign use S&H times 3

A 4P Modem That Works by Jack Feldman

Teletrends TT512P Modem is an internal, 300/1,200-baud modem for the Model 4P. Teletrends Corp., P.O. Box 2198, Garden Grove, CA 92642, 714-554-7401. \$179.95.

Purchasing a Tandy computer is like joining a club. If Tandy makes a mistake, a lot of clever club members can see the flaw and find a way to make it right. The shortcoming for the Model 4P was its modem. Although the built-in modem for the transportable was a good idea, Tandy's implementation was lacking: It featured a 300-baud modem at a time when 1,200 was common and an autodialing scheme that defied logic. This modem took the 4P out of consideration as a working computer for telecommunications.

Enter the Teletrends TT512P board. This internal modem gives the 4P the telecommunications punch that makes it a serious computer for on-the-go operations. It fits neatly in place of the Tandy modem board, runs at either 1,200 and 300 baud, and uses the familiar IBM PC AT dialing protocol. And it costs little more than did the discontinued Tandy modem.

Installation

Installation is easy. First, disconnect your 4P from all power sources. Look at the rear of the computer, find the cover plate to left of center, and remove it. If you're replacing an existing modem, remove its cable from the DB25 connector and gently pull the modem card from the edge-card connector and out of the computer.

Insert the new modem in the slot and make sure the card is firmly seated. Although they were out of stock as of press time, Teletrends promises to include a replacement cover plate with the TT512P. This cover is designed to be

The TT512P makes the 4P a serious computer for on-the-go operations.

used in place of the 4P's cover and fastened with the screws you removed from the original plate.

Now plug the new cable into the 4P's DB25 connector and connect the modem to the phone line. You can also connect your phone to the other modular jack on the modem card.

Using the Modem

If you have a terminal program that has an autodial feature, you don't have to read the manual to get started. Fortunately, I had an autodial terminal program and a Hayes modem at hand, so the first test was to see if the modem would work without changes. Everything worked fine. There were some differences, but they were minor.

First, you do not hear the modem placing the call and making the connection. The card has no room for a speaker, so when the number dialed appears on the screen, you have to wait for the screen to tell you if you've been connected or if the modem has timed out.

As a plug-and-go system to use with software already configured for the 4P, the modem is a winner. Before reading the manual, I used the modem with a variety of terminal programs and hosts, including the following public-domain software: PTerm in Model 4 mode with TRSDOS 6.2, LTerm in Model III mode with LDOS, and MEX in Model 4 mode under CP/M.

Since the manual mentions Modem80 as a commercial package that works with the modem, I tried that, too. I found that all the packages worked perfectly.

I used the various terminal packages to dial into a variety of host computers. First, I dialed a 3B2 system and then called the Teletrends data number to leave a technical question. After that, I downloaded data from bulletin-board systems (BBSes) around the country. Finally, I called the Knowledge Index as an example of a commercial data-base search.

The TT512P also features autoanswer, which lets you use your 4P as a host computer, and speed shift, which lets you, via software, select the speed at which you access a BBS. The software and modern work together to keep your computer sending at the speed appropriate for the individual BBS.

The TT512P doesn't have a switch that lets you turn off the autoanswer. When you boot TRSDOS 6.2, the modem sets DTR (data terminal ready) to "on," whether you have a terminal program resident or not. To keep the modem from responding to an incoming call, when you boot the program use the DOS Sysgen command to turn the Setcom DTR

The Teletrends
TT512P modem
works well
with software
designed
for the 4P.

parameter off. But the manual doesn't cover this.

Undocumented Information

The manual does seem brief, but the TT512P is a plug-and-go device: You plug it in, and it works nicely with the 4P. However, you'll need further technical information if you intend to set up a BBS.

The manual doesn't include a technical help phone number. Although the company backs its product with a generous two-year warranty, you'll have to find its ad in 80 Micro if you need to phone for help.

The manual refers to result codes, but it doesn't tell you what they are. The screen displays one of six result codes (for instance, connect, no carrier, ring), which indicate the modem's response to input from the computer or the line.

You can use the F code to put the TT512P in half-duplex mode, but the manual doesn't tell you about this, either. This lack of technical information isn't fatal, but it does make it difficult to get full use of the modem. The manual doesn't mention that you can use the TT512P as part of a BBS; to do so, the modem has to signal the computer that a call is coming in at either 300 or 1,200 baud. The technical section of the Teletrends BBS said that the modem had this feature, but it didn't explain how it works.

When you use a Hayes-type modem, you have to make a special cable that connects pin 12 on the modem to pin 22 on the computer. Once again, since this is a dedicated modem, the proper connection is built into the cable.

Conclusion

The Teletrends TT512P modem is well made and functions as promised. It works well with software designed for the 4P and lets you use the computer as a terminal or host. However, its manual's lack of technical information makes it more difficult to get to all the modem's features.

8 MHZ SUPER SPEED-UP FASTEST SPEED-UP AVAILABLE (models 1, 3, 4, 4P, 40—all versions) BESTSELLER!! MAKE YOUR COMPUTER THE FASTEST IN TOWNIO \$129.00 SUPER-RAM Ramdisk program to use 128K-1 megabyte memory, the most extended program on the market today. Newdos-80 or TRSDOS 6.X SPECIAL PRICE \$25.00 SPECIAL (NEWDOS-80 + TRSDOS 6.X) \$40.00 upgrade for older version \$4.00 + old diskette **AUTOMATIC PDRIVE RECOGNIZER** \$25.00 (NO MORE PDRIVE HASSLE) ONE MEGABYTE MEMORY BOARD MODEL 4 NON GATE-ARRAY VERSION . . . \$105.00 MODELS 4, 4P, 4D GATE ARRAY VERSION\$135.00 upgrade from ½ meg to 1 meg for price difference ½ MEGABYTE MEMORY BOARD MODEL 4 NON GATE-ARRAY \$75.00 MODELS 4, 4P, 4D GATE ARRAY VERSION SAVE MORE MONEY!! A) 8-Mhz-SPEED UP + Meg-board + (NEWDOS-TRSDOS DRIVER) \$247.50 B) 8-Mhz-SPEED UP + Meg-board + (NEWDOS-TRSDOS DRIVER) \$274.50 SEATRONICS

P.O.B. 4607 - 6202 ZA MAASTRICHT - HOLLAND Please specify exact system configuration for orders. If not known, check with your dealer to see which type (gate-array or non-got-array) you have. For P&H, add \$4.00 for software, \$8.50 for hardware. MONEY BACK GUARANTEE VISA-MASTER CARD-ACCES-EUROCARD TRAVELERS CHEQUES-MONEY ORDER

Classifieds

GET THE ATTENTION YOU DESERVE

Tell more than 200,000 dedicated, interested TRS-80 users about your product or service with an efficient and economical 80 Micro classified ad.


You'll reach the most people in the market for the least amount of money!

With 80 Micro's well-established audience of involved buyers, sellers, and swappers, your ad is bound to get fast results!

For more information, write to:

80 Micro

Attn. Classified Manager 80 Elm Street Peterborough, NH 03458



The LDOS 5.3 upgrade kit is now available to take your Model III or 4 (in 3 mode) to the year 2000. LDOS 5.3 provides complete media compatibility with LS-DOS 6.3, the newest Model 4 DOS released by Logical Systems, Inc. With LDOS 5.3, you can add 12 years to the life of your software. Just look at these improvements over version 5.1.4!

DOS Enhancements:

- Date support through December 31, 1999; time stamping for files.
- Enhancements to LDOS now free up 14 additional file slots for data
- On-line HELP facility for DOS and BASIC 117 screens of help.

LIBRARY Enhancements:

- New FORMS, lets you change printer filter parameters.
- New SETCOM, lets you change RS-232 parameters.
 Improvements to LIST add paged displays, full-screen hex mode, and flexible tab expansion.
- MEMORY displays directory of terminate and stay resident modules.
- SYSTEM lets you direct the SYSGEN to any drive; adds a flexible drive swap subcommand; SMOOTH for faster disk throughput.
- DIRectory display enhanced with time stamps, file EOF, and more.
- We've also improved: AUTO, COPY, CREATE, DEBUG, DEVICE, DO, FREE, KILL, and ROUTE; and added CLS and TOF commands.

UTILITY Enhancements:

- We've added TED, a full screen text editor for ASCII files.
- LCOMM now gives you access to LDOS library commands while in terminal mode.
- PATCH supports D&F patch lines with REMOVE capabilities.
- DATECONV has been added to convert older disks to the new date convention.

BASIC Enhancements:

- Improvement to line editing with the addition of line COPY and MOVE.
- Very flexible INPUT@ added for screen fielded input.
- We've added a CMD"V" to dump a list of active variables with values - including arrays.

For \$24.95 (+S&H), the LDOS 5.3 upgrade kit includes a DOS disk and documentation covering the enhancements. Specify Model 3/4 or MAX-80.

P.S. - Don't return you old disk!



MISOSYS, Inc.

Sterling, VA 22170-0239 703-450-4181 MC, VISA, CHOICE Orders Only! 800-MISOSYS 1P-5P EST Monday-Friday

VA residents add sales tax. S&H: US \$2, Canada \$3, Foreign \$6.

DeskHelp**** DeskMate**

CREATE...

- •MAIL MERGE •DIRECT MAIL
- •FORM LETTERS
- •LABELS •CHECKS
- •CUSTOM FORMS
 •INVOICES
- •INVOICES
 •COLLECTION LETTERS
 •ROLODEX™ CARDS
- •ROLODEX™ CARDS •OUTPUT TO DISK •PRINTER CODES

PLUS . . .

- •100% ML, FAST •WINDOWS •INDEXING •EASY TO LEARN
- EASY TO USE
 MANUAL RECORD
 SELECTION
- TEXT FILTER
 CUSTOMIZE
 DEFAULTS
 ERROR CHECKING

Now you can with DeskHelp!

DeskHelp was written especially for you, the DeskMate owner, by Bobby Ballard, nationally known DeskMate expert.



Due to popular demand, Atmospheres is extending it's introductory offer for the best DeskMate add-on software available. Until the end of June, send \$49.95 plus \$3.00 S/H

ATMOSPHERES

1207 Eighth Avenue Dept. #4 Brooklyn, NY 11215 718-788-6799

Include \$3.00 SH, NYS residents add tax.

DeskMate is a trademark of Tandy Corp. Requires DOS 2.xx or higher and 384K. DeskHelp is a trademark of Atmospheres.



<u>SafeSkin</u>

KEYBOARD PROTECTOR

Finally! A keyboard cover that remains in place during use!

SafeSkin prevents damage from liquid spills, dust, ashes, paper clips, staples, etc. This custom fit cover is made of ultra-thin, ultra-tough, clear flexible plastic, molded to fit every key and contour, allowing normal key response and feel. Available for the Model 100, Tandy 1000/2000, Model 3 & 4, IBM-PC, AT, Apple, DEC, Wyse and many others. Send \$29.95, Check or M.O., Visa & MC include expiration date. Specify computer type. Dealer inquiries invited. Free brochure available.

Merritt Computer Products, Inc. 4561 South Westmoreland Dallas, TX 75237 (214) 339-0753

Circle 145 on Reader Service card.

Automatic DeskTop Publishing

with the

PowerText Formatter

With a Hewlett-Packard LaserJet and word processing software, all you need for DeskTop Publishing is the new PowerText Formatter.

For books, manuals, manuscripts, television scripts, screenplays, letters, memos, proposals, newsletters, contracts or ads like this, add the PowerText Formatter to your word processor for in-house printing. Write without concern for layout. Publish without typesetting. Everything is totally automatic.

Automatic Selection of up to 16 typestyles, Proportional justification, Text layout, Page layout, Hyphenation, Multi-column layout, Table of contents, Sorted bibliography, Two level index, Footnotes on same page,

Newsletter formats, Boxed text, Outline numbering, and much more.

PowerText Graphics integrator for including pictures, graphs, symbols from *any* graphics package available as add-on to PowerText Formatter.

Works with all of the popular word processors and any ASCII Editor. For PC/MS-DOS computers.

Beaman Porter, Inc.

417 Halstead Avenue Harrison, NY 10528 (914) 835-3156 (800) 431-0007

Price: 89.95 each plus 5.00 shipping.

REVIEWS

Words and Pictures by Harry Bee

A-Plus ETG runs on the Models 1000/1200/3000 (256K) and requires one disk drive. Savtek Corp., P.O. Box 1077, Waltham, MA 02254. 617-891-0638. \$89.95.

It's easy to find a high-quality word processor for under \$100 these days. The difficulty is choosing one from the many; a new product vying for your attention must have something special to stand out from the crowd. A-Plus has what it takes.

A-Plus ETG combines a fine, mediumduty, what-you-see-is-what-you-get (WYSIWYG) word processor, A-Write, with a capable, paint-like graphics program, A-Draw, to let you create and print illustrated documents. The presentation is attractive and slick. Its implementation is almost faultless. A-Plus is easy to learn and use, yet the elements that make it easy don't get in your way. In addition, it has a full complement of file-management utilities, a clock with an alarm and a timer, a perpetual calendar (from 1582), and a six-function calculator.

The program installs easily on floppyor hard-disk systems. Because the package is so feature rich, many program overlays and auxiliary files must be available while you work. As a result, moving between major programs is a bit slow. More importantly, because these files take up so much space on the program disk, I found a single floppy drive inadequate for using the program effectively. Two drives should be the minimum system.

A Matter of Appearances

Subtitled "The Home Work Solution," A-Plus aims for the school and home user, and nothing about the package creates a misleading impression. As a result, it is an excellent product in its intended environment.

The language of its more than 300 pages of documentation is careful and patient. The manual is thorough with plenty of illustrations, and it is fully indexed. I particularly liked the hints, usually several of them about each function, that suggest less obvious ways to get the most out of the program. In addition, plenty of context-sensitive help screens are available from inside the program, and a quick-reference card and sample files come with the package.

A-Plus's screens are clean, well-designed, and clear. You can access every function by menu selection: You highlight your choice with the arrow keys

and press the enter key. But you can also select every function with a one-, two-, or three-key command. Furthermore, express keys let you move between the major programs without having to go through the main-menu screens. In certain cases, you can get rid of the menus altogether.

For instance, within the word processor at the lowest help level, the bottom half of the screen is filled with menus. To accomplish any function, you can page through the menus until you find the one you want, then highlight and select it. If a subcommand is necessary, you find yourself in a pull-down menu with further choices. However, the menus also show you the alphabetical key you need with the control key to issue the same command. Soon, you'll need menus for reference only. When you've learned the commands sufficiently, you set the next help level, which removes the menus from the screen.

A-Write

The word processor gives you a complete set of standard editing tools, including search and replace, block cut



A-Plus allows you to insert a chart into text.

and paste, copy, and move. You can print a block of text, but you must save it as a separate document first. Cursor control is good, and scrolling is generally quick. (Since files are disk-based, you sometimes have to wait for sections to load.)

Your document can include up to five separate paragraph formats specifying tabs and margins (up to 78 columns wide only), line spacing, and justification. A double-spaced paragraph appears that way on the screen. A margin release allows outdenting and line positioning to let you center titles. Page for-

matting includes headers, footers, and automatic numbering.

On the screen, bold, underlined, italicized, and super- and subscripted characters appear that way. Special characters cover the needs of most European languages; symbols and Greek letters facilitate math and science writing.

The most impressive of A-Plus's WYSIWYG features is the concurrent display of graphics. You can bring a drawing, illustration, chart, or headline, created with A-Draw, into your document. Once you've imported a graphic, you can move it until it's where you want it. Graphics can interrupt your text, as with a heading, or you can run text beside them. Using the margin release, you can type over or inside a graphic to make bordered text and labeled illustrations.


Whether you can print what's on the screen depends on your printer. A-Plus uses printer-specific drivers; it doesn't support all printers. The version of the program I tested included 18 drivers covering about 24 popular printers. Mine wasn't among them. However, the people at Savtek Corp. are eager to de-

Continued on p. 112

Circle 464 on Reader Service card.

Grafyx Solution™ Save \$100.00

Hi-Resolution Graphics for Mod 4/4D/4P/III



Superior Hardware. The Grafyx Solution provides 153,600 pixel elements which are arranged in a 640 × 240 or on the Model III a 512 × 192 matrix. Hundreds of new business, personal, engineering, and educational applications are now possible. The hi-res display can be shown on top of the standard display containing text, special characters, and block graphics. This simplifies program debugging, text labeling, and upgrading current programs to use graphics. The Grafyx Solution fits completely within any tape or disk based Model 4, 4D, 4P, or III. Installation is easy with the plug-in, clip-on Grafyx Solution board.

Superior Basic. Over 20 commands are added to the Basic language. These commands will set, clear or complement points, lines, boxes, circles, ellipses, or arcs. The hi-res screen can be printed on any of 30 popular printers or saved or loaded to disk without leaving Basic. Areas may be filled in with any of 256 patterns. Sections of the screen may be saved and then put back using any of five logical functions. Labels can be printed in any direction. The viewing area can be changed. The entire screen can be complemented or cleared. Graphics Basic provides dot densities of 640 × 240, 320 \times 240, 160 \times 240, and 160 \times 120, all of which can be used in the same display.






Superior Software. The board comes with over 40 programs and files which make it easier to use, serve as practical applications, demonstrate its capabilities, and serve as programming examples. The software works with TRSDOS 1.3, 6.1.2, 6.2; DOSPLUS 3.4, 3.5, 4; LDOS; and Newdos80. The Grafyx Solution is also supported by over 20 optional applications programs: Draw, Bizgraph, xT.CAD, 3D-Plot, Mathplot, Surface Plot, Chess, Slideshow, etc.

The Grafyx Solution package is shipped complete for \$199.95 (reduced from \$299.95). The manual only is \$12. Payment may be by check, Visa/MC, or COD. Domestic shipping is free on pre-paid orders. Texas residents add 51/8 tax.

MICRO-LABS, INC. 214-235-0915 902 Pinecrest, Richardson, Texas 75080

Discover The Texas



Tandy® 1000 SX Computer




Now your business can have PC compatibility at a fraction of the price! Runs virtually all MS-DOS* software at speeds up to fifty percent faster than the IBM† PC! Includes MS-DOS 3.2 and DeskMate® II 6-in-1 software, two 5 ¼" disk drives, 384K RAM and 5 card slots. #25-1051 *TM Microsoft Corp. †IBM/TM International Business Machines Corp. Monitor extra

Our lowest-priced PC compatible is ideal for home or business use! Runs MS-DOS* business, home and educational software at speeds up to fifty percent faster than the IBM† PC! Includes built-in 5 1/4" disk drive, 256K memory, MS-DOS 2.11 and Personal DeskMate® software. #25-1050 *TM Microsoft Corp. †IBM/TM International Business Machines Corp. Monitor and platform extra

Cat No.	Description	Retail	Wholesale
25-4101	3000 MS DOS/Basic	99.95	69.67*
26-6022	Tandy 6000	3,499.00	2,773.67*
25-4011	40 Meg Tandy 3000	4,299.00	3,166.27*
26-1277	DMP-430 Printer	699.00	506.87*
26-1279	DMP-2200 Printer	1,695.00	1,230.57*
26-3901	Tandy 600 Portable	1,599.00	1,238.47*
26-5103	Tandy 2000 2 disk	1,599.00	542.27*
26-5104	Tandy 2000 10 Meg	2,499.00	1,163.97*

Connection for Tandy Computers.



The affordable alternative to the IBM† PC/AT! Runs virtually all popular MS-DOS* software. Complete with a 20 megabyte hard disk, 5¼" slim-line floppy disk drive, and memory expandable up to 12 megabytes. Come in now for a demonstration! #25-4010 †TM International Business Machines Corp. *MS—DOS/Reg. TM Microsoft Corp. Monitor extra

These prices were effective in January. CALL FOR LATEST PRICES!

*The Texas Connection members pay just 8% above our published wholesale price, plus shipping. All prices include a 3% cash discount. Non-certified funds take 10 working days to clear. All prices subject to change.

Members pay 8% above wholesale plus shipping.

Call Toll Free! 1-800-843-0781

Benefits:

The Texas Connection's Wholesale Pricelist Quarterly Updates

Advance Notice of Price Changes and New Products 10 day return on Hardware

Some Factory Reconditioned/Repaired items

available at fantastic savings
Tandy and Non-Tandy products at unheard of
savings

Join and Start Saving Today!

Defective Hardware replaced or repaired at our discretion.

Some items have a manufacturer's warranty.

Same day processing for fast delivery. We ship daily!

THE TEXAS CONNECTION • MEMBERSHIP APPLICATION

TO: HTI, a Radio Shack dealer


724 W. Main, Lewisville, Texas 75067

YES. Enroll me as a member in the TEXAS CONNECTION[™] and send your catalog of Tandy computer products I may purchase at just 8% above your normal wholesale prices. I will periodically receive newsletters which list special sales, factory-reconditioned equipment, and other cost saving specials. I am under no obligation to buy anything, now or in the future.

*Membership	1 Year	r 2 Years
	()\$8	
NOTE: Charter Member	ship — Free if you sign up be	fore May 31, 1987!
() Check enclosed () Visa		() Mastercard
		Expires:/
Name		
Address		Apt
City	State	Zip
Telephone ()		
My Computer (s) Tandy		Other
Signature X		
	(December of Commence broad to)	

1-800-843-0781

Quick Boot



Bypass the 1000's memory test on a warm reboot.

by Dave Rowell

ixteen seconds isn't longroughly the time a Tandy 1000 takes to test 640K of RAM during a reboot. If you reset your 1000 a few times a day, however, those 16-second delays can become annoying. IBM owners don't have to put up with this, nor do owners of other compatibles.

Now you don't either, because I've got

System Requirements

Tandy 1000 MS-DOS 2.x to 3.20 **GW-Basic or Microsoft** Assembler 1.0 or later a program that reboots Tandy 1000s without the memory test. With Reboot loaded, you press the control-alternate-delete key sequence and your 1000 hops to it, immediately loading in the boot sector from your start-up drive.

If you're uncomfortable with assembly language, you can create Reboot with a Basic program (Program Listing 1, Reboot.BAS). The sidebar describes how to do this (see p. 48) and how to make a Config.SYS file that loads Reboot when you, turn on your computer.

If you have an assembler, use Program = Listing 2, Reboot.ASM, written for Microsoft's MASM. Reboot is meant only for à Tandy's 1000 series. It is unnecessary on § other PC compatibles, which provide a warm boot without a memory test.

Reboot is a memory-resident program (Reboot.SYS) that loads as a device driver from a Config.SYS file. (I'll explain why a device driver later.) Once resident, it takes only 400 bytes of RAM. The program monitors keyboard input by filtering the keyboard hardware interrupt (9) and performs a warm boot when it detects the standard reboot key sequence (control-alternate-delete).

Easy to Remember

The BIOS keyboard-handler routine never gets to read the three-key combo, and the 1000's normal reboot procedure is avoided. I chose to usurp the standard reset sequence because it's one of the few key inputs that Microsoft Windows lets through to the BIOS keyboard handler. It's also easy to remember, and you've still got the red button if you need a full reboot.

The program reboots your 1000 by invoking the bootstrap-loader routine (interrupt 19 hexadecimal [hex] or INT 19H) that MS-DOS provides. INT 19H resets the boot drive, then loads and runs the boot program from the first sector of the boot disk.

The boot program loads the MS-DOS system files into memory, which in turn load Command.COM, and you've got your DOS prompt without the memory check. However, memory-resident programs and some device drivers create complications in both MS-DOS versions 2 and 3.

Under MS-DOS 2, the reboot sequence that INT 19H starts doesn't reset the addresses in the interrupt vector table to the original values that the ROM BIOS sets during the first boot.

Most memory-resident programs alter hardware-interrupt vectors to point to their own interrupt handlers in RAM. These handler routines are usually written over during DOS initialization, however, so that INT 19H leaves hardware-interrupt vectors pointing to inappropriate code.

When the clock chip, for instance, signals for an interrupt, as it does 18 times per second, the CPU executes the now-bogus code to which the clock-interrupt vector now points, and the computer freezes up.

To avoid the problems memory-resident programs create, Reboot stores all interrupt vectors that the 1000's ROM BIOS boot-up code sets. Reboot stores the first 32 vectors (zero–1FH), and 40H, 41H, and 44H during its installation as a device driver.

Later, when you initiate the three-key reboot, the program restores the saved interrupt vectors, zeroes out all other vectortable entries, and executes INT 19H. (To find which interrupt vectors the ROM sets, I wrote a boot-sector program that prints out the contents of the interrupt-vector table at boot-up.)

Reboot also stores and restores the equipment word (address 0:0410H) and the top-of-memory word (0:0413H). Ill-behaved programs sometimes change this important data in the BIOS data area and don't tell DOS about it.

I wrote Reboot as a device driver to get it working as soon as possible in the booting process. It's a Trojan horse to get a memory-resident program into operation before other device drivers and programs can alter the hardware interrupts. Fortunately, the DOS doesn't change any hardware-interrupt vectors before Reboot loads.

The program is a dummy device driver that performs no device functions except initialization. You must load Reboot.SYS before any device drivers that change hardware-interrupt vectors. Put it first in Config.SYS, except in unusual cases in which you must load another driver first.

Avoids Hang-ups

With MS-DOS 3.20, Microsoft attempted to protect INT 19H from the hang-ups that memory-resident programs cause. DOS 3.20 stores important vector values so that the 3.20 INT 19H can restore them before loading in the boot sector.

However, DOS 3.20 doesn't read and store the interrupts until all device drivers are loaded. If any device driver (including Reboot.SYS) intercepts hardware interrupts, INT 19H restores vectors pointing to the overwritten device-driver interrupt handlers, and booting fails.

Although the DOS 3.20 INT 19H interrupt-restore routine is in RAM (part of IBMBIOS.COM), DOS changes the INT 19H vector to point to it before loading device drivers, so Reboot can't bypass it. However, the 1000's MS-DOS 3.20 has a 1-byte flag at address 0070:1D1FH that determines whether the INT 19H will restore hardware interrupts.

If Reboot determines that it's running under 3.20, it sets that byte to zero, preventing INT 19H from changing the vectors that Reboot has restored. MS-DOS 3.10 does not attempt to restore hardware interrupts.

Even though Reboot.SYS is a dummy device driver, it must adhere strictly to device-driver format and rebuff any calls that could be made to it as a device (see "A Driver of Your Own Device," by Robert D. Covington, 80 Micro, July 1986, p. 40, for details).

The device header under the label Header (Listing 2) is standard for a serial device. It's important to make the actual device name in the header different from the name of the file itself. Once a device is installed, you can't copy, rename, or delete any file of the same name, no matter what the extension—a problem when you're debugging or experimenting with a new device driver. The name in the header is Rboot; the file itself is Reboot.SYS.

The driver-function request handler, starting at label INTR, takes requests from DOS, but any device function other than initialize (code zero) results in an immediate return with the done bit (8) set. DOS only requests the initialize function (label Install) once at boot-up.

Reboot's initialize function stores the important interrupt vectors and other information needed later, sets up the keyboard-interrupt vector (9) to point to a handler in Reboot, then frees up the now unneeded initialization code (placed at the end of the driver) so DOS can use that space.

First, the initialization routine gets the DOS version and stores it. Reboot must treat version 3.20 differently when it reboots. The DOS version function is one of the DOS services available to device drivers during initialization.

The DOS function for getting the vector of a particular interrupt is not available to device drivers. But because the vectors that Reboot stores are contiguous, the 8086 family's powerful string commands make getting and storing the two-word vectors quick and easy.

Saves Instructions

The segment:offset combination of DS:SI points to the source at the bottom of RAM, and ES:DI points to the destination table in Reboot. The CPU automatically increments the pointers SI and DI, saving a few instructions. The equipment list and top-of-memory words are found down in the BIOS data area starting at segment 0040 hex.

Before setting INT 9 to point to its own keyboard handler, Reboot saves the current INT 9 vector. For all key presses except the control-alternate-delete reboot combination, Reboot's keyboard handler will pass control to the original handler.

Again, the DOS interrupt-vector functions aren't available during device installation, so Reboot writes the new vector itself, first disabling maskable interrupts. Otherwise, you could press a key, and the keyboard-hardware interrupt could be called when its address was only halfchanged, freezing the computer.

After setting up its interrupt handler, Reboot displays a loading message, then sets the break address in the request header that DOS uses to communicate with the driver. Now that the installation code has done its job, Reboot casts it away, starting at the label Install (the break address).

Once installed, Reboot becomes a hardware-interrupt handler. The interrupt routine is never a working part of the device driver, but the driver sets it in place and activates it.

Reboot's interrupt handler monitors codes that the keyboard sends to represent key presses and releases. When it detects a press of the delete key (scan code 53H), Reboot checks a byte in the BIOS data area (address 0:417H) that keeps the status of special keys like the control and alternate keys.

If bits 2 and 3 of this byte are set, then both of these keys are currently pressed, and Reboot jumps to its reset routine. If the delete key isn't pressed, or both keyboard-status bits aren't set, Reboot sends control to the normal keyboard interrupt handler in ROM.

I used the string functions again to transfer the stored addresses back to the interrupt-vector table. Interrupt handlers can't easily use the DOS function that changes interrupt vectors, because the DOS services aren't re-entrant.

If a handler interrupts code that's in the middle of a DOS interrupt itself, calling DOS again destroys information on the DOS stack belonging to the interrupted code. In Reboot's case, it might not matter, because the warm boot wipes the slate clean anyway.

Regardless, I used the string functions because they're easier to use, given the large number of interrupts changed. Interrupts must be disabled (with the CLI instruction) when altering interrupt vectors to prevent a higher-priority hardware interrupt (only the clock in this case) from using a vector that's only half changed.

After restoring the equipment list and top-of-memory words, Reboot checks the DOS version. If it's version 3.20, the program zeroes the flag that determines whether or not DOS restores hardware interrupts itself. Reboot then clears the screen and resets the video mode to the boot-up default: 80-column black and white.

DOS must also have a stack area during reboot. Reboot uses the same one that the ROM BIOS sets up for the boot program—the top 256 bytes of the interrupt vector table.

The last step before invoking INT 19H is to signal the keyboard that it can send further scan codes and to signal the interrupt-controller chip that this interrupt is over. (See Dave's MS-DOS Column, 80 Mi-

Program Listing 1. Reboot.BAS. FILE.SIZE% = 615 OPEN "R",1,"REBOOT.SYS",1 'record size of 1 FIELD %1,1 AS X% PRINT "Creating REBOOT.SYS." FOR I% = 1 TO FILE.SIZE% : READ X LSET X%=CHR%(X) : PUT %1 : NEXT I% 1628 984 2871 2111 461 CLOSE 8 PRINT "REBOOT.SYS created." 9 END 11 DATA 255, 255, 255, 255, 8, 128, 22, 8, 33, 8 12 DATA 82, 66, 79, 79, 84, 32, 32, 32, 8, 8 13 DATA 8, 8, 46, 137, 38, 18, 8, 46, 148, 6 14 DATA 28, 8, 283, 81, 82, 86, 87, 38 15 DATA 6, 14, 31, 196, 62, 18, 8, 184, 8, 8 16 DATA 38, 138, 93, 2, 128, 251, 8, 117, 3, 232 17 DATA 77, 1, 13, 8, 1, 38, 137, 69, 3, 7 18 DATA 31, 95, 94, 98, 89, 91, 88, 283, 8, 8 19 DATA 36, 8, 8, 8, 8, 81, 17, 13, 51, 192, 142 21 DATA 216, 168, 23, 4, 36, 12, 68, 12, 116, 8 22 DATA 31, 88, 258, 46, 255, 46, 78, 8, 31, 88 23 DATA 14, 31, 198, 247, 8, 191, 8, 31, 88 23 DATA 185, 64, 8, 252, 258, 243, 165, 251, 185, 6 25 DATA 8, 184, 8, 8, 258, 243, 171, 251, 185, 18 26 DATA 8, 250, 243, 165, 251, 185, 118, 1, 184, 8 27 DATA 8, 250, 243, 171, 251, 161, 82, 9, 38, 163 28 DATA 16, 4, 161, 84, 8, 38, 163, 19, 4, 161 29 DATA 86, 9, 61, 3, 28, 114, 12, 184, 112, 8 30 DATA 142, 192, 187, 227, 31, 38, 198, 7, 8, 184 31 DATA 2, 9, 205, 16, 184, 9, 185, 16, 184, 48, 8 33 DATA 142, 208, 188, 9, 1, 258, 285, 16, 184, 48, 8 33 DATA 142, 208, 188, 9, 1, 258, 289, 12, 128 34 DATA 2, 208, 188, 9, 1, 259, 289, 12, 128 35 DATA 32, 230, 32, 226, 259, 205, 25, 8, 8, 8 36 DATA 8, 8, 9, 9, 8, 8, 8, 9, 8, 8 37 DATA 6, 8, 9, 9, 9, 9, 9, 9, 8 38 DATA 19, 9, 9, 9, 9, 9, 9, 9, 8 39 DATA 19, 9, 9, 9, 9, 9, 9, 9, 8 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 8 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9, 8 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9, 9, 9, 9, 9, 9, 9, 9, 9 30 DATA 19, 9 PRINT "REBOOT.SYS created." 384 2874 2048 2168 2057 2264 1969 2135 1776 2365 2199 2232 2256 2473 2298 2360 2359 2170 2149 2380 2110 2368 2329 2188 1615 1616 Listing 1 continued

How to Create and Use Reboot.SYS

Using the Basic that comes with your Tandy 1000 and Program Listing 1, you can create Reboot.SYS. After loading Basic, type in the listing and save it as Reboot.BAS. Running Reboot.BAS from Basic creates the file Reboot.SYS. Copy the newly created Reboot.SYS to your boot-up disk.

You load Reboot.SYS and make it active in a file called Config.SYS. If there is no Config.SYS on your boot disk, you can use the Copy command to create it by typing the following three lines at the DOS prompt:

COPY CON CONFIG.SYS DEVICE = REBOOT.SYS

The third line is the end-of-file marker (control-Z). To enter this line, press F6 and then the enter key. DOS then creates a file named Config.SYS with the line DEVICE = REBOOT.SYS.

If you already have a Config.SYS file on your boot disk, you must edit it and insert a new first line containing DEVICE = REBOOT.SYS. You can use Edlin or any word processor that creates pure ASCII files. You can also use the following series of DOS commands to add a new first line to Config.SYS:

REN CONFIG.SYS CONFIG.ADD
COPY CON CONFIG.SYS
DEVICE = REBOOT.SYS
^Z
COPY CONFIG.SYS + CONFIG.ADD
TYPE CONFIG.ADD
TYPE CONFIG.SYS

The first command renames the existing Config.SYS. Then the Copy command creates a new Config.SYS file containing DEVICE = REBOOT. SYS. (See above for instructions on this particular process.) The next Copy command appends the old Config.SYS (Config.ADD) onto the new Config.SYS.

Use the two type commands to make sure the new Config.SYS is the same as the old, but with the new first line that loads Reboot.SYS. If the new Config.SYS meets your approval, delete Config.ADD.

To activate Reboot, make sure both Reboot.SYS and your new Config.SYS are in the root directory of your boot disk. Then reboot your computer. You should see a message indicating that the Reboot driver is loaded. Your computer should function as usual after this procedure.

To activate a warm boot without a memory check, hold down the control and alternate keys, and press the delete key. As with a normal reset, don't invoke Reboot during a normal drive operation. You could damage the disk directory.

Reboot works on Tandy 1000s with MS-DOS version 2 or 3 up to version 3.20. If it ever happens that Reboot doesn't respond to the three-key reset sequence, or it fails to boot properly, you can always resort to your 1000's red reset button.

READ, WRITE, FORMAT TRS-80 DISKS IN A PC

TRANSFER ANY MOD I/III/4 FILE CONVERT BASIC PROGRAMS for use on the IBM PC, XT, AT and TANDY PC's

Conv3toPC V2.0 "Convert Mod I/III to PC package." \$139.95 Includes Hypercross Mod I/III to TRANSFER any Mod I/III file or BASIC program to a PC/MS-DOS Diskette, and Cnv3toPC.BAS to CONVERT 95% or more of each transferred BASIC program to PC BASIC syntax. Mod I's need a "disk doubler" to run

Conv4toPC V1.0 "Convert Mod 4 to PC package." \$139.95 Includes Hypercross Mod 4 to TRANSFER any Mod 4 file or BASIC program to a PC/MS-DOS Diskette, and Cnv4toPC.BAS to CONVERT 95% or more of each transferred BASIC program to PC BASIC syntax.

> ".. Conv3toPC has saved me months of work!" ".. Conv4toPC is the best conversion package I ever used."

AVAILABLE WORLDWIDE through Radio Shack's Express Order Software

Conv3toPC V2.0 Catalog #90-0345

Conv4toPC V1.0 Catalog #90-3100

Important note: Every converted BASIC program will require some user editing (the 5% or less) before it will run on a PC. To facilitate such revisions, every keyword that may need manual attention is flagged and our user guides explain why and what needs to be done. For most programs, a casual knowledge of BASIC is sufficient to make the changes. However, if a BASIC program contains machine language, it will be extremely difficult for the average user to handle some of the necessary manual revisions!

Please feel free to call us if you have any questions or doubts about whether these packages are right for you. We will candidly answer all your questions and send you our free demo disk (\$2.00 for S/H). Or, order either package; read through the entire user guide for complete details; then, if you decide it doesn't suit your needs, return it for a full refund—less a \$10.00 restocking fee. Refunds will NOT be granted if the sealed bag containing the program diskettes has been opened!

OTHER EMSI SOFTWARE

PCXZ 1.0 Cross-Zap Utility for PC/MS-DOS

Now, from The Author that brought you Hypercross, HyperZap and SuperCross comes an amazing new program for owners of Tandy 1000, 1200, 3000 and true PC compatibles. PC Cross-Zap allows you to read all double density TRS-80 type disks on your PC. Not only that, PCXZ offers many of the features that TRS-80 owners have long enjoyed with Hypercross and Hyperzap.

PC Cross-Zap is a utility program that runs on your PC or PC-compatible. With it you can copy files to or from TRS-80 disks at will. You can also format a disk, copy disks, explore, read and write sector data, repair bad directories and much more. Long after your TRS-80 is gone you will still be able to read your old disks. Even when your TRS-80 disks are gone you can continue to use PCXZ to read, fix and modify MS-DOS and other disks so your investment will never be lost.

\$139.95

\$99.95

\$139.95

With PCXZ you can format a TRS-80 disk (not the mixed density Model I types). You can copy files from a TRS-80 disk error free, without losing any data. Just like HyperCross.

Formats Supported Model I mixed density DOS+ 3.4, DoubleDOS, LDOS (SOLE), MultiDOS, NEWDOS 80 V2, TRSDOS 2.7/8. Model I/III Double Density. DOS + 3.5, LDOS 5.1 Model III: DOS+ 3.4, MultiDOS, NewDOS 80, TRSDOS 1.3 Model 4/4P: MultiDOS, DOS + 4, TRSDOS 6. Max-80: LDOS 5.1. All formats also supported in double sided, 35, 40 and 80 tracks were appropriate. For 80 track formats you must have an 80 track drive on your PC

Systems Requirements PC,XT,AT or compatible, Tandy 1000 or 1000Ex (needs DMA), 1000 SX, 1200, 3000 with at least one 40 track drive and 256K minimum memory.

Cnv4toPC.BAS (No Hypercross) \$99.95 HYPERCROSS MOD I/III \$49.95 **HYPERCROSS MOD 4** \$49.95 \$24.95 CROSS REFERENCE For PC BASIC programs. Referenced variables, line #s, keywords.

Conv3toPC V2.0 (Complete)

Conv4toPC V1.0 (Complete)

Cnv3toPC.BAS (No Hypercross)

FASTSORT \$24.95

Machine language SORT callable from PC BA-SIC. Excellent replacement for Mod III CMD "O" command.

\$39.95 PEEKs 'N POKES

Utilities for PC BASIC programmers. Call for details, or see Oct. 86 review in 80 Micro.

STAY-RES QuickBasic 1.1, 2.0.

INSIDE TRACK More utilities for PC BASIC programmers. Call Solve mixed number arithmetic problems on your for details, or see Oct. 86 review in 80 Micro.

NEW!! A tool chest of routines that do for PC BASIC LOGIC and DEDUCTION

AND BETTER did for Mod III BASIC. QuickBASIC V2.0

hanced functions.

800-922-0786

New!! \$89.95 Demo \$5.00 NORTON UTILITIES V3.1

Write your own memory resident pop up pro- Industry standard for directory & file recovery. grams (ala Side Kick) in PC-BASIC. Requires Also, modify file attributes, search/sort directories etc, etc.

\$59.95 FRACTION CALCULATOR \$24.95

PC. Exact common fraction answers without dec-\$69.95 imals. Instruction mode great for children.

\$24.95

what Rosenfelder's fantastic BASIC FASTER Full color Mastermind game for the PC to challenge any age. Play 1-9 columns, 2-5 colors, direct or indirect hints. Have fun while improving Compile PC BASIC programs for speed and en- your powers of deductive reasoning. Requires color monitor/adapter.

Prices subject to change without notice.

EDUCATIONAL MICRO SYSTEMS, INC.

PO Box 471, Chester, New Jersey 07930



EMSI direct order terms: VISA, Mastercard, MO, check or COD. Add \$3.00 shipping/handling. Add \$1.90 for COD. Foreign or first class, add first class postage (package wt. 21 lbs.). NJ residents add 6% sales tax.



WHY PAY MORE... When you can own for MUCH LESS!



Enjoy year round Sale prices with credit card convenience or special discount prices for Cash Purchases.

Same day processing for speedy delivery

Special 30 day return policy.

FULL CATALOG SELECTION

Customer Service 9 AM to 5 PM Texas time

BIG D COMPUTERS

ROANOKE CENTER-ROANOKE, TX 76262

CALL 1-800-FOR BIG D (1-800-367-2443)







in Texas call (817)491-2461

```
Isting I continued

39 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

40 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

41 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

42 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

43 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

44 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

45 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

46 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

47 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

48 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

49 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

50 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

50 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

50 DATA 0, 0, 0, 0, 0, 0, 0, 0, 0, 0

51 DATA 33, 163, 86, 0, 36, 7, 191, 247, 0, 196

52 DATA 0, 0, 142, 222, 185, 64, 0, 252, 243, 165

53 DATA 190, 0, 1, 185, 10, 0, 243, 165, 14, 31

54 DATA 51, 192, 142, 192, 38, 161, 16, 4, 163, 82

55 DATA 0, 38, 161, 19, 4, 163, 84, 8, 191, 36

56 DATA 0, 38, 161, 19, 4, 163, 84, 8, 191, 36

56 DATA 33, 140, 77, 2, 251, 180, 9, 186, 244

59 DATA 1, 205, 33, 95, 7, 186, 139, 1, 38, 137

68 DATA 55, 14, 38, 140, 77, 16, 184, 0, 0, 195

61 DATA 10, 18, 18, 84, 49, 40, 48, 48, 32, 82

62 DATA 101, 98, 111, 111, 116, 32, 100, 114, 105, 118

63 DATA 101, 114, 32, 108, 111, 97, 100, 101, 100, 46

64 DATA 32, 32, 32, 32, 32, 60, 67, 116, 114, 108

65 DATA 45, 65, 108, 116, 45, 68, 101, 108, 62, 13

66 DATA 45, 32, 56, 48, 32, 77, 105, 99, 114, 111

69 DATA 32, 77, 97, 103, 97, 122, 185, 110, 101, 110

70 DATA 19, 10, 36, 87, 114, 105, 116, 116, 101, 118

71 DATA 32, 98, 121, 32, 68, 97, 118, 101, 32, 82

Program Listing 2. Reboot.ASI
Listing 1 continued
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    1618
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    1613
1614
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       1616
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       1618
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    1948
2214
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2384
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2374
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2190
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2224
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2175
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2539
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    2387
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2398
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    2333
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                    2415
                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                       2326
```

Program Listing 2. Reboot.ASM

reboot

'REBOOT.SYS --- Tandy 1888 device to reboot quickly'

REBOOT.ASM When you press Ctrl-Alt-Del on a Tandy 1888, an involved reboot is initiated. (On the IBM only a short boot with no memory test occurs.)

Listing continued

cro, November 1986, p.80, for details on the workings of the keyboard and interrupt hardware.) Reboot sends several end-of-interrupt signals to the interrupt-controller chip in case any lower-priority hardware interrupts are pending. Finally, Reboot initiates a warm boot with INT 19H.

Interrupts are kept enabled during Reboot's resident routine (with the STI instruction), so the the clock-tick interrupt (INT 8) can continue to update the system timer. All other hardware interrupts are lower priority; therefore, they are disabled until the end-of-interrupt signal is sent to the interrupt-controller chip.

Further Reading

If you're interested in this kind of programming, here are two books you'll find helpful: Advanced MS-DOS, by Ray Duncan (Microsoft Press, 1986), covers interrupt handlers, device drivers, and the booting process. The Norton Programmer's Guide to the IBM PC, by Peter Norton (Microsoft Press, 1985), covers interrupt handlers, system information stored in low memory, and other topics.

Dave Rowell is a staff writer for PC Resource magazine. Write to him c/o 80 Micro, 80 Elm St., Peterborough, NH 03458.

MODEL 4P USERS!

INTRODUCING THE TELETRENDS MODEL TT5512P 300/1200 INTERNAL CARD MODEM

TT512P

Haves Compatibility Adaptive Equalization High Speed Signal for Use with BBS Tone and Pulse Dialing FCC Part 68 and 15 Registration

Auto Answer-Dial-Speed Select Call Progress Messages Dual RJ11C Modular Telephone Plugs Full 2 Year Warranty \$179.95 \$129.95 (Offer expires May 31, 1987)

NEW!! TT5 EXTERNAL STANDALONE

All the Features of the Model TT512P 7 LED Indicators Speaker with Volume Control \$199.95

24 HOUR DATA INFORMATION/ORDER (714) 554-7400 VOICE (714) 554-7401

Teletrends parts and products namufactured in the USA. e 385 on Reader Service card.



TELETRENDS CORPORATION


Box 2198 Garden Grove, CA 92642

yes is a trademark of Hayes Microcomputer Products

Tandy is Dandy

...until you want MORE!

USER INSTALLABLE BOARDS FOR TANDY 1000/3000



MULTIFUNCTION

Model 1000 provides DMA and an additional 512K of memory bringing your 128K Tandy 1000 to 640K, serial port, RAM disk and print spool software. Clock calendar is optional.

2008 512K-\$249

Model 1000SX additional 256K of memory, bringing your 384K Tandy 1000SX to 640K, serial port, RAM disk and print spool software.

Clock calendar with 20 year battery is optional.

2027 256K-\$199

Model 1000SX, 1000EX and 3000 one serial and one parallel port. Second serial port and clock calendar with 20 year battery are optional.

2028 1 serial for Model 1000SX + 1000EX-\$99

2029 1 serial for Model 3000HL-\$149

2030 2nd serial-\$49

Dr. Dr. Zucker

2031 2nd serial - \$79

VIDEO PRODUCTS AVAILABLE TOO! JUST CALL AND ASK. Offer Expires March 31, 1987



ZUCKERBOA



235 Santa Ana Court • Sunnyvale, CA 94086 • (408) 720-1942 • CA (800) 654-2212 • US (800) 222-4920

ZUCKERBOARD is a registered trademark of Advanced Transducer Devices Inc.

Tandy 1000/3000 are Trademarks of Radio Shack, a Division of Tandy Corporation.

ZUCKERBOARD

Price List

Part #	Price				
	Tandy 1000				
2002	Memory Expansion With 256K	\$109			
2003	Memory Expansion With 512K	\$149			
2004	Clock/Calendar Option	\$ 49			
2006	Secondary Expansion Memory With 256K	\$109			
2007	Secondary Expansion Memory with 384K	\$125			
2009	Multifunction Board With 512K, Serial, And Clock	\$279			
2016	Hard Disk Card	\$599			
	Tandy 1000SX				
2006	Memory Expansion With 256K	\$109			
2027	Multifunction Board With 256K, Serial, And Clock	\$199			
2016	Hard Disk Card	\$599			
	Tandy 3000HD and HL				
2017	Hard Disk Card For HL	\$599			
2033	Serial Port Board for HD	\$139			
2034	Second Serial Port For 2033	\$ 79			
2036	Multifunction Board For HL With 128K, Serial, And Clock	\$199			
Та	ndy 1000, 1000SX, and 3000HL				
2004	Clock/Calendar Chip Option	\$ 49			
2031	Clock/Calendar Board With Software	\$ 59			
2029	Serial Port Board	\$ 99			
2030	Second Serial Port For 2029 And 2027	\$ 49			
2035	MS DOS 3.2 With GW BASIC	\$ 89			

ZUCKERBOARD

Model	Qty.	Unit Price	Ext. Price
TANDY 1000			
2002		\$109	
2003		149	
2004		49	
2006		109	
2007		125	
2009		279	
2016		599	
TANDY 1000SX			
2006		109	
2027		199	
2016		599	
TANDY 3000			
2017		599	
2033	-	139	
2034		79	
2036		199	
TANDY 1000, 1000SX, 3000		-	
		49	
2004		_ 59	
2031		99	
2029		40	_
2030 2035		89	
2035		_ 69	
Subtotal			
CA Residents add applicable tax			
Shipping \$6.00 per product in the U.S.			
Total			
Name			
Address			
City, State			
Phone			
Visa MasterCard		Amex 🗆	
Number	Ex	pires	
Check or Money Order			
please allow 2-4 weeks delivery.			

TUCKERBOARD

Check or Money Order please allow 2-4 weeks delivery.

Model	Qty.	Unit Price	Ext. Price
TANDY 1000			
2002		\$109	
2003		149	
2004		49	
2006		109	
2007		125	
2009		279	_
2016		599	
TANDY 1000SX			
2006		109	
2027		199	
2016		599	
TANDY 3000			
2017		599	
2033		139	
2034		79	
2036		199	
TANDY 1000, 1000SX, 3000			
2004		49	
2031		. 59	
2029		99	-
2030		49	
2035	-	89	
Subtotal			
CA Residents add applicable tax			
Shipping \$6.00 per product			
in the U.S. Total			
Name			
Address			
City, State			
Phone			
Visa ☐ MasterCare	d 🗆	Amex 🗆	
Number	P	pires	

Sunnyvale, CA 94089 235 Santa Ana Court ATTENTION: DR. DR. ZUCKER

POSTAGE WILL BE PAID BY ADDRESSEE FIRST CLASS

PERMIT NO. 1625

BUSINESS REPLY CARD

SUNNYVALE, CA

MAILED IN THE UNITED STATES NO POSTAGE NECESSARY

ADVANCED TRANSDUCER DEVICES, INC.


FIRST CLASS BUSINESS REPLY CARD **PERMIT NO. 1625** SUNNYVALE, CA

POSTAGE WILL BE PAID BY ADDRESSEE

ATTENTION: DR. DR. ZUCKER ADVANCED TRANSDUCER DEVICES, INC.

Sunnyvale, CA 94089

235 Santa Ana Court



UNITED STATES NO POSTAGE MAILED

It's another **CKERBOARD**

Price List

Part #	Price				
	Tandy 1000				
2002	Memory Expansion With 256K	\$109			
2003	Memory Expansion With 512K	\$149			
2004	Clock/Calendar Option	\$ 49			
2006	Secondary Expansion Memory With 256K	\$109			
2007	Secondary Expansion Memory with 384K	\$125			
2009	Multifunction Board With 512K, Serial, And Clock	\$279			
2016	\$599				
	Tandy 1000SX				
2006	Memory Expansion With 256K	\$109			
2027	Multifunction Board With 256K, Serial, And Clock	\$199			
2016	\$599				
	Tandy 3000HD and HL				
2017	Hard Disk Card For HL	\$599			
2033	Serial Port Board for HD	\$139			
2034	Second Serial Port For 2033	\$ 79			
2036	Multifunction Board For HL With 128K, Serial, And Clock	\$199			
Та	ndy 1000, 1000SX, and 3000HL				
2004	Clock/Calendar Chip Option	\$ 49			
2031	Clock/Calendar Board With Software	\$ 59			
2029	Serial Port Board	\$ 99			
2030	Second Serial Port For 2029 And 2027	\$ 49			
2035	MS DOS 3.2 With GW BASIC	\$ 89			

Specially Selected

by the Editors of 30 Micro...

HERE'S WHAT YOU WILL GET...

ow on disk and ready for action! A special vear-end collection of the very best programs published by 80 Micro in 1986. Business programs, utilities, graphics, and applications... they're the best programs from a whole year of the #1 magazine for Tandy users!

And as a special convenience, our tech editors have compiled separate Best of 1986 disks for the Model III and Model 4, each with its own on-disk documentation.

The Best 1986

The Best of 1986 — Model III:

Commando - Build macros that let you set program parameters with a single command and customize DOS commands.

Trace - Trace and locate assembly language bugs.

Copykey - Copy text from one part of your screen to another in Basic and enter Basic keywords by pressing shifted letter

Wildcard - Three wildcard utilites for copying, killing, and attributing files.

Easydata - Design a database with sorting capabilities.

Unpatch - Automatically reverses patches for removal.

Index - Set up a commented disk

Precision - Calculate double precision mathematical results for an octet of basic math functions.

Microtab - Record and tabulate statistical data.

Makedata - Enter data statements automatically for fast entry of machine language code from Basic.

Crypt - Encrypt and decrypt your private text code.

Teaser - Create and solve long division puzzles.

Hamcode - Make your file recoverable with a matching parity check file.

The Best of 1986 - Model 4:

Sounder - Enhance your Model 4's sound capability.

Basic Data Base Management System - Customize your own database

Restored Art - Use this machine language subroutine to add graphic commands to Basic.

Helper - Create customized help files.

Extended Command Interpreter Provide multiple commands on a single line in DOS and a history of the last ten command lines executed.

Timer - Measure your elapsed computer

Diskcat - Catalog up to 800 files in a master disk directory.

Framer - Add Get and Put to your Model 4 graphic commands.

Mark 4 - Keep track of school grade records.

Precision - Calculate double precision mathematical results for an octet of basic math functions.

Microtab - Record and tabulate statistical

Makedata - Enter data statements automatically for fast entry of machine language code from Basic.

Crypt - Encrypt and decrypt your private text code.

Teaser - Create and solve long division puzzles.

Hamcode - Make your file recoverable with a matching parity check file.

Send me The Best of 1986 disk(s) for just \$21.45 each! If I order both the Model III and Model 4 versions, I save \$5 off the total price (2 disks for \$37.90)!

Model III Model III
dual drive version single drive version Model III

■ Model 4 version

☐ Payment Enclosed ☐ Visa ☐ AmEx ☐ MC Card # _____Exp. Date ___

State_ Price includes postage and handling. Foreign airmail, please add \$1.90 each

Model III and Model 4 are registered trademarks of Radio Shack, a division of **Tandy Corporation**

Mail to: Load 80, Elm Street, Peterborough, NH 03458

ith the holidays right around the corner, The Best of 1986 is just the thing to brighten up your favorite Tandy user's Christmas! Order today for Christmas giftaivina!

Return the coupon or attached order card today, or Call Toll Free

1-800-258-5473

In New Hampshire, dial 1-924-9471

```
Listing continued
Listing continued
                                                                                                              es
   ; Many people with 640K of memory find waiting 16 seconds for a memory
                                                                                                     pop
                                                                                                              ds
   t check annoying. This program (Reboot) monitors keyboard input, and
                                                                                                     pop
                                                                                                              di
   performs a warm reboot when you press the reboot key combination.
                                                                                                     pop
                                                                                                              gi
   dx
                                                                                                     pop
                                                                                                     pop
                                                                                                              CX
                                   :offset from 0 of equipment list word
   equipment_adr
                            410B
                                                                                                              bx
                                                                                                     pop
   memorytop_adr
                            413H
                                    offset of top-of-memory word
                   equ
                                                                                                     pop
                                                                                                              av
   keystatus_adr
                            417H
                                   :offset of keyboard status byte (0:417H)
                   equ
                                   ; segment where DOS 3.20 IBMBIOS.COM resides
                           0070H
   dos320bios_seg
                   equ
                                                                                                                              ; far return to DOS
                                   offset of DOS 3.20 INT 19H flag
   dos320flag adr
                   equ
                           lfe3H
                                                                                              : Resident Int 9 handler. If Ctrl-Alt-Del pressed, reboot initiates reset
           segment public 'CODE'
                                           ; code segment begins
   code
                                                                                              ; without memory check.
   REBOOT proc
                    far
                                                                                              keyboardint
                                                                                                              44
                                                                                                                                      storage of previous BIOS INT 9 vector
                                                                                              equipment
                                                                                                              dw
                                                                                                                                      storage of original equipment word
                                           ;device drivers originate at 0
                                                                                              memorytop
                                                                                                              dw
                                                                                                                                      storage of original top-of-memory
                                                                                              dosversion
                                                                                                              dw
                                                                                                                                      ; version of MS-DOS
           assume cs:code, ds:code, es:code
                                                                                              ; The keyboard interrupt handler (short and quick) starts here.
   ; Header for device driver.
                                                                                              keyboard:
                                    :-1 means end of list (DOS will change)
   header dd
                                                                                                     sti
                                                                                                                              ; enable interrupts (only the clock)
                    RABAR
                                    ;device attribute word (character device with
           dw
                                                                                                     push
                                                                                                                              ; used registers must be restored
                                                                                                             ax
                                           no special properties)
                                                                                                     push
                                                                                                              ds
           dw
                    ctrat
                                    strategy entry point
                                                                                                     in
                                                                                                             a1.60H
                                                                                                                              ;read 8255A-5 (PPI) keyboard data
           dw
                    intr
                                    ;interrupt entry point
                                                                                                             al,53H
                                                                                                                              ; Is it Del key scan code?
                                                                                                     CMD
                                    ;8-character device name (3 blanks at end)
           db
                    'RBOOT
                                                                                                              out
                                                                                                                              ; if not the Delete key
                                                                                                     jne
                                                                                                     xor
                                                                                                                              ; point ds to memory bottom
                                                                                                             ax,ax
   : Local storage for DOS-passed request header address.
                                                                                                     mov
                                                                                                             ds.ax
                                                                                                     mov
                                                                                                             al,ds: byte ptr keystatus_adr ; get keyboard status byte
   req_head
                                                                                                                              :mask for Ctrl and Alt bits (243)
                                                                                                     and
                                                                                                             al,12
                                                                                                     CMD
                                                                                                             al, 12
                                                                                                                              ; is Ctrl/Alt key combo active?
   ; Strategy routine for device driver stores address of request header
                                                                                                     je
                                                                                                              reset
                                                                                                                              ; if yes, then reboot
   ; passed in es:bx by DOS.
                                                                                             out:
                                                                                                     pop
                                                                                                             de
                                                                                                     pop
                                                                                                             ax
   STRAT proc
                   far
                                                                                                     cli
                                                                                                                              :disable maskable interrupts
                                                                                                     jmp
                                                                                                             cs:keyboardint
                                                                                                                              ; pass to old int. service routine
           mov
                   word ptr cs:[req_head],bx
                                                    ; request header offset
                   word ptr cs:[req_head+2],es
                                                    request header segment
           mov
                                                                                              reset: pop
                                                                                                             ds
                                                                                                                              ; restore used registers
           ret
                                                    :far return to DOS
                                                                                                     pop
                                                                                                             ax
   STRAT endp
                                                                                              ; Restore ROM interrupt vector table from int_table. Zero out rest of vector
                                                                                              ; area. ds:si is source and es:di is destination for string block moves.
   ; Interrupt routine for device driver handles all function requests. It
   ; grabs necessary information from request header pointed to by req_head.
                                                                                                                                      ; point ds to this segment
   ; This is a dummy driver. If the request command code in the header is 0
                                                                                                     push
                                                                                                     pop
   ; (initialize), it sets up the Reboot resident keyboard interrupt handler
                                                                                                     mov
                                                                                                             si, offset int_table
                                                                                                                                      :ds:si is source (int_table)
   ; in memory. This happens only once (during device installation). With any
                                                                                                     mov
                                                                                                             di,0
                                                                                                                                      ;point es:di to 0:0--real vector table
   ; other code, a dummy routine sets the return status to done and returns.
                                                                                                     mov
                                                                                                             es,di
                                                                                                     mov
                                                                                                             cx,64
                                                                                                                                      ; move 64 words from table
           proc
   INTR
                   far
                                                                                                     cld
                                                                                                                                      ;direction up
                                                                                                     cli
                                                                                                                                      ; no interrupts allowed while changing
           push
                   ax
                                                                                              rep
                                                                                                     movsw
                                                                                                                                      :block word move til cx=0
           push
                   bx
                                                                                                     sti
                                                                                                                                      reenable interrupts
           push
                   CX
                                                                                                     mov
                                                                                                             Cx.64
                                                                                                                                      ; going to fill next 64 words with 0
                   dx
           push
                                                                                                     mov
                                                                                                              ax,0
                                                                                                                                      :from AX
           push
                   si
                                                                                                     cli
                   di
           push
                                                                                              rep
                                                                                                     stosw
                                                                                                                                      ;store 64 0 words, only di increments
           push
                   ds
                                                                                                     sti
           push
                                                                                                     mov
                                                                                                              cx, 10
                                                                                                                                      ; move ten stored words
                                                                                                     cli
                                   ; use ds for local data
           push
                   CS
                                                                                              rep
                                                                                                                                      ;from ds:si to es:di
                                                                                                     MOVSW
           pop
                    ds
                                                                                                     sti
                                                                                                     mov
                                                                                                              cx,374
                                                                                                                                      ;374 words in table above int 44H
                                   ;point es:di to request header
           les
                    di,[req_head]
                                                                                                     mov
                                                                                                             ax.0
                                                                                                                                      :fill with 0s
                                    ; set zero for initial status word
           mov
                   ax.0
                                                                                                     cli
                                    ; put command byte in bl
           mov
                    bl, es: [di+2]
                                                                                              rep
                                                                                                     stosw
                                    ; is it zero (initialize)?
           cmp
                   b1,0
                                                                                                     sti
                    intout
                                    ; if not then dummy device return
           jne
                                    ;install memory resident Reboot
                    install
                                                                                             ; Restore original equipment list and top-of-memory word. (es still at 0.)
                                    ; set done bit (8) in status word
   intout: or
                    ax,0100H
                                                                                                              ax, equipment
                    es: [di+3],ax
                                   return status to request header
                                                                                                     mov
                                                                                                             es:word ptr equipment_adr,ax
```

;get stored word ; put back in data area Listing continued

```
80
Micro,
May
```

```
Listing continued
                                                                                           Listing continued
                                                                                                                                        ;point es:di to the table (dest.)
                                                                                                               di, offset int_table
                                                     ; same with top-of-memory
                                                                                                       mov
            mov
                    ax, memorytop
                    es:word ptr memorytop_adr,ax
                                                                                                       mov
                                                                                                               si.0
                                                                                                                                        ;point ds:si to 0:0 (source)
            mov
                                                                                                               ds.si
                                                                                                       mov
                                                                                                                                        ; move 64 words (32 2-word vectors)
    : If MS-DOS version 3.2, change INT 19H flag in RAM section of BIOS to zero.
                                                                                                       mov
                                                                                                               cx,64
                                                                                                                                        :direction up
    ; This section will have to be augmented for future versions of MS-DOS.
                                                                                                       cld
                                                                                               rep
                                                                                                       movsw
                                                                                                                                        :block word move
                                                                                                       mov
                                                                                                               si.0100H
                                                                                                                                        :ds:si points to int vector 40
                     ax, dosversion
                                             : get dos version
                                             ; jump if not 3.20 (al=3; ah=14H=20)
                                                                                                                                        ;10 more words
            cmp
                     ax.1403H
                                                                                                       mov
                                                                                                               cx,10
                                                                                                                                        ;es:di points to next table space
                                                                                               rep
                                                                                                       movsw
            jb
                    cls
                     ax, dos320bios_seg
                                                                                                       push
                                                                                                               CS
            mov
                                                                                                       DOD
                                                                                                               ds
                                                                                                                                        ; restore ds to this segment
            mov
                     es.ax
                     bx,dos320flag_adr
            mov.
                    byte ptr es: [bx],0
                                                                                               ; Store equipment byte and top-of-memory.
            mov
    ; Clear screen with BIOS video interupt (10H). (At this point, the BIOS
                                                                                                                                                 point es to memory bottom
                                                                                                       xor
                                                                                                               ax,ax
    ; interrupt is pure, and only the clock hardware interrupt is working.)
                                                                                                       mov
                                                                                                               es,ax
                                                                                                                                                :qet current equipment list
                                                                                                       mov
                                                                                                               ax, es: word ptr equipment_adr
                                     :set video-80x25 black & white
                                                                                                       mov
                                                                                                                                                 store here
    cls:
            mov
                     ax.0002H
                                                                                                                equipment, ax
                                                                                                               ax, es: word ptr memorytop_adr
                                                                                                                                                same for top-of-memory
            int
                     108
                                     :BIOS video services call
                                                                                                       mov
                     ах.0600Н
                                     :initialize (clear) screen
                                                                                                       mov
                                                                                                               memorytop, ax
            mov
                                     gray on black
            mov
                     bh,7
                                                                                               ; Get and save current address of INT 9 so that resident Reboot can pass
                                     supper left corner (0,0)
            mov
                    CX.0
                    dx,184fH
                                                                                               : control to the original interrupt routine. (es still at 0.)
                                     ; to bottom right corner (24,79)
            mov
            int
                                                                                                                                                 address of int 9
                                                                                                                                                es still at 0
                                                                                                       mov
                                                                                                               ax, es: [di]
    ; Set up new stack area using top 128 words of interrupt vector table (used
                                                                                                               word ptr ds:keyboardint,ax
                                                                                                                                                 store int vector offset
    ; by ROM during booting). (128 words = 256 bytes = top 1/4 of table.)
                                                                                                       mov
    ; No interrupt can occur immediately after a 8088 segment register is changed,
                                                                                                       mov
                                                                                                               ax, es: [di+2]
                                                                                                               word ptr ds:keyboardint+2,ax
    ; so no need for disabling interrupts between changing ss and sp.
                                                                                                                                                store int vector segment
                                                                                                       mov
                                                                                               ; Reset low-level keyboard interrupt to point to Reboot routine.
                     ax, 30H
                                     :segment 30H same as 0:300H
            mov
            mov
                     ss,ax
                                                                                                               ax, offset keyboard
                                     ; stack pointer is stack "bottom" (0:400H)
                                                                                                       mov
            mov
                     Sp, 100H
                                                                                                       cli
                                                                                                                                        ; disable maskable interrupts
    , Reenable keyboard input (via programmable peripheral interface-PPI) and
                                                                                                       mov
                                                                                                               word ptr es: [di],ax
                                                                                                                                        :new offset
                                                                                                               es:[di+2],cs
                                                                                                                                        inew segment
    ; send end-of-interrupt signal to programmable interrupt controller (PIC).
                                                                                                       mov
                                                                                                       st i
                                                                                                                                        ; reenable interrupts
                                     ; disable interrupts
            cli
            in
                     al,61H
                                     Port B of 8255A-5 PPI
                                                                                               ; Display driver loading message.
                     а1,80н
                                     ;toggle keyboard clear bit on
            or
                                                                                                               ah,9
                     61H,al
                                                                                                       mov
            out
                     al,7fH
                                     ;off (bit 7 of Port B)
                                                                                                       mov
                                                                                                               dx, offset message
            and
                                                                                                       int
            out
                     61H,al
            mov
                     cx,3
                                     ; count for eoi loop
                     al,20H
                                     ;end of interrupt for 8259A PIC
                                                                                               : Set break address in request header to cut off installation procedure.
    eoi:
            mov
            out
                     20H.al
                                     ; (port 20H) -- 2 extra just in case lower
                                                                                                                                        recover request header address
                                     priority hardware interrupts are pending
            loop
                     eoi
                                                                                                       pop
                                                                                                                25
                                     :ROM bootstrap loader (finally)
            int
                     19H
                                                                                                       mov
                                                                                                                dx.offset install
                                                                                                                                         end of resident code
                                                                                                       mov
                                                                                                                es: [di+14].dx
                                                                                                                                         ;offset of driver end
    ; Storage table for initial ROM vector table.
                                                                                                       mov
                                                                                                                es:[di+16],cs
                                                                                                                                        segment of driver end
                             64 dup (0)
                                             groom for the first 32 vectors
                                                                                                       mov
                                                                                                                ax, Ø
    int_table
                                                                                                                                        ; zero out status word
                             10 dup (0)
                                             room for vectors 48-44
                                                                                                        ret
                                                                                                                                        ;near return
    ; Start of installation routine. Memory from here on will be released
    : after initialization.
                                                                                               ; Data for installation (nonresident).
    INSTALL proc
                                                                                               message
                                                                                                                        13,10,10
                     near
                                                                                                                        'T1000 Reboot driver loaded.
                                                                                                                db
                                                                                                                                                          <Ctrl-Alt-Del>'
                                             ; save address of request header
            push
                                                                                                                db
                                                                                                                        13,10,' Copyright 1987 -- 80 Micro Magazine'
                                                                                                                        13,10,10, '$'
                                                                                                                db
                     di
            push
                                                                                                                        'Written by Dave Rowell'
    ; Get and store DOS version so that DOS versions 2 and 3 can be treated
    ; differently. This DOS function call is available at driver installation.
                                                                                               INSTALL endp
                                             :DOS version function call
            mov
                     ah.30H
                                                                                               INTR
                     21H
                                                                                                        endp
             int
                     dosversion, ax
            mov
                                                                                               REBOOT endp
                                                                                                                        ; end of main routine
    ; Store ROM interrupt vectors (8-1F and 48,41 and 44 hex) in program table.
                                                                                               CODE
                                                                                                       ends
                                                                                                                                ; code segment ends
                     ds
                                             point es to this segment
             push
                                                                                                        end
             pop
                     es
```

WITH ONE OF MONTE'S BUNDLES

These special bundles are ready for you to save a bundle of money. CP/M software is actually preferred because of the vast amount of programs available. The programs in these bundles have been optimized to run on the Model 4-4D-4P. For example, we have memory-mapped WordStar and it runs circles around the standard version others sell. We also added printer drivers for the Radio Shack Daisywheel II, DMP-2100 and most other Radio Shack Printers as well. You have read the reviews and know that our CP/M is the best for the Model 4. Your Models 4 and our CP/M form an unbeatable combination. Send for our free public domain software catalog and see for yourself.

'A'' Bundle \$299 WordStar SpellStar Star Index MailMerge Montezuma Micro CP/M

Save a Bundle

on these books and disks.

Take advantage of our volume discounts. Buy any three items from this list and deduct \$5 from your total order. Buy four and deduct \$10. Buy five....deduct \$15. Buy six....deduct \$20 etc. Please add \$1 for each book for shipping.



TRS-80 Disk & Other Mysteries. The "How To" book of data recovery for the TRS-80 Model 1 disk operating system. 128 pages. Retail \$22.50. NOW \$18

Microsoft BASIC Decoded & Other Mysteries. The complete guide to Level II and BASIC. 312 pages. Retail \$29.95.

The Custom TRS-80 & Other Mysteries. The complete guide to customizing TRS-80 hardware and software. 336 pages. Retail \$29.95. NOW \$24

BASIC Faster & Better & Other Mysteries. The complete guide to BASIC programming tricks and techniques. 290 pages. Retail \$29.95. NOW \$24

BASIC Faster & Better Library Disk. Contains 121 functions, subroutines and user routines. Search, merge, compare and listing routines plus array handlers. BASIC overlays and video drivers. BFBLIB. Retail \$19.95.

BASIC Faster & Better Demonstration disk. Contains 32 demos of the Library Disk contents above. BFBDEM. Retail \$19.95 NOW \$16

BASIC Disk I/O Faster & Better & Other Mysteries. Programming tips and techniques to store/retrieve data from disk. 432 pages. Retail \$29.95.

NOW \$24

BASIC Disk I/O Faster & Better Demonstration Disk. All of the major demo programs and library of disk I/O subroutines in 25 BASIC programs. Random, indexed, sequential and treesam file handlers included. DFBLOAD. Retail \$29.95. NOW \$24

Machine Language Disk I/O & Other Mysteries. A guide to machine language disk I/O for the TRS-80. 288 pages. Retail \$29.95. NOW \$24

TRSDOS 2.3 Decoded & Other Mysteries. Detailed explanation of the Model 1 disk operating system. 298 pages. Retail \$29.95. NOW \$24

How to do it on the TRS-80. A complete applications guide to the TRS-80 Model 1, 2, 3, 4, 100 and Color Computer. 352 Pages. Retail \$29.95. NOW \$19

The Custom Apple & Other Mysteries. Who cares? Retail \$29.96. NOW \$19

B" Bundle \$399 WordStar Star Index MailMerge ReportStar SpellStar CalcStar Montezuma Micro CP/M DataStar

MS-DOS BUSINESS SOFTWARE

Ability Accounting Partner I Accounting Partner II	\$ 62
Accounting Portner I	270
Accounting Faither I	200
Accounting Partner II	099
Borland Turbo Lighting	53
BPI AP/AR/GL/Payroll	. 319
BPI Inventory	477
bel inventory	411
Carbon Copy	128
Cornerstone	62
Carbon Copy Cornerstone Clickart Personal Publisher	112
Crosstalk 16	00
Crosstaik 16	99
DAC Easy Accounting	39
DAC Ency Mate	24
DAC Easy Mate DAC Easy Payroll DAC Easy Payroll Tutor DAC Easy Port DAC Easy Word	200
DAC Easy Payroll	29
DAC Easy Payroll Tutor	14
DAC Fasy Port	19
DAC Form Word	20
UAC Easy Word	29
dBase II	349
dBase III Plus	399
Diagram Macter	212
Dellars & Casas	100
Dollars & Sense	109
EGA Paint	45
Framework II	469
Eroologoo	215
Freelance Generic CAD 2.0	2 13
Generic CAD 2.0	89
Lotus 1-2-3, 2.01	319
Lotus 1-2-3, 2.01	54
Managina The Market	90
managing the market	09
Managing Your Money 3.0	119
Microsoft Multiplan	127
Microsoft Word/Spall 3.0	260
Microsoft Word/Spell 3.0	240
Lottus 1-2-3, Ose Win Managing The Market Managing Your Money 3.0 Microsoft Multiplan Microsoft Word/Spell 3.0 Microsoft Project Mirror	249
Mirror	44
MultiMate	239
Nounroom	37
Newsroom	
Paradox	445
Print Shop	37
PFS: 1st Choice	89
DEC.EIA	
PFS:File	60
PFS:Graph	88
PFS:Report	79
PFS:Pro Write	119
D D : : "	400
ProDesign II	100
Q & A	235
R:Base 5000 1.01	269
ProDesign II O & A R:Base 5000 1.01 R:Base Extended Report Writer R:Base System V Reflex: The Analyst Reflex Workshop Stretick	85
D.Dase Extended Report Willer	200
H:Base System V	399
Reflex: The Analyst	53
Reflex Workshop	36
Cidabiah	40
SIGENCE	400
Smart Software System	432
SuperCalc 4	295
Superkey	37
Henex Workshop Sidekick. Smart Software System SuperCalc 4 Superkey. Timeline Project Manager Twin, Lotus 1-2-3 Clone.	260
Timeline Project Manager	209
Twin, Lotus 1-2-3 Clone	54
VP Info	55
VP Info	55
VI FIGURET	
Webster New World Writer	/5
Word Perfect 4.2	209
Word Perfect Library	61
Webster New World Writer. Word Perfect 4.2 Word Perfect Library WordStar 2000 Plus 1.01	260
WOOdai 2000 Flus I.VI	209
WordStar 3.31	189

\$499 WordStar ReportStar MailMerge CalcStar SpellStar dBase II Star Index Turbo Pascal Montezuma Micro CP/M **用电动向电路电对射**管

" Bundle

MS-DOS LANGUAGES/

UTILITIES
Bourbaki "1 Dir"
Clipper
Clipper
Copy II PC Option Board 80
Crosstalk 16
Disk Optimiser
Fastback
Fontasy 2.0
Homebase 2.0
Microsoft C Compiler 4.0
Microsoft Macro Assembler
Microsoft Windows 1.0363
Microsoft QuickBASIC Compiler: 60
Norton Commander
Norton Utilities 3.1
Sidekick
Sideways 3.1
Smartcom II
Smart Notes
Superkey
SQZ
Turbo Database Toolbox
Turbo Editor Toolbox
Turbo Gameworks
Turbo Graphics Toolbox
Turbo Lightoing 52
Turbo Lightning
Turbo Prolog
Turbo Tutor
Word Perfect Library
Word Wizard
VYOIG VVIZAIG

MS-DOS RECREATIONAL SOFWARE

Certificate Maker \$	36
Championship Golf	30
F-15 Strike Eagle	
Gato	
Galo	23
Hitchikers Guide to the Galaxy	25
Jet	35
Kareteka	22
Kings Quest	
Leather Goddess	24
Microsoft Flight Simulator	32
NFL Challenge	50
Sargon III	29
Silent Service	21
Toy Shop	
Wizardry	38

MS-DOS HOME SOFTWARE

Bank Street Writer													
Certificate Maker					,	,							.36
Dollars and \$ense			,								•		115
Micro Cookbook													
Managing Your Mon	e	y						 					113
Newsroom					,							,	.35
Print Shop													.38
Print Shop Graphics	ı	j	b	ra	ar	٧		 					.22

MS-DOS EDUCATIONAL SOFTWARE

Mastertype .				,								\$	26
Math Blaster				,									. 29
Mind Prober													.30
Spell It!													
Typing Tutor													
Word Attack													. 29

LL TOLL FREE! 800-527-0347 800-442-1310 (Texas)

* For orders over \$100

Everex Internal 1200 w/software	ı,	,				\$ 99
Haves 300 external			,	,	,	.149
Hayes 1200 w/SmartComm		į				.399
Haves 1200B w/SmartComm						
Hayes 2400						. 599
Hayes 2400B w/SmartComm						. 569

RODENTS

Microsoft Bus Mouse w/sftwr		į.		,		\$	115
Microsoft Serial Mouse w/sftwr.	ì						.135
Mouse Systems Mouse w/sftwr.							. 120
C&H Mach III Joystick, each	,			,	,		36
TAC10 Joystick							
Willard/Ben Combo w/friends						C	ALL

HARD DRIVES

20mb 65ms	ST225 kit complete					\$	389
30mb 65ms	ST238 kit complete				,	ú	.469
30mb 40ms	ST4038 bare drive	i	4	4		'n	.579

MONITORS

Mitsubishi 6920 1024 x 1024			3	1899
NEC Multisync 800 x 560				. 599
Amdek 722 EGA 649 x 350				. 529
Mitsubishi 1410 EGA				. 439
Mitsubishi 1409 RGB				.319
Magnavox RGB 640 x 200				. 299
NAP TTL 1000 x 350 Amber/Green	٦	,		.110

PRINTERS

Citizen 120D 120cps NLQ, col	. \$ 189
Citizen MSP-15 160cps NLQ, 32 col .	399
Citizen MSP-20, 200cps NLQ, 80 col .	345
Citizen Premier 35DW, w/tractor	499
oshiba 321 216cps, NLQ, 80 col	539
Toshiba 341 216cps, NLQ, 132 col	769
C. Itoh 3520 350cps NLQ, 132 col	1195
Canon LBP-8A1 Laser	1895
Canon Laser Toner kit	89

ADD-ONS MEMORY & UPGRADES

UFGRADES	
Hercules Graphics plus \$	199
Paradise Autoswitch EGA	
Clone EGA Plus	
Hercules Compatible Graphics	
Color Graphics, 3-output	
16K RAM, 200nsec, 8 chips	
64K RAM, 150/200nsec, 8 chips	16
Model 4 128K RAM w/PALchip	
64K RAM set of 9 chips	
256K RAM set of 9 chips	49
8087 Numeric coprocessor, std	
8087 Numeric coprocessor, fast	
80287 Numeric coproc. std	
80287 Numeric coproc. fast	
NEC V20 Wonder Chip, 5mHz	
NEC V20 Wonder Chip, 8mHz	
Model 1 RS-232 Kit complete	
Model 3/4 RS-232 Kit complete	. 69
Model 3/4 Internal Drive kit	169

TRS-80 SOFTWARE AND **BOOKS**

Modern 80 Mod 1/3 Com Pkg	¢ 22
Super Utility Plus 3.2 M1/3/4	49
Super Utility Plus M4-4P/D	only 49
SuperCROSS/XT Specify M1/3/4	
Conv 3-PC M3 BASIC to PC	119
Conv 4-PC M4 BASIC to PC	119
TRS-80 Beginners Guide	FREE
Inside Level II (a rare find)	9
TRS-80 Model 4/4P Tech Manual	33
TRS-80 Model 1000 Tech Manual	25
Using Super Utility Plus 3.x	16
See more books on the opposite page	

BOOKS & MANUALS

IBM BASIC Faster & Better	\$	22
IBM BASIC Disk for above		. 22
IBM BASIC Manual 3rd ed		. 19
Running MS-DOS 2nd ed		. 17
Running MS-DOS Advanced	į.	.17
Using Wordperfect 4.1		.13
Nortons Programmer's Guide		. 15
See opposite page for more books.		

CP/M SOFTWARE

GDGGG II	
WordStar Professional	a
ReportStar	
DataStar	
CalcStar	
Multiplan	
Out-Think	
Mex Plus	Э
Mex Plus	9
Rembrandt	à
Supercalc II	
Turbo Pascal	
Turbo Tutor	
Turbo Database Toolbox	
Turbo Holiday Pak (above 3)	9
Twist & Shout	Δ
All of the above CP/M software is avail	ľ
able in various 51/4" formats as well as	
8" standard CP/M format. Please spec	
ify format and include \$10 per dist	
	•
additional.	

CABLES

07.000
TRS-80 Printer cable 26-1401
IBM Parallel Printer cable 10'
Standard IBM 25 pin RS232 10'
Std TRS-80 25 pin RS232 10'20
Printer A/B Switch Box Cable 6'
Gender Changer, Spec M/M F/F

ACCESSORIES

C & H Mach III Joysticks, ea \$ 34
Sony 2D disks, box of 10
Our own 2D disks, bag of 10
Disk Storage Box w/lock hlds 100
Keyboard Extender Cable, 6'
TTL Monitor Extender Cable 6'10
Tilt and Swivel Monitor Stand
Vert CPU Stand PC/XT/CLONE
2-position Parallel Printer Switch 39
4-position Parallel Printer Switch
2-position RS-232 Switch
4-position RS-232 Switch
Standby Pwr Sup. 300W/20 min

BUY FROM US RIGHT NOW

instructions should you have a problem

GOOD AS GOLD WARRANTY

GOOD AS GOLD WARRANTY
We want you to be happy with your purchase.
All items we offer carry the manulacturers' warranty and any problem you might have in service will be handled by his service organization. Please call us should you have any difficulty in obtaining service. Your satisfaction is our goal and we back it up with a 30 day money-back guarantee (except software). We will be happy to mail you a copy of the complete warranty details on request.




\$ 385

2544 W. Commerce Street P.O. Box 224767 Dallas, Texas 75222-4767

Telephone: 214-631-7900 Facsimile: 214-634-8303 Copyright 1987 by Montezuma Micro.

Leave the Printing



Set up a RAM buffer to free your Tandy 1000 while printing out files.

by David A. Williams

spooler, one of the most useful utilities you can own, frees your computer to perform other tasks while your printer slowly grinds out the great American novel or the world's largest spreadsheet. A spooler can use a RAM buffer, a disk buffer, or a combination of the two.

Spooli (see the Program Listing) uses

System Requirements

Tandy 1000/1200/3000 Assembly language Editor/assember Parallel printer

the first method. It places characters that would otherwise be sent directly to your printer into a reserved 64K block of memory. The characters remain in that block until your printer is ready to take them. Spooli then doles out characters to your printer while your computer appears to be devoting its full attention to its next task. Spooli includes commands that let you purge the buffer and make duplicate copies.

A print spooler should be transparent, 💆 meaning that, except for the fact that your documents appear to print much faster, everything should work as usual. A & spooler should be fast, allow your printer spooler to operate at normal speed, and be adaptable to the spooler should be fast, allow your printer spooler should be adaptable to operate at normal speed, and be adaptable to the spooler should be spooler should be spooler should be adaptable to the spooler should be ada able to your hardware configuration. It

to Spooli

should not require an inordinate amount of memory and must have the features you need.

I tried several commercial spooler programs and did not find one that satisfied all of the above criteria. You might not like everything about Spooli, but you can easily customize it to fit your requirements.

I tried to keep Spooli simple. The program's buffer is fixed at 64K bytes and only services printers that are connected to the LPT1 parallel port. You can change the port address, but you cannot use Spooli to run two parallel printers or a serial printer.

How It Works

Spooli is memory-resident and consists of an initialization program, several routines that either replace or supplement existing interrupt routines, and a 64K buffer. The initialization routine runs once when you load the program. The routine uses DOS function calls 35 and 25 to replace the interrupt vectors for the timer interrupt, 08 hexadecimal (hex); the keyboard interrupt, 09 hex; and the basic input/output system (BIOS) printer interrupt, 17 hex.

The routine then calculates the buffer's starting address, ensures that it starts on a segment boundary, and tells DOS how much memory to reserve for the program and the buffer.

BIOS interrupt 17 hex has three functions: send a character, initialize a port, and test printer status. Spooli provides for all three functions, but the characters go into the buffer instead of going directly to the printer. Since the buffer does not need to be initialized, 17 hex merely reports printer status.

The buffer occupies one full segment, 64K bytes. Two pointers, In_PTR for input and Out_PTR for output, keep track of the data flow. I chose to use this size in order to simplify the design. When the pointers reach the top, FFFF hex, they overflow to 0000 hex and start over from the bottom. This circular organization allows Spooli to handle print jobs that are larger than 64K, but it cannot free your computer until less than 64K of text remains to be printed.

A counter, BUF_CNT, keeps track of how many characters are in the buffer. The data in BUF_CNT is redundant (you can derive it from the contents of the two pointers). Only two BUF_CNT values are of interest: 0000 and FFFF hex. The former tells you that there are no more characters to send while the latter says, "Wait, the buffer is full!"

Before storing a character, Spooli checks to make sure that the buffer is not already full. If it is full, the program loops until the printer takes some data from the buffer and makes room for more. This means that the program hangs here if the printer is off line and the output exceeds 64K of text.

Spooler programs could be made more efficient if there were an interrupt that signaled when the printer was ready to accept another character. The BIOS provides for such an interrupt, but most computers are not wired to use it and require another approach. Spooli uses the timer interrupt.

Eighteen times a second, a clock signal interrupts the computer to update the counters that are keeping the time of day. Spooli intercepts the timer interrupt and steals a few milliseconds to send characters to your printer, using the interrupt 17 hex routine, before jumping to the timer interrupt routine. After it sends each character, Spooli updates Out_PTR and BUF_CNT.

Printing would take forever if Spooli printed only one character each time it called the output routine. To output a reasonable amount of text in one batch,

yet keep your computer from getting hung up if your printer goes off line, Spooli loops through the output routine. It counts the passes, whether or not a character is sent, and exits when the count equals the value of the constant Cycles, currently set at 100.

This Cycles value of 100 causes the computer to spend about a third of its time servicing the printer and works well with printers that have only a single-line buffer. If your printer has a larger buffer, you can make the value of Cycles smaller. This permits your computer to spend more time doing other things without slowing down the printer.

Although a spooler should be able to run automatically, you must have external control. Spooli provides a purge command, alternate-P, which empties the buffer and resets the pointers to zero. The program also contains a duplicate command, alternate-D, which lets you make additional copies. You can execute these commands from within programs or from the DOS prompt.


Controlling Spooli

The control routine intercepts the keyboard interrupt, 09 hex, and looks for alternate-P or alternate-D key combinations. When it detects either one, it calls the appropriate routine. If this choice of commands interferes with any of your programs, you can select another combination.

You can use the purge command anytime, but if you do so while your program is printing, the buffer continues to fill. The duplicate command only works on documents that are smaller than 64K for which you executed the purge command before starting your printing job. You can also use the duplicate command to stop and then restart a print operation if the paper becomes jammed or some other calamity occurs.

Easy Restart

You can restart at any time. To begin printing again, simply take your printer



off line, solve the problem, press alternate-D, and put your printer back on line. Make sure your printer is turned on before starting a print operation. Sometimes the computer output port cannot distinguish between a dead line and a ready signal.

Assembling Spooli

Spooli is designed to be assembled and then converted to a COM file. The following commands, which you can place in a batch file, will perform the tasks if you are using the Microsoft macro assembler, MASM.

ECHO OFF MASM %1; LINK %1; DEL %1.OBJ EXE2BIN %1 %1.COM DEL %1.EXE

Name the source file Spooli.ASM, the batch file ASM.BAT, and type ASM SPOOLI to start the process. Ignore the warning message that your computer will display concerning a missing stack sector.

David A. Williams is a staff engineer with a major aerospace firm and has 25 years of experience with computers. Write to him at 2452 Chase Circle, Clearwater. FL 33546.

Program Listing. Spooli.

SPOOLER PROGRAM, David Williams CYCLES EOU 100 : NUM OF LOOPS THRU OUTPUT ROUTINE ;Data area containing keyboard buffer and status word BIOS_DATA SEGMENT AT $40\,\mathrm{H}$ ORG 1AH HEAD DW BUFFER 15 DUP (?) DW BUFF_END BIOS_DATA ENDS CSEG SEGMENT ASSUME CS:CSEG, ES:CSEG, DS:CSEG 1004 BEGIN: JMP INIT ;Counters, pointers, and other data DATA_SEG DW 0 ;BUFF BUFFER SEGMENT ADDRESS ;OUTPUT POINTER ;INPUT POINTER OUT_PTR DW а IN PTR DW ;AMOUNT OF DATA IN THE BUFFER ;ORIGINAL TIMER INT VECTOR ;ORIGINAL KYBD INT VECTOR ;ORIGINAL PRINTER INT VECTOR BUF_CNT OLD_TIMER OLD_KYBD_INT DD 0 PRINT DD 0 ROUTING CAlled by kybd input to purge buffer, duplicate output CONTROL PROC FAR ASSUME DS:BIOS_DATA STI PUSH PHSH DS PUSH ;Input data from the keyboard and look for control characters PUSHF OLD_KYBD_INT CALL AX, BIOS_DATA DS, AX MOV MOV MOV BX, TAIL :FIND CHARACTER SUB BX,OFFSET BUFFER CMP NO WRAP JAE MOV BX, OFFSET BUFF_END GET CHARACTER AX,[BX] AX,2000H NO WRAP: MOV ; IS IT ALT-D? CMP Listing continued .17

Circle 291 on Reader Service card.

COMPUTER WAREHOUSE INTRODUCES THE TURBO XT/AT PERSONAL COMPUTER

\$AVE—BUY DIRECT FROM THE FACTORY!!

Epson Printer(s)	Call	Tandon Hard Drives	Call
Citizen 120 D.	\$249	AT Hd Disk/Floppy Disc Cntrlr	\$195
Panasonic Printer(s)	Call	DTC Hard Drive Cntrlr for XT	\$125
*Star Microenics NP-10	\$269	Western Digital Hd Drive Cntrlr	\$125
NX-10	\$299	Konan Hard Drive Cntrlr	\$115
NX-15	\$399	AT Flpy Dsc Ctlr (360K/1.2 MG)	\$135
NB-15	\$1400	AT Konan Hard Drive Cntrlr	\$140
ADD-ON(S)		CABLES	
XT Mthrbrd 640K	\$120	Printer Cable (6 ft.)	\$6.50
8088-2, 4.77/8 MHZ OK		Serial Cable	\$7.50
XT Mthrbrd 640K	\$155	AB Switchbox	\$35
8088-2, 4.77/8 MHZ OK		Joystick	\$20
4 Layer			
AT Mthrbrd 1MEG	\$500	MONITORS	
80286-2, 6/8 MHZ OK		Samsung TTL	Amber
AT Mthrbrd 1 MEG	\$535		Green
80286-2, 6/10 MHZ OK		Samsung TTL	Amber
Multi I/O	\$85	Titted Swivel	Green
384K Multifunction Board OK	\$80	Goldstar TTL	Amber
Color/Graphics/Printer	\$70	dordstar 112	Green
Color/Graphics/Composite	\$60	Sharp RGB Monitor	Call
Mono/Graphics/Printer	\$75	Goldstar RGB Monitor	Call
Mono/Graphic	\$65	Mitsubishi RGR Monitor	Call
EGA Card	\$265	LTI EGA Monitor/Titd Swyl	
			\$435
Floppy Disc Cntrlr (2 ports)	\$30 \$40	Casper EGA Monitor/Titd Swvl Sonv EGA Multi-Scan Monitor	\$415
Floppy Disc Cntrlr (4 ports) Clock Card		Sury EGA Muni-Scan Monitor	\$675
Game Card	\$20 \$18	DATAPRODUCT(S)	
20 MEG	+10		\$320
Seagate Hd Dry St 225 w/Ctrlr	\$399	Quality Letter/Serial 35 cps.	
S'gate 30 MEG Hd Dry St 238			
o gait of med no bit of 200		44 17 17 17 17 17	

\$349

*System(s) include

Public Domain Software

IDEAL TURBO XT...\$549.

Slide Case • 150W Power Supply 640K Turbo-Motherboard W/640K RAM (4.77/8MH) 1 Fujitsu Drive Disc Controller 5060 Keyboard (XT/AT)

IDEAL TURBO AT...\$1760.

Case • 200W Power Supply 1MB Turbo-Motherboard W/1MB RAM (6/8/10 MZ) •

- 1 360K Floppy Drive 1 1.2MB Floppy Drive
- 1 30MB Hard Drive
- 1 AT I/O
- 1 Floppy/Hard Disc Controller
- 1 AT Keyboard



ADD ON: Monographic or Color/Graphic....\$70.
TTL Monochrome (Green or Amber)....\$119. (Available for XT/AT)

CALL US TODAY
FOR THE IDEAL PERSONAL COMPUTER AT AN IDEAL PRICE!!

The Computer Warehouse

464 Hillside Ave., Needham, MA 02194 (617) 449-6988

MA 1-800-527-5995
MASTERCARD/VISA/AMERICAN EXPRESS ACCEPTED.

Microscience 20 MEG Hard Drive

w/Controller

w/Controller

PRINTER(S)

GOING PORTABLE?

WHAT ARE THE TWO MOST IMPORTANT CONSIDERATIONS?

SIZE AND WEIGHT!

This printer is half the size and half the weight of your Model 100. Anywhere you happen to be, cruising at 30,000 feet or in a cab to an important business meeting, you can get a guick and guiet printout. A perfect companion for your Model 100/200/600.

FEATURES?

This printer has them all:

- 81/2" wide thermal paper
- · 512 byte buffer
- · Epson MX-80 bit-mapped graphics
- · Built-in automatic self test function
- · Excellent User's Manual

(ACTUAL print sample) 80 Chars/Line, 40 CPS! Enlarged! underlined Emphasized! CONDENSED gives you 160 chars. per line!

\$99 GRAND TOTAL

You get the printer and a specially made 18" cable (connects printer to your Model 100/200/600 or NEC 8201/8401), 20' roll of paper, a paper holder, and 4 "C" batteries everything you need to start printing immediately with the push of a button. This price also includes free UPS surface shipping in the cont. USA. There is no surcharge for VISA/MC/Amex - even the phone call is free.

RUGGED

This printer was designed to print over 300,000 lines without maintenance - that's over 104 pages every week for a year.

DIRECT TO YOU

We've been selling this printer to our portable customers and corporate accounts for over a year. Two of our largest accounts, NBC and National Geographic, use them in the field all over the world. To meet the demand we have gone direct to the Japanese manufacturer. Our large volume cost is unbelievable - that's why we can offer it direct to you at this fantastic price, yet still give you great service and support (6 month parts/labor warranty, 30 day money back satisfaction quarantee).

SUPPORT

We stock paper (rolls and sheets), cables, and accessories for the printer. The full accessory kit costs only \$24 and includes a carrying case, 100' roll of paper, and an A/C adapter (saves batteries when A/C power is convenient).

NO RISK

Try it for 30 days, ask your friends and business associates if they've ever seen anything like it. You can return it in 30 days for any reason and get a full refund. Don't let yourself miss this portable printer bargain of a lifetime.

IT'S EASY TO ORDER

Send your order with payment to the address below. Or, if you prefer, credit card orders can be handled by phone-VISA, MasterCard, and American Express are welcome. California residents add 6% sales tax. Checks allow 3 weeks to clear. Institutions and Corporations call for purchase order approval.

1-800-732-5012 TOLL FREE

Orders only (8am. - 5pm. PST)

In California (805) 987-4788 For orders or customer service

If you would like our latest product catalog or to find a dealer near you, please write or call (805) 987-4788



420 Constitution Ave. Camarillo, CA 93010 Telex: 888661 (PURPLE) 732-5012

Canada: Canada Portable Computer, Langley, B.C. (604) 856-8858

Circle 478 on Reader Service card.



```
Listing continued
                                                                                               Listing continued
                            AX.1900H
                                                   : IS IT ALT-P
                                                                                                                    CALL
                                                                                                                            PRINT
                                                                                                                                                  : CALL OLD PRINT ROUTINE
                     CMP
                                                                                                                                                  TEST FOR BUSY
                                                                                                                    TEST
                                                                                                                            AH.80H
                     JZ
                            PURGE
                                                                                                                    JNZ
                                                                                                                            CONT
                                                                                                                                                  : NOT BUSY
           NEXT:
                     POP
                            AX
                                                                                                                    CMP
                                                                                                                            CX.CYCLES
                                                                                                                                                  : HAS IT EVER BEEN READY
                     POP
                            DS
                                                                                                                                                  :YES, CONTINUE
                                                                                                                    JNZ
                                                                                                                            LOOP
                     POP
                            BX
                                                                                                                    JMP
                                                                                                                            EXIT
                                                                                                                                                  ; NO, EXIT
                     IRET
                                                                                                          :Print a character
           ; Purge spool buffer
                                                                                                                                                  ;TURN OFF INTERRUPTS
                                                                                                          CONT:
                                                                                                                    CLI
           PURGE:
                     CLI
                                                                                                                     MOV
                                                                                                                            SI, OUT PTR
                     MOV
                            CS:OUT PTR, 0
                                             RESET
                                             ; THE
                                                                                                                     MOV
                                                                                                                            ES, DATA SEG
                                                                                                                                                  GET BUFFER SEG ADDR
                     MOV
                            CS: IN_PTR, Ø
                                                                                                                                                  GET CHAR FROM BUFFER
                                                                                                                    MOV
                                                                                                                            AL, ES: [SI]
                     MOV
                            CS:BUF CNT. 0
                                             : COUNTERS
                                                                                                                    INC
                                                                                                                            OUT_PTR
                                                                                                                                                  : INC OUTPUT POINTER
                     JMP
                            FINI
                                                                                                                    DEC
                                                                                                                                                  : ADJUST BUFFER COUNT
                                                                                                                            BUF_CNT
           :Duplicate output or restart
                                                                                                                    MOV
                                                                                                                            AH, Ø
                                                                                                                                                  ;OUTPUT A CHARACTER
          DUPE:
                     CLI
                                                                                                                    PUSHE
                                                                                                                                                  :MATCH IRET
                            AX, CS: IN_PTR
                                             : START
                     MOV
                                             ; OVER
                                                                                                                    CALL
                                                                                                                            PRINT
                                                                                                                                                  ; CALL OLD PRINT ROUTINE
                     MOV
                            CS:BUF CNT, AX
                     MOV
                            CS:OUT_PTR, 0
                                             ; FROM BOTTOM
                                                                                                                     STI
                                                                                                                                                  : IS THE BUFFER EMPTY
                                                                                                                    CMP
                                                                                                                            BUF_CNT, Ø
                     STI
           FINI:
                            TAIL, BX
                                                                                                                    JZ
                                                                                                                            EXIT
                                                                                                                                                  EXIT IF SO
                     MOV
                                                                                                          LOOP:
                                                                                                                     LOOP
                                                                                                                            REPEAT
                                                                                                                                                  ; LOOP
                     JMP
                            NEXT
                                                                                                          EXIT:
                                                                                                                     POP
                                                                                                                            ES
           CONTROL
                     ENDP
                                                                                                                     POP
                                                                                                                            DS
           ;Input routine,
                           replaces INT 17H routine
                                                                                                                     POP
                                                                                                                            SI
           INPUT
                     PROC
                            FAR
                                                                                                                     POP
                                                                                                                            DX
                                             : RESTART INTERRUPTS
                     STI
                                                                                                                     POP
                                                                                                                            CX
                                              SET FLAGS
                     OR
                            AH, AH
                                                                                                                     POP
                                                                                                                            AX
                     JZ
                             STORE
                                              : CHAR TO BUFFER
                                                                                                                    CLI
                                              :TEST FOR AH=1
                     DEC
                            AH
                                              ; INITIALIZE PORT
                                                                                                                    JMP
                                                                                                                            CS: [OLD_TIMER]
                                                                                                                                                  ; JUMP TO OLD TIMER INT
                     JZ
                             PRTSTAT
                                                                                                          OUTPUT
                                                                                                                    ENDP
                     DEC
                                              :TEST FOR AH=2
                            AH
                                                                                                                     DB 16 DUP(?)
                                                                                                                                                  ; GUARD SPACE
                                              GET PRINTER STATUS
                            PRTSTAT
                     JZ
                                                                                                          ; Initialization routine, runs when spooler is loaded
                     IRET
                                                                                                          INIT PROC NEAR
           :Accept character, but store instead of print
                                                                                                          ;Initialize printer port
           STORE:
                     PUSH
                            SI
                                                                                                                     MOV
                                                                                                                            AH, 01
                     PHSH
                            DS
                                                                                                                     MOV
                                                                                                                            DX . Ø
                                             ; PUT THE CHAR IN THE BUFFER
                     CALL
                            SAVE
                                                                                                                    INT
                                                                                                                            17H
                     POP
                            DS
                                                                                                          ;Get current timer interrupt vector
                     POP
                                                                                                                     MOV
                                                                                                                            AX,3508H
           PRTSTAT:
                     CMP
                             CS:BUF_CNT, ØFFFFH
                                                   : IS BUFFER FULL ?
                                                                                                                     INT
                                                                                                                                                       :GET THE VECTOR
                             BUSY
                     JZ
                                                                                                                     MOV
                                                                                                                            WORD PTR OLD_TIMER, BX
                                                                                                                                                      SAVE THE OFFSET
                     MOV
                             AH, 90H
                                                   ; SELECTED, NOT BUSY
                                                                                                                            WORD PTR OLD_TIMER+2, ES
                                                                                                                                                      SAVE THE SEGMENT
                     IRET
                                                                                                          ;Set timer interrupt vector to output routine
                             AH, 10H
                                                   : SELECTED, BUSY
           BUSY:
                     MOV
                     IRET
                                                                                                                     MOV
                                                                                                                            AX, 2508H
                                                                                                                                                       DOS REQUEST
                                                                                                                     MOV
                                                                                                                            DX, OFFSET OUTPUT
                                                                                                                                                      POINTER TO OUR ROUTINE
           INPUT
                     ENDE
           ;Routine to put character in buffer
                                                                                                                     INT
                                                                                                                            21H
                                                                                                          :Get current kybd interrupt vector
                            NEAR
           SAVE
                     PROC
                                                   :BUFFER FULL?
                                                                                                                     MOV
                                                                                                                            AX,3509H
                     CMP
                             CS:BUF_CNT, ØFFFFH
                                                   YES, WAIT
                                                                                                                     INT
                                                                                                                            21H
                                                                                                                                                          GET THE VECTOR
                     JZ
                             SAVE
                                                                                                                            WORD PTR OLD KYBD INT. BX
                                                                                                                                                          : SAVE THE OFFSET
                                                                                                                     MOV
                     CLI
                             DS, CS: DATA_SEG
                                                   ; SET DS TO BUFFER SEGMENT
                                                                                                                     MOV
                                                                                                                            WORD PTR OLD_KYBD_INT+2, ES
                                                                                                                                                          ; SAVE THE SEGMENT
                     MOV
                                                                                                          ;Set kybd interrupt vector control routine
                                                   GET INSERT POINTER
                     MOV
                             SI, CS: IN_PTR
                                                                                                                            AX, 2509H
                                                                                                                                                          : DOS REQUEST
                     MOV
                             [SI],AL
                                                   : SAVE CHAR
                                                                                                                     MOV
                                                   : INC POINTER
                                                                                                                            DX, OFFSET CONTROL
                                                                                                                                                          ; POINTER TO OUR ROUTINE
                     INC
                             CS: IN_PTR
                                                                                                                     MOV
                     INC
                             CS:BUF_CNT
                                                   ; INC COUNTER
                                                                                                                     INT
                                                                                                                            21H
                     STI
                                                                                                          ;Get current print interrupt vector
                                                                                                                     MOV
                                                                                                                            AX,3517H
                                                                                                                                                  GET IT
                     RET
                                                                                                                     INT
                                                                                                                            21H
           Output routine. Attached to front of timer int routine
                                                                                                                     MOV
                                                                                                                            WORD PTR PRINT, BX
                                                                                                                                                  : SAVE IT
           OUTPUT
                     PROC
                             FAR
                                                                                                                     MOV
                                                                                                                            WORD PTR PRINT+2, ES
                     CMP
                             CS:BUF_CNT, 0
                                                   ; ANYTHING TO PRINT?
                                                                                                          ;Set INT 17H vector to input routine
                     JNZ
                                                                                                                     MOV
                                                                                                                            AX, 2517H
                                                                                                                                                  DOS REQUEST
                     JMP
                             CS: [OLD_TIMER]
                                                                                                                            DX, OFFSET INPUT
                                                                                                                                                  POINTER TO OUR ROUTINE
                                                                                                                     MOV
                                                   ; RESTART INTERRUPTS
           GO:
                      STI
                                                                                                                     INT
                                                                                                                            21H
                      PUSH
                             AX
                                                                                                          ;Compute buffer
                                                                                                                           segment address and allocate memory
                      PUSH
                             CX
                                                                                                                            DX, OFFSET INIT
                                                                                                                                                  POINT TO START OF INIT
                                                                                                                     MOV
                      PUSH
                             DX
                                                                                                                     MOV
                                                                                                                                                   ; AMOUNT TO SHIFT RIGHT
                                                                                                                            CL,04
                      PUSH
                             SI
                                                                                                                     SHR
                                                                                                                            DX, CL
                                                                                                                                                  ; DO IT
                      PUSH
                             DS
                                                                                                                     MOV
                                                                                                                            AX,CS
                                                                                                                                                  GET CURRENT CODE SEGMENT
                             ES
                      PUSH
                                                                                                                            AX, DX
                                                                                                                                                  : ADD OFFSET TO INIT
                             CS
                     PUSH
                                                                                                                            DATA_SEG, AX
                                                                                                                                                  BUFFER SEGMENT ADDRESS
                                                                                                                     MOV
                      POP
                                                   : SET DATA SEGMENT
                                                                                                                     ADD
                                                                                                                            DX, 1001H
                                                   : SET NUMBER OF TIMES TO LOOP
                             CX, CYCLES
                      MOV
                                                                                                                     MOV
                                                                                                                            AL, Ø
                                                                                                                                                  ; NORMAL EXIT CODE
           :Check printer
                           status
                                                                                                                     MOV
                                                                                                                            AH, 31H
                                                                                                                                                  QUIT AND STAY
                     MOV
                             AH, 02
                                                   ; INT 17H, RETURN STATUS
                                                                                                                            21H
           REPEAT:
                                                                                                                     INT
                      MOV
                             DX, Ø
                                                   ; SELECT LPT1
                                                                                                          INIT
                                                                                                                     ENDP
                                                   TO MATCH IRET IN INT17H
                     PUSHF
                                                                                                          CSEG
                                                                                                                     ENDS
                                                                            Listing continued
                                                                                                                     END BEGIN
                                                                                                                                                                                       End
```

TANDY Model 1000 & MS-DOS TRS-80™ Models 1, 3 & 4 SOFTWARE

SMALL BUSINESS ACCOUNTING

SMALL BUSINESS ACCOUNTING with PAYROLL \$99.95

This program is based on the **Dome Bookkeeping Record #612** and handles **bookkeeping** and **payroll** for a small business. Bookkeeper provides single entry ledgers with category breakdowns for both income and expenses. Monthly, through last month, and year-to-date summaries. Fiscal year can start with any month.

Payroll handles up to 99 employees with **automatic computation** of F.I.C.A. and federal income tax. State tax and three optional deductions also included. Prints both payroll and expense checks on same forms. Monthly, quarterly, and yearly summaries as well as automatic computation of Form 941 reports and W-2 forms. Simple and easy to learn—ideal for first-time computer users.

MAILING LIST \$99.95

Build and maintain mailing lists of up to **32,767** names. Up to five-line labels including first and last names, optional second line, address, city, state, zip code, and optional fifth line. Optional lines can be used for telephone numbers, account numbers, or any data, and may be printed at your option. Sort or search names by **any** field. Each name record can be associated with up to 14 different **key groups**. File can be printed by any combination of key groups. Print labels in 1, 2, 3, or 4 adjustable columns, on envelopes or in master index format. Runs on floppies or hard disk, limited only by disk capacity.

HOME BUDGET and CHECKBOOK ANALYST \$59.95

A complete checkbook program together with budgeting, income and expense analysis, comparisons, and projections. Enter and print checks, enter deposits, and compute your current checking balance. Program also handles non-check expenses, bank debits, and income. Monthly and year-to-date summaries and yearly projections based on data through a known month. Monthly expenses compared to a pre-established budget.

SMALL BUSINESS MANAGEMENT SYSTEM \$299.95

A complete **point-of-sale** program for a small business. Handles **order entry, invoicing, inventory,** and **bookkeeping,** including general ledger, accounts receivable, and accounts payable.

Order desk handles order entry and invoicing. Items ordered are automatically deducted from inventory, accounts receivable updated. Includes up to 999 8-character part numbers (1,999 for MS-DOS). Handles both customer accounts and single orders. Invoices printed on forms or plain paper and include discounts, sales taxes, and shipping and handling charges.

Bookkeeper keeps general ledger, accounts receivable and payable, produces customer statements. General ledger produces monthly and year-to-date totals. Receivables tracked to invoices, automatically updated as income entered.

Inventory produces sales and inventory reports showing items in stock, amounts sold, monthly rates of sale, and profits.

Installation tailors program to your business.

SOFTWARE FOR TRS-80™ MODELS 1, 3, and 4 Only

TYPITALL Word Processor \$69.95 TYPITALL with Spelling Checker \$99.95

Word Processor upwardly compatible with SCRIPSIT — it reads your old SCRIPSIT files and uses the same formatting and cursor movement commands. But it is a completely new word processor with many features more advanced than SCRIPSIT, SUPERSCRIPSIT, or other word processors.

Send any control or graphic/special character to the printer. Control/graphic characters included in the text so that you have complete control of all features of your printer. Print the formatted text on the screen before going to the printer. Send formatted text to a disk file for later printing. Merge data from a file during printing. Names, addresses, and other text can be inserted during printing. No need for a separate program for "mail merge" capabilities. Print while editing (spooling). Assign any sequence of keystrokes to a single control key. Call up to 16 help screens at any time. Move cursor forwards or backwards by character, word, line, or page. Reenter the program with all text intact if you accidentally exit without saving the text. Optional spelling checker comes with 29,500 word dictionary. Verify a 3,500 word document in less than two minutes. This is a full-featured word processor – not a demonstration diskl

SYSTEM DIAGNOSTIC \$69.95

Is your computer working correctly? **Are you sure?** System Diagnostic has complete tests for every component of your TRS-80 Model 1, 3, or 4 (separate versions for each model).

ROM: checksum test. RAM: three tests including every location and data value. Video display: character generator, video RAM, video signal. Keyboard: every key contact tested. Line printer: character tests with adjustable platen length. Cassette recorder: read, write, verify data. Disk drives: disk controller, drive select, track seek, read sectory, formatting, read/write/verify data with or without erasing, disk drive timer, disk head cleaner. Single or double density, 1-99 tracks. RS-232-C Interface: connector fault, data transmission, framing, data loop, baud rate generator.

SMART TERMINAL \$39.95

The **Intelligent** telecommunications program for your TRS-80 Model 1, 3, or 4, or Model 2 CP/M. **Memory buffer** for sending and receiving files. **Automatic transmission** of outgoing data. **Automatic storage** of incoming data. **Character translations**. True BREAK key. Help screens, line feed filters, echo and line printer toggle switches, and more.

TRS-80 MODEL III ASSEMBLY LANGUAGE \$29.95

A complete course in assembly language, written for the **beginner**. Contents include: the Z-80 instruction set, ROM and RAM, Using the Editor/Assembler, reading, printing and moving data, arithmetic operations with integers, floating-point and BCD numbers, logical and bit operations, cassette input and output, USR subroutines in BASIC, RS-232-C data communications, disk input and output, and the TRSDOS 1.3 disk operating system

With the book you also receive **Monitor #5**, a comprehensive machine language monitor and debugging program. **These are the last copies of the book in print.**

HOWE SOFTWARE

64 Windmill Road Armonk, New York 10504-2832

Information and same day orders:

(914) 273 - 3998

30-day Money Back Guarantee!

When ordering, please give your computer model number.

*TRS-80 is a trademark of Tandy Corp.

24-Hour TOLL-FREE Order Number:

Outside California call:

(800) 428-7825, ext. 169

Inside California call:

(800) 428-7824, ext. 169

Please allow 2-3 weeks for delivery.

Terms: checks, Visa, Master Card, or C.O.D.
Shipping and handling: \$3:00. Canada, Mexico, Hawaii: \$6:00
Air mail overseas: \$17:00. New York residents add sales tax.

1-800-248-3823


COMPUTERS



EPSON™ PRINTERS

LX-86 Dot Matrix Printer 80 Column
FX-85 Dot Matrix Printer 80 Column
FX-286 Dot Matrix Printer 132 Column
LQ-800 Dot Matrix Printer 80 Column
LQ-1000 Dot Matrix Printer 132 Column
EX-800 Dot Matrix Printer 80 Column
EX-1000 Dot Matrix Printer 132 Column
EX-1000 Dot Matrix Printer 132 Column
LQ-2500 Dot Matrix Printer 132 Column
LQ-2500 Dot Matrix Printer 132 Column
Epson 420I High Speed Printer
DX-20 Daisy Wheel Printer
HI-80 Plotter Printer

EPSON™ FX-85 \$38500



TANDY™ 3000 COMPUTERS

25-4001 Tandy 3000 1.2 Meg Drive 512K
25-4010 Tandy 3000 20 Meg Hard Drive 512K
25-4011 Tandy 3000 40 Meg Hard Drive 640K
25-4050 1.2 Meg Disk Drive Kit
25-4051 360K Disk Drive Kit
25-4060 Hard Disk Controller
25-4061 40 Meg Hard Drive Kit
25-4062 20 Meg Hard Drive Kit
25-4103 MS-DOS 3.2/Basic/Deskmate
25-3046 Deluxe Text Display Adapter
25-3047 Deluxe Graphics Display Adapter
26-5111 VM-1 Monochrome Monitor

26-5112 CM-1 Color Monitor
*Monitors not included

TANDY™1000 SX **\$840**⁰⁰* 384K 2 Disk Drives

25-1051

TANDY™ 1000 COMPUTERS

25-1050 Tandy 1000EX 256K 1 Disk Drive 25-1061 Tandy 1000EX External Drive 360K 25-1011 Memory Plus Board 256K and DMA 25-1062 EX Memory Plus Board 128K and DMA 25-1012 8087 Math Co-Processor 1000/1200 25-1020 VM-4 Monochrome Monitor 25-1022 CM-10 Color Monitor 25-1023 CM-5 Color Monitor 25-1508 MS-DOS/GW Basic Reference Manual 30051030 PBJ Multifunction Board 512K DMA 30051530 ZuckerBoard OK Memory DMA 30051530 ZuckerBoard Multifunction 512K DMA 30281410 256K Memory Chips (Each)

*Monitors not included

TANDY™ 102 **\$370**00 24K Portable Computer 26-3803



TANDY™ PORTABLE COMPUTERS

26-3804 Tandy 100,102,200,600 AC Adapter 26-3805 Tandy 100,102,200 Acoustic Coupler 26-3816 Tandy 100 8K Ram Kit 26-3817 Tandy 102 8K Ram Kit 26-1409 Tandy 100,102,200,600 Printer Cable 26-1410 Tandy 100,102,200,600 Modem Cable 26-3860 Tandy 200 24K Portable Computer 26-3866 Tandy 200 24K Memory Upgrade 26-3901 Tandy 600 Portable Computer 26-3910 Tandy 600 92K Ram Upgrade 26-3808 Tandy Portable 3½" Drive

COLOR COMPUTERS

26-3127 Color Computer 2 64K
26-3334 Color Computer 3 128K
26-3131 Color Disk Drive 0
26-3132 Color Disk Drive 2nd
26-3008 Dual Gyrating Joysticks
26-3012 Deluxe Joystick (Each)
26-3512 CM-8 RGB Color Monitor
26-3124 Multi-Pak Interface
26-3025 Color Mouse
26-3145 Hard Disk Interface
Serial to Parallel Epson
Serial to Parallel Centronic

TANDY" PRINTERS

26-2800 DWP-520 Daisy Wheel 26-2801 DWP-520 Tractor 26-2812 DWP-230 Daisy Wheel 26-2813 DWP-230 Tractor 26-2810 DMP-2110 Dot Matrix 26-2830 PC-695 Color Plotter 26-1279 DMP-2200 Dot Matrix 26-1276 DMP-105 Dot Matrix 26-1277 DMP-430 Dot Matrix 26-1280 DMP-130 Dot Matrix 26-1280 Printer Controller 26-2820 Printer Selector Interface

HARD DRIVES

25-1007 HDController Tandy 1000 25-1025 10 Meg HD External 25-1029 20 Meg Hard Card 26-4157 Cable Kit (6000 & 16) 26-4171 35 Meg Hard Disk Primary 26-4173 35 Meg Hard Disk Secondary 26-4173 70 Meg Hard Disk Primary 25-3020 Tape Cartridge System 25-4066 20 + 20 Meg DCS 25-4064 20 Meg Internal DCS 26-1245 10 Meg DCS

MONITORS & CARDS

25-3010 Monochrome Monitor 25-3045 Dual Mode Adapter Amdek 300A Monitor Amber Amdek 300 Monitor Green Amdek 310A Monitor Amber Amdek 722 EGA Color Monitor Hercules Graphics Adapter Paradise Color/Mono Adapter Paradise EGA Adapter Card Video 7 Mono Graphic Adapter Video Plus Adapter (CC) Trackstar Apple Board

For Technical Questions and Information CALL 1-517-625-4161 FOR ORDERS ONLY CALL 1-800-248-3823

Monday thru Friday 9 am - 6 pm Saturday 9 am - 3 pm EST. 124 South Main Street, Perry, MI 48872

Caught in a Time Stamp

Automatically time-stamp your Basic programs for future reference.

If you program in Basic, you've probably been confused when searching for the last update of a file, or wondered when you last worked on a program. TRSDOS date-stamps your files on the disk directory, and MS-DOS both date- and timestamps directory files. My program, TRS Stamp, automatically puts a time-stamp at the beginning of your program listings for further convenience.

Using TRS Stamp

TRS Stamp (see the Program Listing) is a Basic routine that runs on the Model 4 and Tandy 1000. It also runs on the Models I/III with changes listed later. It is short and easy to implement. You can modify TRS Stamp to insert information other than the time, but unless that information changes often, there is no real advantage to doing so.

Once you have appended TRS Stamp to the end of your program, insert the time-stamp line at the beginning of the program. To activate TRS Stamp, break out of your program and type GOTO x, where x is the line number at which you appended the routine. Then save your program to disk.

You must run your program to initialize the variable tables before you break out. Typing GOTO x without having done so will not work.

Anatomy of TRS Stamp

Line 1 does not have to be the first line of your program. It is, however, easy to list in Basic, and you can review it from the TRSDOS Ready (or MS-DOS's A>) prompt with the List (or Type) command. You can put the line anywhere you want. You can

call the variable for a "Last updated xx/xx/xx" notice in the program. It is important, however, that the space allowed for the update area match the length of the combined date and time line.

The subroutine only accepts replacement characters up to the length of the dummy string.

The VARPTR call in line 65000 determines the location of the string. The VARPTR points to the actual location of the string in the program line because the variable is a constant. Line 65020 determines the actual address of the string.

Line 65030 sets up the replacement string. You can damage your program by overrunning the length of the dummy string with a too-long replacement string. The subroutine in line 65040, therefore, only accepts replacement characters up to the length of the dummy string. It does this by using the length of string parameter in the VARPTR function.

Line 65050 is perhaps the most confusing. The parameters for Poke and Peek commands are restricted to integers, so they must fall within the -32,767 to 32,767 range. If you require a number

larger than 32,767 for poking or peeking, you must subtract 65,536 from it to get a valid integer.

Line 65060 inserts the replacement line, character by character, into the spaces allocated by the dummy string.

Line 65070 is the For. . . Next loop closure for line 65040.

Suggestion for Successful Stamping

You can compress TRS Stamp into two or three lines, but unless you are cramped for space, it is simpler to run the routine as is and then delete it at the end of the program-development procedure. You can merge TRS Stamp from disk if the line numbers are suitable and you saved the routine in ASCII format.

TRS Stamp modifies the program to which it is attached. Make certain that the string variable for the date-stamp is unique in that program and save a copy of the program prior to executing TRS Stamp. After executing the routine, list your program on the screen for a quick visual check.

Model I/III Changes

To make TRS Stamp work on the Model I/III, change line 65040 to read:

65040 FOR T = 1 TO PEEK(C) - 1

Also, change the DZZ\$ and ADDRS variables to two-letter variables. ■


Lionel P. Tercier has been programming in Basic on Tandy computers for several years and is a professional photographer. Write to him at Box 2430, Bonnyville, Alberta, Canada TOA 010.

System Requirements

Model 4 or Tandy 1000/1200/ 3000 (Models I/III with changes) Basic Available on The Disk Series

NEW FLOPPY DISK DRIVES For Mod 1-3-4-1000, IBM





F. 5.25" Power supply \$ 59
G. 1-40tk SS 5.25" TEAC 129
1-40tk DS 5.25" TEAC 139
1-40tk DS 5.25" TEAC 199
H. 2-40tk DS 5.25" TEAC 219
2-40th DS 5.25" TEAC 229
2-80th DS 5.25" TEAC 299
Add 51" for Stainless Steel
Bare 40tk SS 5.25" TEAC 199
Bare 90tk DS 5.25" TEAC 109
Bare 90tk DS 5.25" TEAC 109
Bare 90tk DS 5.25" TEAC 109
TEAC FD55A/B/F Ser, Man 20
TM/00-1/2 Service Manual 20

Aerocomp continues to lead the way to the BEST value in disk drives and related peripheral products for your computer. Sound engineering, high performance, quality construction, no-risk free trial, outstanding warranty service and a reputation for doing the right thing make your decision to buy AEROCOMP the correct one. Please look over our selection and call our toll-free order number with your selection now. If you are not sure of

what you need just call our technicial assistance number and we'll help you out. All drives are new—not factory blems, seconds, closeouts or defunct manufacturers surplus (MPI, Qume, Shugart, etc). Instruction manuals are included at no extra cost and service manuals are available. We appreciate your business and will do our very best to support you.

Add \$4 shipping for non-drive items; \$6 for single drives; \$10 for dual drives.

INCREASED DISK STORAGE FOR YOUR MODEL I

Add 80% more capacity to your disk drives with our Double Density Controller (DDC).

Add double density to your TRS-80 Model I by installing our DDC in your expansion interface. Lets talk about density. The Model I was designed to store data on diskettes in single density. Single density refers to the method used to write data to the disk. Your diskette is organized into tracks and sectors. Early Model I's had 35 track drives while later models, and most aftermarket drives,

had 40 tracks. In single density the tracks on the diskette surface are divided into 10 sectors. Each sector contains 256 bytes of data for a total of 2,560 bytes or 2.5k per track times the number of tracks your drive is capable of addressing. Double density, on the other hand, allows each track to be divided into 18 sectors. As in single density each sector contains 256 bytes but now there are 18 sectors instead of 10 giving an new storage capacity of 4,608 bytes or 4.5k per track. The result is 80% more data in the same space. You may wonder why Radio Shack did not choose to use double density in the beginning. The reason is simple. It costs more money. Double density disk storage techniques were more expensive to implement back then.

Reliable double density operation required a better disk drive than Radio Shack was furnishing in addition to better quality components and diskettes. Therefore, no double density for the Model I. We went to work and came up with a design that allowed



reliable double density operation on the Model I. In fact, our DDC had a higher probability of data recovery than any other disk controller on the market then or since. Our analog design phase lock loop data separator has a wider capture window than the digital types others use. This allows high resolution data centering. Our "DDC" analog circuit allows infinitely variable tuning with opti-

mum attack and settling times. The oft-stated fears of adjustment problems rumored by digital dilettantes have been proved groundless by thousands of satisfied users the world over. The bottom line is state-of-the-art reliability and performance. TRS-80 Model I disk system owners who are ready for reliable double density operation will get 80% more storage per diskette; single and double density operation with far fewer disk I/O errors; single density compatability; simple plug-in operation. You will need a disk operating system that has the necessary double density software driver. All the popular DOS's (except TRSDOS) have the software driver. We have a special combination offer that saves you \$10 and includes the LDOS operating system in the event you do not already have a DOS.

Please add \$5 shipping

LOW COST HARD DISK DRIVES FOR YOUR TRS-80



Our hard disk systems provide you with the latest integrated designs, proper controllers and pre-tested drives to ensure no unwelcome surprises. Our systems are engineered to provide years of trouble free service. These systems come complete ready to go to work. There is nothing else to purchase. Your choice of either CP/M, LDOS or TRSDOS software drivers at no charge. Additional drivers may be purchased for \$30.

Each unit is guaranteed for one full year, parts and labor, at no additional cost. We provide the little things that are so important to a long troublefree life. Things like state-

\$ 399 & up COMPLETE 5 Megabyte **Primary** Add a Secondary for only

Add \$20 shipping \$349 Add \$30 for Stainless Steel

of-the-art continuous duty switching power supplies; buffered seek drives; plated media; filtered forced-air ventilation for cool operation and extended life; power line EMI filter; solid steel construction; gold plated connectors; front panel LED indicators for Power-Ready-Select-Read-Write; built-in diagnostics; automatic error correction; provision to add a secondary drive; plus attention to details and a dedication to provide quality service that is unequaled. We are so sure you will be satisfied that we offer a 14 day



free trial. If you are unhappy with your hard drive, for any reason, just let us know within 14 days of your receipt and we will promptly refund your purchase price (less shipping). You can't go wrong. Start enjoying the real power and speed of your computer with one of our hard disk drives. Do it today! Use our toll-free ordering lines now.

ADDITIONAL SIZES AVAILABLE

	PRIMARY	SECONDARY	
20 Megabyte	749	649	
30 Megabyte	999	899	

20 Megabyte 30 Megabyte Add \$10 shipping

SAVE YOUR MONEY WITH OUR NEW **INTERNAL HARD DISK DRIVES**

When you shop and compare hard disk drives for your Tandy 1000 or IBM you will find the best values here. Our hard drive specialists put together a hard disk system that you can count on to give you years of dependable service.

These systems allow you to boot directly from the hard drive. The controller automatically goes into a self test diagnostics mode at power up that verifies optimum system performance. The latest in error checking and correction is built-in allowing extremely reliable handling of your data. Our installation kit comes complete with everything you need to install it into your computer. Complete illustrated instructions as well as all cables and software needed are included. All connectors and card edges are gold plated and keyed so correct assembly is assured with no possibility of damage to your computer, the controller or hard disk drive. These kits are warranted for one year including parts and labor. Our half-high drives have low power requirements making it unnecessary to modify or change your factory power supply. Model 1000 computers require a memory board (Tandy or other) with DMA. Use your standard PC or MS-DOS version 2.1 or later.

We promise your satisfaction with a 14 day money back guarantee. If, for any reason, you are unhappy with your hard drive just let us know within 14 days of receipt and we will arrange the return and a full refund of your purchase price (less shipping). Why wait? Call us now toll-free.

DISK DRIVES TO YOUR MODEL 3/4

Convert your cassette Model 3 or 4 to disk operation with one of our easy to install kits. Detailed illustrated instructions are included. All you need is a screwdriver and pair of pliers. Included is our own advanced controller with gold contacts capable of 4-drive operation; plated steel mounting towers complete with RFI shield; power supply plus all the cables and hardware. Choose a 1 or 2 drive system or the basic kit and pick the drives you want and your disk operating system from the list on the opposite page. Give us a call. We are ready to help with the answers to your questions.

Complete system, less drives . \$ 159 1-Drive system	HI
Disk Controller Only	69



Add \$4 shipping

CALL TOLL-FREE 800-527-3582 USA 800-442-1310 Texas

214-637-5400 Information



Have your American Express, MasterCard or Visa ready. We will not charge your card until the day we ship your order. Mail orders-are welcome. Money orders are accepted as well as your company, and personal checks as long as they are bank printed and have your address and telephone number. We will ship surface COD with no deposit on most items but all COD's require cash or a Cashier's Check on delivery. Texas residents add State Sales Tax. No tax collected on out of state shipments. There is a one year warranty on all hardware items against defects in materials or workmanship. Your satisfaction is guaranteed on all hardware products. If you are not satisfied, for any reason, call us within 14 days of receipt and we will arrange the return of the hardware product and the cheerful refund of your money (less shipping). All original materials must be intact and undamaged as well as the original shipping container. This offer does not apply to software. Defective software will



2544 West Commerce Street P.O. Box 223957 Dallas, Texas 75212 TELEX: 882761 * FAX: 214-337:4981 * SERVICE: 214-337-4346

'I have found something in almost every issue that has been worth the price of the subscription. I am amazed at the broad spectrum of the technical articles you publish, with ample material for both novice and advanced programmer."

Roger L. Holstege . . . MD

And with 6 to 12 new programs for your Tandy computer in every issue, you too will find something each month that's worth the low cost of your subscription! Just type them in, and they're yours. Spreadsheets, word processors, all kinds of home, business and personal applications, plus helpful utilities that make all your programs easier to write, debug and use.

VALUABLE HARDWARE **PROIECTS**

Want more value? How about 80

Micro's money saving hardware projects you build yourself...or our frequent patches and enhancements that make commercial software programs even better.

PROGRAMMING TECHNIQUES & **TUTORIALS**

You'll add to the value of your computer and get more out of every hour you spend computing with expert guidance from 80 Micro's programming techniques that help you streamline and improve programs. In addition, 80 Micro's step-by-step tutorials keep you ahead of today's fast-moving technologies like nothing else.

HARDWARE & SOFTWARE REVIEWS

Avoid even one chancey hardware purchase, and you've saved enough to repay years of 80 Micro subscriptions! You'll save yourself a bunch of time and hassle, too, with 80 Micro checking out new software for you. Zero in on programs and products you want and skip the clunkers.

► For even quicker service, **CALL TOLL FREE** 1-800-258-5473 (in NH, dial 1-924-9471) and charge it to your credit card!



THE MOST WIDELY READ MAGAZINE IN ITS FIELD

80 Micro is the most widely read magazine serving Tandy users today, with the largest editorial staff in its field. It's the oldest and most authoritative, too, so you know you can trust the help and advice you find in every issue.

START SAVING NOW WITH 48% OFF THE **COVER PRICE!**

Yes it's true. You don't even have to wait for your first issue to start saving with 80 Micro! Just use the coupon below or return the postpaid card opposite and you'll start receiving 80 Micro every month at a full 48% off the Newsstand Rate. If you're ever dissatisfied, for any reason, you'll be reimbursed for all un-delivered issues. Guaranteed! So do it now. And get 80 Micro's value working for you, every month from now on!

every is	I want to ac sue. Enter my issues at the I save a full 4	Introdu	k subscript ictory Rate	of just	12
☐ Paym	ent enclosed		Bill me		
Name (Pleas	se Print)				
City			State	Zip	
	d Mexico, \$27.97, F nail, \$79.97. US fun for delivery				

A Quick Comparison

Display any two Model 4 text files simultaneously and compare them line by line.

In the course of programming, I usually wind up with several versions of the same program. At some point I need to find the precise differences between these versions and make some reason of the rhyme. Reviewing printed copies of the two programs is out of the question. I wrote Compare Plus, a comparing line editor for the Model 4 that lets you look at any two line-oriented text files simultaneously.

Compare Plus does not modify the files. You control the scan as Compare Plus compares identical areas, but the scan stops when a difference is detected. Your comments entered form the keyboard and selected lines from either file are sent to the printer, giving you data for analysis. Compare Plus reads files written in any programming language and saved in ASCII.

I wrote Compare Plus using Misosys's EDAS editor/assembler (see the Program Listing), commenting the program at key points. You can assemble it with EDAS or Pro-Create. Other assemblers might require syntax modifications. In assembled form, Compare Plus is a 1,123-byte (4½-sector) CMD file.

In operation, the first file appears on the top half of the screen, and the second file appears on the bottom of the screen (see Photo). The screen displays nine lines from each. As you tap the spacebar, Compare Plus reads one more line from each file, scrolls up the existing displays, adds the new lines at the bottom of each, and makes a byte-for-byte comparison of these last two lines. Compare Plus scans identical lines from two files at about 800 lines per minute.

As long as the lines are identical, the comparing scan proceeds freely. When there is a difference, the scan stops and you can analyze and record the discrepancy.

System Requirements

Model 4
64K RAM
Editor/assembler
Printer optional
Available on The Disk Series

To assist this analysis, you can scroll through either file forward or backward.

Since Compare Plus accesses the disk frequently, particularly during the reverse scroll, you will get better performance if you place one or both of the files to be compared on a Memdisk.

Photo. Split screen allows you to compare two files.

Using Compare Plus

Assemble Compare Plus as CED/CMD. You have several ways to invoke Compare Plus, so I'll give some examples. First, suppose you want to compare two EDAS files. No parameters are necessary. At the TRSDOS Ready prompt enter:

CED file1/ASM:1 file2/ASM:2

If you do not include a drive number, TRSDOS finds the file on the first available drive, and Compare Plus's screen display

shows the drive. If you don't include the filespecs on the command line, Compare Plus prompts you for them.

Compare Plus looks for an end-of-file (EOF) marker to terminate and return to DOS. EDAS and its successors use X'1A' (26 decimal), and this is the default value for Compare Plus. Scripsit and many other editors use 00 hexadecimal (hex) as the EOF marker, and Basic programs saved in ASCII also have a zero EOF.

If in doubt, list the file using the hex parameter and look at the last few bytes. The last line should be terminated by an X'OD' followed by 1 or 2 bytes. The first byte following the last X'OD' is the EOF marker. If your EOF marker is, for example, X'1C', specify it as a parameter when you invoke Compare Plus:

CED file1/SRC:1 file2/SRC:2 (EOF = X1C') or (EOF = 28)

EDAS can save a file with or without line numbers. With an EDAS line-numbered file, Compare Plus uses those line numbers, otherwise Compare Plus generates line numbers starting with 100, incrementing by 10. When the file contains line numbers, Compare Plus displays a pound (#) sign in front of the filespec. Compare Plus works even if one file is numbered and the other is not. The byte-for-byte comparison only involves the actual text of the line, since the line numbers have no effect in assembly.

To compare two versions of a Basic pro-

Key	Label	Function
spacebar	NEXT	Read one line from each file and compare
Sors	SCAN	Toggle automatic scan on and off
		When scan is on comparison is done
1	LNI	Last line for file 1 to printer (comparison)
2	LN2	Last line for file 2 to printer (comparison)
Corc	COMNT	Enter a comment from the keyboard and send to
		the printer (comparison)
break	EXIT	Exit to DOS
up arrow	ADV1	Advance file 1 by one line (no comparison)
down arrow	ADV2	Advance file 2 by one line (no comparison)
clear-up arrow	REV1	Reverse file 1 by one line (no comparison)
clear-down arrow	REV2	Reverse file 2 by one line (no comparison)

gram, you must save both in ASCII and specify Compare Plus's Basic parameter, which you can abbreviate:

CED file1/BAS:1 file2/BAS:2 (B)

Specifying this parameter suppresses Compare Plus's automatic line numbering and sets the EOF marker to zero. Fur-

You can use the B parameter on any file to avoid automatic line numbering.

thermore, the byte-for-byte comparison now includes the line numbers.

Compare Plus will not display or compare text past its 80-character-per-line limit. Be aware of this restriction when comparing Basic files.

You can use the B parameter on any file to avoid the automatic line numbering. Note also that the EOF parameter overrides the zero associated with the Basic parameter. Thus:

CED file1/txt:1 file2/txt:2 (B,EOF = 26)

suppresses the line numbers but still looks for an EOF marker of X'1A'.

Compare Plus also keeps a line count for each file and displays these numbers to the right of each filespec. The line count refers to the last-read line and decreases as the file is reversed.

Command Details

Once Compare Plus has the two files, you have 10 commands at your disposal (see the Table). The most important is the "next" command, which advances both files by one line. You can rapidly review long, identical sections by holding down the spacebar. If you want more careful visual review, tap the spacebar for single-line

For the most rapid comparison, use the scan command, which supplies a X'20' (spacebar) character automatically after each line comparison. The scan stops when Compare Plus finds a difference in the two files. When scan is in effect, an S displays in the middle line to the right of the line count. The S key toggles the scan function on and off.

When Compare Plus detects a difference in the two files, the scan stops (the spacebar is inoperative), and a blinking asterisk appears in the center of the screen. Review the lines that differ and take whatever action is indicated. You can access all nine of the other commands at this point or exit the hold by pressing any other key.

As noted in the Table, you control in-

Program Listing. Compare Plus.

```
TITLE '<CED - Comparing line editor>'
00110 ;for Model 4 with TRSDOS 6.2
00120 ;by James L. Hawes
00130 @KEY EQU 1
00140 @DSP
                   EOU
00150 @KEYIN
00160
        @DSPLY
                              10
                              15
17
00180
        PVDCTL
        @PARAM
                   EQU
00200
        REXIT
                              22
00210
        @ERROR
                   EQU
        @OPEN
00220
00230
        @READ
                   EQU
00240
        @FSPEC
                   MACRO
00250 SVC
                              #SVC
00260
00270
                   RST
00280
                   ENDM
00290
                   ORG
                              2700H
                                         ;begin parameter table
;demand flag entry
;default is off
;surpress line numbers
;and set EOFM to 00
00300 PTAB
                              80H
                   DB
00310
                              55H
                               BASIC'
00320
                   DB
00330
                   DB
                              BASIC+1
00340
                   DW
00350
                                         ;demand numeric entry
;to set EOFM
                               'EOF'
00360
                   DB
                                                    default is lAH
                              EOF+1
00380
                   DW
00400 ENTRY
                   PUSH
                              HL
                                                    ;search for possible ;parameters first
                              A, (HL)
00410
00420
00430
                   LD
                   INC
                              ØDH
                   CP
00440
                   JR
CP
                              Z, NPARM
00460
                   JR
                              NZ, ENTRY+1
                   DEC
00470
                              DE, PTAB
00480
00490
                   SVC
                              PARAM
                                                    ;blank out screen buffer ;from 2C00 to 337F
00510 NPARM
                   I.D
                              HL, SCRNB
00520
                   LD
00530
00540
                   LD
                              BC,77FH
                   LDIR
                                                    recover command line; and look for filespec 1
00550
                   POP
                              A, (HL)
40H
00560
                   LD
00570
                   CP
                              C, ENFILL
                   CALL
                                                    ;none given so request it ;move filespec to screen
00580
                              DE, MSGFS1
                   LD
00600
                   PUSH
                                                    ;and on return HL will ;point to ':'
                              MOVEN
                   CALL
00610
                                                    ;save till drv # known
88628
                   I.D
                              (DRV1), HL
                   POP
00630
                              DE, FCB1
                                                    ;open file 1 with ;input buffer 2600
00640
                   SVC
00650
                              @FSPEC
                              A, 13H
                                                    to 26FF
                   LD
                   JR
PUSH
00670
                              NZ, ERJP
00680
                                                    ; save command line
                              HL
                              В,0
                              HL, 2600H
00700
                   LD
                   SVC
                              COPEN
00720
                   JR
                              NZ . ERJF
00730
                              A, (FCB1+6)
                                                    ; get drive # found
                              A. 30H
00740
                   ADD
                              HL, Ø
                                                    ;HL => ':' if present
;if drive # was entered
;on command line, this
00760 DRV1
                   EOU
                              5-2
                   LD
                              (HL), ':'
00770
00780
                   INC
                              (HL),A
                                                    simply overwrites
00790
                   LD
00800
                   INC
                                                    ; with identical info
                              (HL), 20H
00810
                   LD
                    PUSH
                                                    ;IX => FCB1
00830
                   POP
                              IX
                                                    remaining command line
                              A, (HL)
40H
00850
                   LD
                              C, ENFIL2
DE, MSGFS2
                                                    ; similar to file 1
00870
                   CALL
00880
                   LD
                   PUSH
00890
                              MOVEN
                   CALL
00900
                               (DRV2),HL
                   POP
 00920
                              DE,FCB2
                                                    ;open file 2 with
                                                    input buffer 2700
                   SVC
 00940
                              @FSPEC
                                                    to 27FF
                              A, 13H
00960
                   JR
                              NZ, ERJP
                              B,0
HL,2700H
 00980
                   LD
                   SVC
                               @OPEN
 00990
                              NZ . ERROR
 01000 ERJP
                   JP
                              A, (FCB2+6)
A, 30H
91929
                    ADD
                    LD
 01040 DRV2
                    EOU
                              5-2
                               (HL), ': '
 01050
                   LD
 01060
                    INC
                               (HL), A
 01070
                   LD
                    INC
                               (HL), 20H
 01100
```

Listing continued

The Ultimate Expansion for your Tandy

by Hard Drive Specialist



Model 1000 Multifunction Boards New!

4 Megabyte Memory PLUS Card

For the Tandy 1000, 1000A, 1000SX, AND THE TANDY 1200. Expands memory beyond the 640K, limited by DOS, to use the Intel/Lotus/Microsoft expanded memory format. Includes a printer spooler, memory disk, and Plus port. PLUS expansion cards (RS232C, Clock, ETC) can be plugged into a special connector, saving a slot for other applications.

4 Megabyte Plus Card (OK)						 			\$199
TanPak-u									

For the Tandy 1000 and 1000A. Seven of the most needed functions/features have been combined into one package using only one expansion slot. Features include memory up to 512K, RS232, Serial Port, Clock-Calendar, DMA, Printer Spooler, Memory disk, and a PLUS expansion port that can use most PLUS cards.

TanPak OK		\$179
T D-I	Consider	

TanPak_{TM} Secondary

TanPaktu SX

Made for the New Tandy 1000 SX, it contains all the features of the TanPaktm except the Memory and DMA features.

ТапРактм SX \$129.

TANDY 1000 Also Tandy 1000 EX

RS232C Serial- Clock/Calender

Piggy/Back Card by Hard Drive Specialist

Now available for the TanPak, the Tandy Memory Expansion PLUS Card, the HDS Memory Expansion Plus Card, and other boards that configure their expansion port with side A (component side) routing conductors to the top side of the 62 conductor dual row header.

RS232C-Serial PLUS Card	\$ 59.
Clock/Calendar PLUS Card	\$ 59.
RS232C-Serial, Clock/Calendar PLUS Card.	. \$129.

Memory Plus Expansion Board

For the 1000, 1000A. Includes sockets for 512K, DMA, and a

Memory PLUS Expansion Card, OK	 	4	 	\$99.
Model 3/4 RS232C Card				
Model 3/4 Floppy Disk Controller Card		4	 	\$99.
Color Computer Floppy Disk Controller Card		0	 	\$99.

Tandy 1000, 1000A, 1000SX Hard Drives

Shop and compare. Hard Drive Specialist has been building hard drive systems for years and have sold thousands of subsystems to satisfied Radio Shack/Tandy customers. Our drives all use buffered seek logic and plated media to result in almost one-fourth the average access found on our competitor's drives. Internal drive systems include an interface card and a half-height hard drive that replaces the top disk drive in both size and power consumption. External units include an interface card, case, power supply, and hard drive unit. All units require a memory board with DMA compatible with the Tandy 1000.

20 Meg Hard Card	\$499.	30 Meg Hard Card \$699.
NEW! 45 MEG Hard Card		\$899.
20 Meg Internal	\$479.	External \$629.
30 Meg Internal	\$679.	External \$829.
		External \$1029.
		External \$1349.

TANDY 1000 EX Hard Drives

Our new External Hard Drives for the Tandy 1000 EX work just like our hard drive units for the Tandy 1000 with the exception of the PLUS type interfacing. Tandy 1000 EX Hard drives require a memory/dma.card

20 Meg External 1000EX Hard D	rive \$729.	
30 Meg External 1000EX Hard D	rive \$929.	ı
42 Meg External 1000EX Hard D	rive \$1445.	
60 Meg External 1000EX Hard D	rive \$1645.	

Tandy 3000, 3000HL Hard Drives

Hard Drives with 16 bit fast controllers that meet or beat the Tandy Products at a fraction of the cost. Add \$50. to the below prices for a controller that will also operate a 1.2 Meg Floppy Disk Drive.

20 Meg Internal \$579.	External
30 Meg Internal \$779.	External \$929.
45 Meg Internal \$979.	
60 Meg Internal \$1299.	
Model 1,3,4 Hard Drives	Model 1 add \$50

20 Meg \$845. 20+20 Meg \$1245. 40 Meg \$1395. 40+40 Meg \$2295. HARD DRIVE SPECIALIST

Order Line 1-800-231-6671 1-713-480-6000

16208 Hickory Knoll Houston, Texas 77059

Ordering Information

Use our WATS line to place your order via Visa. MasterCard: Discover or Wire Transfer. Or mail your payment directly to us. Any non-certified funds will be held until proper clearance is made. COD orders are accepted as well as purchase orders from government agencies. Most tiems are shipped off the shelf with the exception of hard drive products that are custom built. UPS ground is our standard means of shipping unless otherwise specified. Shipping costs are available upon request.

dividual advance of the files with the upand down-arrow keys. To get the reverse scroll, hold the clear key and tap the appropriate arrow key. Do not reverse-read a file to its first line, because this locks up Compare Plus on sector zero, and you must press break to exit.

The four individual scroll commands return to the command key without any comparison. This allows unhindered search. Upon return from the other four commands, next, print 1, print 2, and comment, Compare Plus again compares the last two lines, and the blinking asterisk appears if they differ. If you wish to avoid the repeated comparison and resulting hold following the two-line prints and the comment, increase the value in line 3640 from six to 10.

Compare Plus displays a blinking asterisk if the last two lines differ.

If the difference appears to be a minor change to a single line, you might want to record the two lines. Pressing the 1 key sends the last line from the top file to the printer and the 2 key sends the last line from the bottom file. Compare Plus labels these printed lines as either "File 1" or "File 2."

Reverse Scrolls

Compare Plus performs the reverse scrolls by searching through the files for the beginning of the 10th line preceding the current line. It then reads nine lines and scrolls upwards. All of this action is carried out on a mapped buffer, and only the final result appears on the video. If Compare Plus displays lines 250–330, reversing once displays lines 240–320. This is done without any confusing movement and repeats it at a respectable 280 lines per minute.

Frequently, the difference between the files is due to added lines. When this happens, you can scroll forward and in reverse through each file separately as needed. You might want to send several lines to the printer and make one or more comments to your printout. As you type a comment line, it appears on the bottom line of the screen. Press enter to terminate a comment. The left-arrow key is a backspace. The comment line is limited to 79 characters plus the enter key, but you can use as many lines as you need.

Use the individual scrolls to get the two

files back into sync. Individual scrolling can easily handle situations such as a group of lines moved from one area of the program to another, or two different files containing the same sizable subroutine, where you want to see whether two routines are identical.

I have written an LDOS 5.x Model III version of Compare Plus. Unfortunately,

space is too limited to publish it here. It is available, however, on The 80 Micro Disk Series. See p. 6 for details.■

James L. Hawes has done extensive amateur programming for several years. Send your questions and comments to him at 1781 Lafreniere St., New Orleans, LA 70122.

Listing o	ontinued		
	01110	POP	IY ;IY => FCB2
	01120 01130	LD SVC	C,14 @DSP ;turn on cursor
	01140	JP	START ;get above 27FF to use buffers
	01150 MOVFN	SVC	@FSPEC
	01160 01170	LD	H,D L,E
	01180 MOV1	INC	HL
	01190	LD	A, (HL)
	01200 01210	CP RET	3 Z ;if find 03, no drive given
	01220	CP	1;1
	01230	RET	2
	01240 01250 ENFIL2	JR LD	MOV1 HL,TWO ;HL=>prompt message
	01260	LD	BC,MSGFS2 ;BC=>where to put it
	01270	JR	ENFIL3
	01280 ENFILI 01290	LD LD	HL, ONE BC, MSGFS1
	01300 ENFIL3		@DSPLY
	01310	LD	H,B
	01320 01330	LD	L,C
	01340	SVC	BC,1F00H @KEYIN
	01350	JP	C,EXIT ; <brk> causes exit</brk>
	01360	RET	28444
	01370 FCB1 01380 FCB2	EQU	2800H 2820H
	01390 FCB2	ORG	2840H
	01400 ERROR	OR	40H ;error causes exit
	01410 01420	LD SVC	C, A @ERROR
	01420 01430 EXIT	LD	BC,85FH ; replace cursor with
	01440	SVC	@VDCTL ;underline
	01450	LD	HL, Ø
	01460 01470 DECNUM	SVC 1 PUSH	@EXIT DE
	01480	LD	DE, DECTAB
	01490 DEC1	LD	A, (DE)
	01500	LD	C,A
	01510 01520	INC LD	DE A, (DE)
	01530	LD	B, A
	01540	INC	DE
	01550 01560	LD	DE A, ØAFH
	01570 DEC2	INC	A
	01580	LD	D, H
	01590 01600	LD ADD	E,L HL,BC
	01610	JR	C, DEC2
	01620	POP	HL
	01630	EX	(SP),HL
	01640 01650	CALL	DE, HL DSP
	01660	EX	DE, HL
	01670	EX	(SP), HL
	Ø168Ø Ø169Ø	INC	DE, HL C
	01700	JR	NZ, DEC1
	01710	POP	DE
	01720 01730	LD JP	A, 20H DSP
	01740 DECTA		-10000
	01750	DW	-1000
	01760	DM.	-100
	01770 01780	DW DW	-10 -1
	01790 DSP	CP	9
	01800	JR	Z,DTAB
	01810 01820 DSP1	AND LD	7FH ;strip bit 7 (DE),A
	01830	INC	DE
	01840	PUSH	DE ; check for end of line
	01850 01860	PUSH	HL DE, HL
	01870	LD	DE,-SCRNB ;subtract begining
	01880	ADD	HL,DE ; of screen buffer
	01890	LD	DE,50H
	01900 01910	XOR SBC	A HL, DE
	01920	JR	NC, \$-2
	01930	ADD	HL,DE ;HL = position in line
	01940 01950	LD OR	A,H L ;zero if end of line
	01960	POP	HL ;zero ir end or line
	01970	POP	DE
	01980	RET	1.5 man 1.5 ma
			Listing continued

You Love Those Cheap Mail Order Prices . . . But You Don't Want To Wait For A Week, Right? We Ship Within 24 Hours!

"If you call me (Gus Zeller) by noon, I'll make sure your order is on the truck today"-Gus

You've Never Seen Prices Like These!

"HELP! I've told Gus to clear some shelves to make room for the new products coming this spring to COMPUTER SUPPLIES OF PETERBOROUGH. I'm not buying him any more shelves, that's for sure. Help him out! Call him today"-The Boss

Discount Amiga Software!	LIST	NOW	TRS-80 Bargains Galore! BUSINESS ANALYSIS (T) EASY CALC INVESTORS PARADISE (T) TEXTEDIT (BOOK & DISK) BECINNESS RUSSIAN EVERYDAY RUSSIAN (T) MUSIC TEACHERS PROGRAMMERS PRIMER TYPING TEACHER (Color & M-100 Only) ALIEN ATTACK FORCE (T) MOD. 1-111 ARCHIMEDES APPRENTICE (T) BALL TURRET GUNNER (T) M1-3 ATTLEGROUND (T) M1-3 CRAYON D-M1-8 DOME OF KILGARI (M-1&8, Disk & Tape) TEMPLE OF THE SUN FLIGHT PATH (T) MOD. 1-111 GOMOKU & 3D TIC TAC TOE (T) HOUSE OF THIRTY GABLES LITTLE RED RIDING HOOD T-M1+3 16K MASTER REVERSI MOUNTAIN PILOT (T) COLOR MUSIC MASTER MUSIC TEACHERS SANTA PARAVIA(D&T & Color) SPARROW COMMANDER (D) SWAMP WAR DISK EDITOR DISK SCOPE (D) CASETTE SCOPE LEVEL II 16 32 48K DYNAMIC DEVICE DRIVES (D&T) RENUM COMPRESS (T) TEACHER (T) M1+3 THE ELEMENTS (T) M1+3 VIC 20 History Makers! BUDGETEER (T) PRACTICALC PLUS - T MATH DUEL TINY TUTOR (T) AGGRESSOR (CART) ATTACK FORCE (T) BARREL JUMPER (T) CARNIVAL COMPANION (T) CHOPLIFTER (CART) ATTACK FORCE (T) BARREL JUMPER (T) CARNIVAL COMPANION (T) CHOPLIFTER (CART) CONQUEROR DRAW POKER FLY SNATCHER (T) GALACTIC BLITZ (T) ROAD TEST (T) SKRAMBLE (T) SUBCREAKA (T) TORPEDO (T) YOU WON'T Believe my prices High quality Thompson monitors, Broth printers, Joysticks, all kinds of ribbons (And boy oh boy do we have Cables).	
MIGA TEXT CRAFT	99.95	62.50	BUSINESS ANALYSIS (T)	Only \$4.0
RCHON II ADEPT	39.95	23.23	EASY CALC	Only \$4.0
ELUXE PAINT	99.95	58.08	TEXTEDIT (BOOK & DISK)	Just \$4.0
ELUXE PAINT ART UTILITY DISK	24.95	13.75	BEGINNERS RUSSIAN	I'll Take \$4.0
ELUXE VIDEO	99.95	58.08	EVERYDAY RUSSIAN (T)	Also \$4.0
ACKER (AMIGA)	44.95	28.68	PROGRAMMERS PRIMER	Also \$4.0
HITCHHIKERS GUIDE TO THE GALAXY	39.95	22.00	TYPING TEACHER (Color & M-100 Only)	Also \$4.0
EATHER GODESSES	39.95	21.99	ALIEN ATTACK FORCE (T) MOD. 1-111	Also \$4.0
EVEN CITIES (AMA)	39.95	26.40	PALL TURRET GUNNER (T) M1+3	Also \$4.0
KYFOX	39.95	23.23	ATTLEGROUND (T) M1+3	Also \$4.0
ILTIMA III	59.95	34.85	CRAYON D-M1+3	Also \$4.0
ORK I (AMIGA)	39.95	25.49	DRACONOLIEST (Disk & Tape)	Also \$4.0
ORK III	44.95	24.75	TEMPLE OF THE SUN	Also \$4.0
Barrels of Discount Apple		3 76	FLIGHT PATH (T) MOD. 1-111	Also \$4.0
ERTIFICATE MAKER	49.95	31.24	HOUSE OF THIRTY CARLES	Also \$4.0
MINT SHOP	49.96	24.73	LITTLE RED RIDING HOOD T-M1+3 16K	Also \$4.0
ARDS TALE	44.95	26.81	MASTER REVERSI	Also \$4.0
HITCHHIKERS GUIDE	39.95	21.98	MOUNTAIN PILOT (T) COLOR	Also \$4.0
HIGHT FLIGHT	How Bo	ut 7.00	MUSIC TEACHERS	Also \$4.0
ILENT SERVICE (APP)	34.95	19.23	SANTA PARAVIA(D&T & Color)	Also \$4.0
ORK III DISK	44.95	24.74	SPARROW COMMANDER (D)	Also 34.0
AZZLE DRAW <app iic=""></app>	59.95	39.57	DISK EDITOR	Also \$4.0
YPING TUTOR III	49.95	29.02	DISK SCOPE (D)	Also \$4.0
ATABE MANAGER	6.25	4.14	CASETTE SCOPE LEVEL II 16 32 48K	Also 34.0
MERLIN MACRO ASSEMBLER	39.95	9.50	RENUM COMPRESS (T)	Also \$4.0
low 'bout this Atari Softy	ware?	1000	TEACHER (T) M1+3	Also \$4.0
IABA PERSON INFO MANAGER PHONE	ATA 29.95	19.84	THE ELEMENTS (T) M1+3	Make it \$3.9
PRINT SHOP <ata></ata>	44.95	28.09	VIC 20 History Makers!	
VORD WRITER ST	79.95	52.96	BUDGETEER (T)	Only \$4.2
CHESSMASTER 2000	39.95	23.23	PRACTICALC 20 (D)	34.2
ARCHON <ata></ata>	39.95	13.20	PRACTICALC PLUS - T	Also. \$4.2
Classic Commendant Cause	39.95	21.90	MATH DUEL	Ugh \$4.2
Liassic Commodore Stuff!			TINY TUTOR (T)	Another \$4.2
DATA MANAGER (C128)	69.95	10.84	ALIEN BLITZ (T)	OK. \$4.2
SWIFT CALC W/SIDEWAYS (128)	69.95	43.71	ASTRO BLITZ (CART)	\$4.2
BULGE THE BATTLE ANTWERP	6.25	3.64	ATTACK FORCE (T)	\$4.3
PROFESSIONAL WORD PROCESSORS	9.95	6.59	BARREL JUMPER (T)	\$4.5
CLIP ART COL VOL 1	39.99	24.99	CHOPLIFTER (CART)	\$4.2
DISK ORGANIZER	14.95	9.38	CONQUEROR	\$4.2
NEWSROOM (C64)	49.95	31.23	DRAW POKER	\$4.3
CHESSMASTER 2000 C64	39.95	23.29	GALACTIC BLITZ (T)	\$4.3
TYPING TUTOR III <c64>*</c64>	39.95	21.99	GORTEK & THE MICROCHIPS (T)	\$4.3
RCHON II <c64></c64>	40.00	23.76	JOHNNIE JUMPET (T)	\$4.
RATTLE FRONT	39.95	23.23	PINBALL SPECTACULAR	\$4.3
DEADLINE	39.95	23.29	POWER FLOWER (T)	\$4.5
15 STRIKE EAGLE <c64>*</c64>	34.95	19.24	RABBIT BASE	34.
CIGHT SIMULATOR II <c64></c64>	49.95 Men	29.79 by 7.50	REVERSAL (T)	\$4.3
RACING DESTRUCTION SET	39.95	8.71	ROAD TEST (T)	\$4.
RAINBOW QUEST (D)	9.95	5.50	SKRAMBLE (T)	\$4.
MINBOW QUEST (T)	9.95	10.00	SWARM (T)	\$4
JLTIMA IV (C64)	59.95	34.85	SNAKMAN (T)	\$4.5
ILTIMATE WIZARD	19.95	17.42	SUB COMMAND X021+0087 - SUB COMMAN	ND \$4.
BM Software Bargains!			SUPER HANGMAN (T)	34.
BASE III PLUS	Wow! 695.00	458.75	TANK WAR (T)	\$4.
INANCIAL COOKBOOK <ibm>*</ibm>	49.95	33.85	THE COUNT CAR	\$4.
RAMEWORK <ibm></ibm>	631.82	458.70	BIORYTHAM COMPATIBILITY (T)	\$3.
MAIN STREET IRM	6.95	4.60	TORPEDO (T)	31
R BASE 4000 <ibm></ibm>	450.00	334.12	You won't Believe my prices	on:
OLKSWRITER DELUXE <ibm></ibm>	268.18	194.70	High quality Thompson monitors, Broth	er and Star
OLKSWRITES 3	285.00 34.95	178.26 19.21	printers, Joysticks, all kinds of ribbons a	and cables
'15 STRIKE EAGLE <ibm> ET <ibm></ibm></ibm>	49.95	29.79	(And boy oh boy do we have Cables!).	
LEATHER GODDESSES	39.93	41.99	And Finally	
NORTON COMMANDER	75.00			195.00 129.
SCENERY DISK. 1-6 SILENT SERVICE		0-45.00 19.24	MODEM ANCHOR VOLK MINI VM2 MODEM MINI *0VM2 ANCHOR AUTO	150.00 119.
	31.93	10.01	GENERIC 5 1/4 (dd) DISKS ALL TYPES OF DISKETTE HOLDERS AT DIS	1.15 O.
Mac Titles	****	101 00	PICO TILT & SWIVEL	79.95 59.9
JAZZ <mac> MICROSOFT CHART <mac></mac></mac>	595.00 125.00	401.62 78.12	AVERY LABELS AVAILABLE AT GREAT	
MICROSOFT WORD <mac></mac>	195.00		TALK.	
		75.29	(Ask for my new CSP Catal	og l
PFS FILE & REPORT PFS REPORT <mac></mac>	113.65 113.64	84.38	Mak lot tilly new Cor Catal	UB)

1-800-843-6700



Great Home Electronics Buys
Crimp Tool Set Boxed\$7.95
AB Switch Boxes \$25.97
ABC Switch Boxes \$25.97
Audio Adapters \$0.65
Audio Cables—
3ft, 6ft, 12ft, 25ft\$.75 to 1.74
Audio Splitter—
UHF/VHF/FM Coax 3 Way \$1.43
DM Meter, 25 Pocket\$30.75
ECG Meter, Digital \$34.95, 23.15
Headphones?
Pioneer Deluxe \$10.17
Pioneer Mini
CD Cleaning Kit\$7.49
Whistler Radar Detectors
\$99.88 & Telephone Gear
PhoneMate 2-line
Answering Machine \$156
PhoneMate 8000
Answering Machine \$150
Answering Machine w/PhoneMate \$115
Ivory Bell Telephones\$31,50

5 Free Laptop Computers!

YOU DON'T HAVE TO BUY ANYTHING . . .

(Sure. don't worry, you have just as good a chance at winning if you don't buy a single thing at our rock bottom prices ... Sure! Fill out and send in the coupon below.

I'm going to put the coupons in my huge hat and draw out five names.

Each will win a

NEC 8201A Laptop Computer

I'll get your name and address for my mailing list and five people will win a brand spanking new NEC Laptop! Easy!


(Void where prohibited by law. Employees of WGE, Inc. and Computer Supplies of Peterborough are not eligible)

The Drawing will take place June 1. I'll let the winners know. Good Luck!

YES, Include NEC Laptop.	me in the drawing for the
NAME	
ADDRESS	
CITY	STATE ZIP
SEND TO: Comp NE Marketing C 70 Rte. 202N	puter Supplies of Peterborough Offices
Peterborough, N	NH 03458

990 DTAB	LD	А,20Н	03010		INC	C ; the value of EOF will overrid
300	CALL	DSP1	03020		JR	Z, DSCRN ; the default value of
010 020	RET LD	Z A,E ;tab to positions	03030 03040		LD JR	(EOFM),A ;EOFM is lAH or 26 dec DSCRN ;provide 80 byte buffe
33Ø	ADD	A,2 ; (8-2)+8*n	03050		ORG	START+50H ; for comment line
848	AND	7	03060	DSCRN	JR	\$+2 ;provide for jump to GETKS
350	JR	NZ, DTAB	03070		LD	B,5 ;during auto reverse
868 878	LD OR	A,D E	03080 03090		LD SVC	HL, SCRNB @VDCTL ; display screen buffer
880	RET	ь	93100		LD	B, 3
990 READ1	PUSH	DE	03110		LD	HL, OCIBH ; position blinking cur
100	LD	DE, FCB1	03120		SVC	evDCTL ; in middle of screen
110 120 RD1	LD SVC	(IX+10),A ;position NRN @READ	03130 03140		SVC	BC,820H ;make sure cursor @VDCTL ;character is 20H
130	POP	DE	03150	SWCH	JR	GETKS ;allow jump over compare routi
140	RET		03160	;for si	ngle fil	e commands (ADV1, ADV2, REV1, & REV2
150 READ2	PUSH	DE				0 so that compare is done for
160 170	LD LD	DE, FCB2 (IY+10), A	03190		LD LD	B,6 ;00 if BASIC param used
180	JR	RD1	03200	00112	LD	A,B
190 GET	LD	A,D ; if DE < 3000 must be file 1	03210		LD	DE, SCRNB+320H ; DE => last line file
200	CP	30H	Ø322Ø Ø323Ø		ADD LD	A,E
210 220 GET1	JR LD	NC,GET2 HL,2600H ;current buffer position	03240		LD	E,A A,B
230 BPOS1	EQU	\$-2	83250		LD	HL, SCRNB+6EØH ; HL => last line file
240	LD	A, (HL)	03260		ADD	A,L
250	INC	L	03270 03280		LD	L,A A,80 ;80 characters per line
260	LD JR	(BPOS1), HL ; update position NZ, GETRN+1	03290		SUB	B ;don't compare EDAS line numbe
270 280	PUSH	AF ; if L is 00 need next sector	03300		LD	B, A
290	LD	A, (IX+10)	03310	CLP	LD	A, (DE)
300	CALL	READ1 ; read next sector	03320		CP	(HL)
310	JR	GETRN UT 2799U	03330 03340		JR INC	NZ,DIF HL
320 GET2 330 BPOS2	LD EQU	HL,2700H S-2	03350		INC	DE
340	LD	A, (HL)	03360		DJNZ	CLP
350	INC	L	03370		LD	A,20H ;simulate (space bar)
360	LD	(BPOS2), HL	03380 03390	S_SWCH	JR LD	GETKS ; jump to GETKS+3 if SCAN is ON BC,82AH ; change cursor to '*'
370 380	JR PUSH	NZ,GETRN+1	03400	DIE	SVC	BC,82AH ; change cursor to '*'
390	LD	AF A,(IY+10)	03410		SVC	@KEY
400	CALL	READ2	03420		CP	20H
410 GETRN	POP	AF ; recover input byte	03430		JR	Z,DIF
420 430 FORM	CP EQU	1AH ;default end of file for EDAS \$-1 ;changed to 00 if BASIC	03440 03450		PUSH LD	AF ;save this key stroke BC,820H ;change cursor to blan
430 EOFM 440	JP	\$-1 ; changed to 00 if BASIC Z,EXIT ; or as desired by EOF param	03460		SVC	@VDCTL
450	RET		03470		POP	AF ; recover key stroke
460 BACK1	LD	HL, (BPOS1)	03480		JR	\$+5
470	DEC	L (RDOS1) HIdecrease buffer position	03490	GETKS	LD	KEY ; need a call instead of SVC he HL, TABL ; for AUTO to work
480 490	LD LD	(BPOS1), HL ; decrease buffer position A,L ; when L goes from 00 to FF	03500 03510		LD	B, 12
500	INC	A ; must get prior sector	03520	SRCH	CP	(HL)
510	JR	NZ,BK11	03530		INC	HL S. (MI.)
520	LD	A, (IX+10)	03540 03550		LD INC	E, (HL) HL
530 540	DEC	A ; must decrease by 2 A ; to get prior sector	03550		LD	D, (HL) ;DE => command entry
550	CALL	READ1	03570		INC	HL
560 BK11	LD	A, (HL) ;get prior byte	03580		JR	Z,FOUND ;jump if right
570 580 BACK2	RET LD	HT. (RDOS2)	03590 03600		DJNZ JR	SRCH GETKS ; key pressed was not a command
590 BACK2	DEC	HL, (BPOS2) L	03610	FOUND	LD	HL, SWCH+1
600	LD	(BPOS2), HL	03620		LD	(HL),0 ; do compare if command is firs
510	LD	A,L	03630		LD	A,B ; NEXT, SCAN, LN1, LN2, COMNT
620 630	INC JR	A NZ,BK21	03640 03650		CP JR	6 ;jump over compare for last 4 NC,\$+4 ;ADV1, ADV2, REV1, REV2
640	LD	A, (IY+10)	03660		LD	(HL), GETKS-SWCH-2
550	DEC	A	03670		LD	HL, DSCRN
660	DEC	A BPAD2	03680		PUSH	HL ; return address
570 580 BK21	LD	READ2 A, (HL)	03690 03700		PUSH	DE ; command address
590 BK21	RET	of (mm)	03710	KEY	SVC	@KEY
700 START	XOR	A	03720		RET	
710	CALL	READ1 ; read first sector	03730	TABL	DB	20H
720 730	LD RLCA	A, (2600H) ; checking bit 7 of ; first byte	03740 03750		DW DB	NEXT 'S'
740	CCF	; IIIst byte	03760		DM	SCAN
750	SBC	A, A	03770		DB	's'
760	LD	(NQ1), A ; A = 0 if EDAS line numbered	03780		DW	SCAN
770	JR	NZ,STR1 ;else A = FF	03790 03800		DB DW	'l' LN1
780 790	LD	A,'#' ;'#' indicates line (SCRNB+#),A ;numbers from file	03810		DB	121
800 STR1	XOR	A , Indinbers from fire	03820		DW	LN2
810	CALL	READ2	03830		DB	IC.
820	LD	A, (2700H) ; check file 2	03840 03850		DW DB	COMNT
830 840	RLCA CCF		03860		DW	COMNT
850	SBC	A,A	03870		DB	80H
860	LD	(NQ2), A	03880		DW	EXIT
870	JR	NZ, BASIC	03890		DB	ØBH ;up arrow
88Ø	LD	A, ' & ' (SCRNB+3CØH), A	03900 03910		DW DB	MAH ; down arrow
890 900 BASIC	LD	BC, 0	03920		DW	ADV2
910 BASIC	LD	A,B	03930		DB	08BH ;clr up arrow
920	OR	C	03940		DW	REV1
930	JR	Z, EOF	03950		DB	8AH ;clr down arrow REV2
940	XOR	A ;suppress line numering	03960 03970	SCAN	LD LD	HL,S_SWCH+1
95Ø 96Ø	LD	(NQ1),A (NQ2),A	03980	John	LD	A,GETKS-S_SWCH-2 ; jump to GETKS
970	LD	(COMP+1),A	03990		LD	C,20H ; to blank out "S"
980	LD	(EOFM), A ; end of file is 00	04000		CP	(HL) ; compare to current value
990 EOF	LD	BC,-1 A,C ;if both BASIC and EOF are given	04010 04020		JR LD	NZ,SCAN1 ; and toggle to the oth A,GETKS-S_SWCH+1 ; jump to GETKS
000						

MARYMAC INDUSTRIES INC.



McManus family owned and operated

References in your area

,100% pure Tandy products

Best possible warranty

Lowest discounted prices—call: We will MEET OR BEAT

Mastercard, Visa, American Express

We always pay freight and insurance

Most items shipped Same Day UPS

"World's largest independent authorized computer dealer."

22511 Katy Fwy., Katy (Houston), Texas 77450 (713) 392-0747 Telex 774132

OPEN MON.—FRI 8-6 CST 6 phone lines to serve you better!

CALL TOLL FREE 800-231-3680

30 ; avoid	the key	poard input at GETKS and force auto NEXT	05060	LD	DE,-10
40	LD	c, 's'	05070	LD	HL, (LNMB2)
50 SCAN1 60	LD LD	(HL), A ;alter jump at S_SWCH HL,SCRNB+3FØH	05080 05090	ADD LD	HL,DE (LNMB2),HL
70	LD	(HL),C ;put "S" or blank on screen	05100	DJNZ	RV21
80	RET	2 4100	05110	CALL	GET2
90 NEXT	LD EQU	B, ØAFH ; if A is non zero both files \$-1 ; will advance	05120 05130 APREP	LD	A, ØAH ; key stroke for ADV2 HL, AUTO
10 ADVI	PUSH	AF ; will advance	05140 APREP	LD	(HL),9 ;advance 9 lines
20	LD	DE, SCRNB+0A0H ; scroll eight lines	05150	INC	HL
30	LD	HL,SCRNB+0F0H	05160	LD	(GETKS+1), HL ; call AUTO instead of
40 50	LD LDIR	BC,280H ;DE = SCRNB+320H = begin line 9	05170 05180	INC LD	HL
60	CALL	GET ; this makes LDLN loop easier	05190	LD	(HL), A ; pass proper key stroke to AU: HL,DSCRN+1 ; jump over display
70	EX	AF, AF' ; save first byte	05200	LD	(HL), GETKS-DSCRN-2 ; to keep scree
80 90 NQ1	LD EQU	A, Ø \$-1	05210	RET	from flashing while 9 lines are read
00	OR	A ;generate line numbers from	05220 AUTO 05230	DB LD	0 ;counter A,0 ;contains key for ADV1 or ADV2
10	CALL	NZ,LNUMB1 ;100 by 10's	05240	LD	HL, AUTO
20	CALL	LDLN ;load and display one line	05250	DEC	(HL) ; decrease count
30 40 LNCNT1	LD EQU	HL,0 \$-2 ;real line counter	05260	JR	Z, DUN
50	INC	HL	05270 05280 DUN	RET LD	HL, KEY ; replace call to KEY
60	LD	(LNCNT1), HL	05290	LD	(GETKS+1), HL
70	LD	DE,SCRNB+20H	05300	XOR	A
80 90	POP	DECNUM . AF	05310	LD	HL,DSCRN+1 ; remove jump
90	OR	Ar A	05320 05330	LD	(HL),A A,(AUTO+2) ;advance last of 9 lin
10	RET	z ; return if command was ADV1	05340	RET	, (noto.s, jauvance last of 9 life
20 ADV2	LD	DE, SCRNB+460H	05350 CBKS	LD	B, 4
30	LD	HL, SCRNB+4BØH	05360	PUSH	HL
40 50	LD LDIR	BC,280H ;DE = SCRNB+6E0H = begin line 9	05370	SVC	@VDCTL ;get current cursor posn
60	CALL	GET = SCRNB+BEBN = Begin line 9	05380 05390	LD POP	A,L ;look at column HL
70	EX	AF, AF'	05400	OR	A ;don't backspace
80	LD	A, 0	05410	JR	Z,CINPT ;passed beginning of line
90 NQ2	EQU OR	\$-1 A	05420	LD	C, 8
10	CALL	NZ,LNUMB2	05430 05440	DEC	@DSP HL
20	CALL	LDLN	05450	JR	CINPT
30	LD	HL,0	05460 COMNT	LD	В, 3
40 LNCNT2	EQU	\$-2 !!	05470	LD	HL, 1700H ; move cursor to begin
50 50	INC LD	HL (LNCNT2),HL	05480 05490	SVC LD	@VDCTL ; of line 23 BC,85FH ; and change it to
70	LD	DE, SCRNB+3EØH	05500	SVC	BC,85FH ; and change it to @VDCTL ; underscore
80	CALL	DECNUM	05510	LD	HL, START
90	RET	12.22	05520	PUSH	HL ; save for @PRINT
00 LDLN	EX CP	AF,AF' ;recover first byte ØDH ;check for empty line	05530	LD	B,4FH ;79 characters
10	JR	## ODH check for empty line 2,LDLN2	05540 CINPT 05550	SVC CP	6KEY
30 LDLN1	CALL	DSP	05560	JR	Z,CBKS
40	JR	Z, WASTE ; Z if more than 80 characters	05570	CP	ØDH
50	CALL	GET	05580	JR	z, CDUN
60	CP	<pre>ØDH ;end of line Z,ERAS</pre>	05590	CP	20H ; ASCII range
70 80	JR JR	LDLN1	05600 05610	JR CP	C, CINPT 80H
90 LDLN2	LD	A,88H ;block graphic character	05620	JR	NC, CINPT
00	LD	(DE),A	05630	LD	(HL),A
10	INC	DE	05640	INC	HL
20 ERAS 30	LD CALL	A,20H ;erase to end of line DSP	05650 05660	LD SVC	C,A @DSP
40	RET	2	05670	DJNZ	CINPT
50	JR	ERAS	05680 CTRM	SVC	@KEY ;80th character must be 0DH
60 WASTE	CALL	GET ; just read to next 0DH	05690	CP	0DH
70	CP	ODH	05700	JR	NZ, CTRM
80 90	JR RET	NZ, WASTE	05710 CDUN	LD	(HL), A ; an ØDH
00 LNUMB1	LD	BC,10 ;generate EDAS type line	05720 05730	POP	HL ; recover START @PRINT ; send line to PRINTER
10	LD	HL,90 ; numbers from 100 by 10's	05740	RET	Carrie Jacob Lane to Little
20 LNMB1	EQU	\$-2 UL BC	05750 LN1	LD	HL,SCRNB+320H ; begin last line file
30 40	ADD LD	HL,BC (LNMB1),HL	05760 05770 INC	JR	\$+5
50	JP	DECNUM	05770 LN2 05780	LD PUSH	HL,SCRNB+6EØH ; begin last line file HL ; save for second @PRINT
60 LNUMB2	LD	BC,10	05790	LD	DE,50H
70	LD	HL,90	05800	ADD	HL,DE ;get end of line
80 LNMB2 90	ADD	\$-2 HL,BC	05810 LSRCH	DEC	HL A CHILL
30	LD	(LNMB2),HL	05820 05830	LD CP	A,(HL) 20H ;ignore all trailing spaces
10	JP	DECNUM	05840	JR	Z,LSRCH ;ignore all trailing spaces
20 REV1	CALL	BACK1 ;go back one byte (@DH)	05850	INC	HL
3Ø	LD	B,10 ;go back 10 lines	05860	LD	(HL), ØDH ; mark end line with ØI
40 RV11 50	CALL	BACK1 ØDH ;look for end of line	Ø587Ø	EX PUSH	(SP), HL ; save the spot to star
50	JR	NZ, RV11	05880 05890	LD	HL ;replace begin spot A,H
70	LD	HL, (LNCNT1)	05900	CP	2FH
80	DEC	HL ;decrease real line numb	05910	LD	HL, TWO
90 aa	LD	(LNCNT1), HL	05920	JR	NZ,\$+5 ;NZ means it was 32H and want
00 10	LD LD	DE,-10 HL,(LNMB1) ;decrease generated	05930	LD	HL,ONE
20	ADD	HL,DE ;line number	05940 05950	SVC	<pre>@PRINT ;print file ID message HL ;recover beginning of line</pre>
30	LD	(LNMB1), HL	05960	SVC	@PRINT ;print line
40	DJNZ	RV11 ;loop for 10 lines	05970	POP	HL ; recover end spot and
50 60	CALL LD	GET1 ;get into forward gear again A,0BH ;key stroke for ADV1	05980	LD	(HL), 20H ; remove the 0DH
70	JR	A,0BH ;key stroke for ADV1 APREP	05990 06999 ONE	RET	; before screen display
80 REV2	CALL	BACK2	06000 ONE 06010 TWO	DB DB	'File 1 ',3 'File 2 ',3
90	LD	B, 10	06020 BOT	EQU	\$
00 RV21	CALL	BACK2	06030	ORG	2С00Н
10	CP	ØDH	06040 SCRNB	DB	20H
20 30	JR LD	NZ,RV21 HL,(LNCNT2)	06050 MSGFS1	EQU	SCRNB+2 ;where to put filespec
		HL	06060 MSGFS2 06070	EQU	SCRNB+3C2H ; on screen display ENTRY
40	DEC				

Can we talk?

CP/M vs TRSDOS

By moving to CP/M on your Model 4 you achieve two things. First you open the door to a wealth of existing software. More 8-bit software runs under CP/M than any other operating system. This includes virtually all of the "big name" programs which have set the standards by which all others are measured. Programs like WordStar, dBASE II, and Turbo Pascal are available for CP/M, but not TRSDOS. Public domain software, almost unknown under TRSDOS, fills hundreds of megabytes of disk space. Valuable public domain programs like the Small C Compiler are just a toll-free phone call away. Most importantly, hundreds of applications programs are available from a multitude of vendors. Many include the source code. Wouldn't you like to be able to choose from scores of Accounts Receivable or General Ledger programs, instead of the meager selection you now have? Circle our special Reader Service number 600 on the Reader Service Card to receive our comprehensive free listing of suppliers of application programs that run under CP/M.

What about the future?

When the time comes to move up to another computer it will almost certainly use MS-DOS. That's when CP/M users get a pleasant surprise. Since MS-DOS was a derivative of CP/M it operates in almost the same manner. Even better, most of the same software packages are available in 16-bit form and they operate in virtually the same way that they did under CP/M.

Is it easy to use?

Montezuma Micro's CP/M has been carefully crafted to present a maximum of features while taking a minimum of memory. It supports all of the standard features of the Model 4/4P/4D computers, as well as most of the optional ones. Our CP/M has been consistently been awarded the highest ratings in industry magazines. It is version 2.2, the most popular and reliable of all the versions of CP/M produced. Our CP/M has been made as easy to use as possible. All customer-selected features are chosen from simple menus in our CONFIG utility. This includes the ability to configure a disk drive to run like that of scores of other CP/M com-

puters for maximum ease of software portability. Using the unique DBLCROSS program in our Monte's Toolkit utility package you can move files back and forth between CP/M, TRSDOS (1.3 and 6.x), and MS-DOS.

Why use Montezuma CP/M?

We have already told you why our CP/M is the best for the Radio Shack Model 4 computer. The only question left to answer is "Why buy CP/M at all?" Radio Shack has abandoned TRSDOS — all of their new machines use MS-DOS. Most of the software producers have followed, leaving no new software development and saddling the TRSDOS user with whatever software "left-overs" he can find. Which DOS do you want to head into the future with: the one originally written for the Model I or the one that served as the basis for MS-DOS? Make the right choice right now for just \$169.

If I need support?

We don't forget you after the sale. If you have a problem you will find our phones are answered by people, not answering machines or hold buttons. Our philosophy is very simple — we want you to be happy and satisfied with your purchase. If you have a problem then we have a problem, and we'll do whatever we can to resolve it.

Cost to update?

Our owners are protected against instant obsolescence by our lifetime upgrade policy. At any time you can return your original CP/M disk to be upgraded to the latest version free of charge, except for a small shipping and handling fee. Periodically we publish NEW STUFF, a newsletter for registered users of Montezuma Micro CP/M. This publication carries news about new products, tips for getting more out of CP/M, and other valuable information for our users. It is sent free of charge to registered owners.

Can I use a hard disk drive?

CP/M hard disk drivers are available for Radio Shack, Aerocomp, and most other popular brands of hard disk drives. These drivers allow the hard drive to be partitioned into one to four logical drives of varying sizes. These drives may all be used by CP/M, or may be divided between CP/M and TRSDOS. A head-parking utility is included on the driver disk to minimize the risk of damage when the hard disk drive is not in use. Also included at no charge is a utility which will copy, compress, list, print, and delete files with ease. There isn't much you can say about a driver. It either works or it doesn't. Ours works supremely and it only costs \$30.

Hard disk backup?

Unlike the high-priced, underpowered backup utilities available for backup of TRSDOS hard drives, our CP/M HARDBACK utility makes the backup of a hard disk to floppies quick and painless. Only HARD-BACK gives you the choice of backing up the entire drive or only those files which it knows have been changed since the last backup. Daily backup is no longer a chore, since only new data must be copied. With HARDBACK you can quickly restore an entire drive, or only a single file if necessary. Only HARD-BACK will perform a complete check of the hard disk drive and lock out tracks which have become flawed to prevent the use of those tracks for later data storage. Add this supreme program to your hard disk for just \$49. Isn't your time and data worth it?

Specs?

Size of Transient Program Area (TPA): 56,070 bytes in a 64k system. 55,046 bytes in a 63k system (with optional hard disk driver). CP/M IOBYTE: Fully implemented. Device Drivers: Disk (35, 40, 77, & 80 track, single/double density single/double sided, 3, 5, or 8 inch. (More than 85 disk formats supported) Maximum Disk Capacity: 40T SS = 220k, 40T DS = 440k, 80T DS = 880k RS-232: All word lengths, parity, & baud rates. Parallel Printer: With or without linefeed and/or formfeed. Video: 24 by 80 with reverse video. Keyboard: Full ASCII with 9 function keys. RAM Disk: 64k, automatic on 128k systems. Hard Disk: Optional drivers available at extra cost for most popular models. Standard CP/M programs included: ASM, DDT, DUMP, ED, LOAD, MOVCPM, PIP, STAT, SUBMIT, SYSGEN, and XSUB.

Order Information

Give us a call now with your order and we will ship immediately. Prices include delivery to your door in the lower 48 States including APO/FPO. All others please add an amount commensurate to shipping requested. Any excess will be refunded. Credit cards will not be charged before we ship your order. The suitability of software selected is the responsibility of the purchaser as there are NO REFUNDS ON SOFTWARE. Defective software will be replaced upon it's return, postpaid.

The toll-free lines are for orders only.

Specifications/prices are subject to change without notice.









ORDER NOW ... TOLL-FREE 800-527-0347 U.S.A.



For Information: 214-631-7900 P.O. Box 224767 Dallas, Texas 75222 U.S.A.

They Say...We Say. NOW!

TURBO M

OUR FINEST ACCOMPLISHMENT TO DATE.

LOOK AT THESE FEATURES

- 8 Slot motherboard, we even offer an *EXTRA* slot.
- Compatibility—Phoenix bios systems, by far the best and most compatible. We guarantee that the major software will operate flawlessly. Lotus 2.x, Symphony, Flight Simulator (in our color systems), Wordstar 2000, Word, DBase, RBase, the list goes on and on...
- Turbo speed (8MHz clock—you can switch down to 4.77MHz like the competition, would you really want to!!
- Turbo light—No guessing. If it's red, it's Turbo
- 640 K memory—High quality pre-tested chips
- FREE amber monitor and Hercules compatible graphics card
- High resolution graphics—Both the monitor and display card are Hercules compatible. (No low quality composite stuff)
- We even give you a tilt and swivel base for your comfort
- One 360K high quality floppy drive. (Our head technician checks each one)
- Continuous and heavy duty 150 Watt power supply. (15 Watts more than most competitors)
- · AT style keyboard, optional 5161 keyboard
- · A slot for a math co-processor chip 8087
- · One serial port-you can add a second port
- One parallel port for your printer
- One game port for joy sticks
- One light pen port
- A clock calendar for automatic time and date
- FCC approved—(ask the competition if their's is)

Free Software too!

DOS tutorial, PC-Write and Word processor, PC-Calc, spreadsheet, PC-Deskteam and utilities, too.

Long waits for your system—never!! Order today and have it today—if ordered by 10:00 am (call for details). Otherwise we will ship it by tomorrow, during weekdays, if in stock.

Complete Turbo M System with Hard Drives

The absolute newest technology. Our systems constantly monitor the quality of operation of the Turbo M/ST Hard Drive.

11 meg Complete Turbo M System \$949.95 21 meg Complete Turbo M System \$1149.95 32 meg Complete Turbo M System \$1199.95 46 meg Complete Turbo M System \$1349.95



\$699.95

TURBO-M

OPTIONS SECTION

EGA, Color, Hard drive systems, Tape backup systems

SERVICE

No one does it better. Shipments are made everyday from Monday to Friday. All in-stock items are shipped within 24 hours of your placing your order. Want it quickly? I mean real fast!! How about today? Call us by 10:00 a.m. any weekday, and we will schedule same day shipping!!

WARRANTY and AFTER WARRANTY SERVICE

As a team, we have been servicing you since 1981. We know how important it is for you to be up and running. In and out of warranty service is treated the same, IMPORTANT! All repairs are done within 24 hours - not too shabby!

SPEAKING OF WARRANTIES

We're the best. TWO YEARS on all electronic boards and fifteen months on all mechanicals. Just ask us. We will tell you about the "extra" advantages we give you!!

TECHNICAL ASSISTANCE

We pride ourselves in our ability to assist in most situations. We will even try to help you, when able, with a competitors product, or try to steer you in the right direction for assistance. Just call our well-trained technical staff. You will find them anxious to be of service.

Who would you rather listen to?



'URBO-M

OPTIONS SECTION

EGA, Color, Hard drive systems, Tap backup systems

MONEY BACK GUARANTEE

Absolutely. We don't want you to have a product that you aren't happy with. Just let us know within 21 days of receipt and upon return, we will give you a refund (less shipping, handling and insurance).

The prices quoted here are for cash. We will accept MasterCard, VISA, Discover and American Express. Please ask for details.

COD's are accepted without any deposit. Purchase orders accepted based on prior approval, call for details.

Our hours are from 9:30 am to 5:30 pm. Monday through Friday and until 4:00 on Saturday.

Not responsibe for typographical errors. Terms and specifications may change without notice.

Trademarks: IBM Corp. Montezuma Micro

Eagle Computer

Tandy Corp. Zenith Corp. Lotus Development Microsoft Inc.

Keytronics Corp.

TURBO M/AT T286

Check us out

- · Compatibility-Phoenix bios systems, by far the best and most compatible. We guarantee that the major software will operate flawlessly. Lotus 2.x, Symphony, Flight Simulator (in our color systems), Wordstar 2000, Word, DBase, RBase, the list goes on and on. .
- Turbo speed (8MHz clock-you can switch down to 6MHz, but no need to. .)
- · Turbo light-No guessing. If it's on, it's Turbo
- 1024 K memory-High quality pre-tested chips.
- · FREE amber monitor and Hercules compatible graphics card
- · High resolution graphics—Both the monitor and display card are Hercules compatible. (No low quality composite stuff)
- · We even give you a tilt and swivel base for the monitor for your comfort
- · One high quality floppy drive. 1.2 meg or 360K. (Our head technician checks each
- · Continuous heavy duty power supply (200
- · AT style keyboard, optional 5161 keyboard
- 2 Serial Ports—1 parallel port
- A slot for a math co-processor chip 80287
- · One parallel port for your printer
- · One light pen port
- · A clock calendar for automatic time and date w/battery backup
- FCC approved—(ask the competition if theirs is)

After we burn the Turbo M/ in for at least 72 hours. we set up your system to automatically turn on the high speed clock and give you the correct time and date.

Long waits for your system-never!!! Order today and have it today-if ordered by 10:00 a.m. (call for details) Otherwise, we will ship it by tomorrow, during weekdays, if in stock.

SMART INC.

200 Homer Avenue Ashland, MA 01721 1-617-872-9090

OLL FREE

ORDERING 1-800-34

3103

2981

4388

End

Data-Statement Generator

Convert assembly code to Basic Data statements with checksums.

+10:RETURN

onverting assembly-language source code to Basic Data statements has its advantages. For instance, you can use converted assembly routines within Basic programs, or you can share your assembly code with programmers who don't own an editor/assembler.

My program, Datapoke, reads a CMD file and writes a Basic program. This Basic program contains the CMD file code in Data statements (in decimal format). It also contains the code to read the Data statements, verify each line with checksums and write a CMD file, using the same file name as the original CMD file.

How It Works

Datapoke differs from similar utilities in that it does not go past the actual end of file within the last record of the source file, and it builds a checksum value for each line of data. When the new program runs, it processes each Data Statement and checks its sum against the final value at the end of the line (the value with the minus-sign (-) flag preceding it). If the numbers match, the program processes the next line. If they do not match, it reports a checksum error in the current line and displays the line number.

Should someone type in the new program and enter an incorrect data or checksum value, the program indicates an error when run.

Using Datapoke

Type Datapoke in Basic on your Model I/III/4 (Program Listing 1) or Tandy 1000 (Program Listing 2) and save it. Datapoke uses the "Source" prompt to ask for the file name of the CMD program you want to convert, and the "Destination" prompt for the name of the Basic program that you want to create.

Datapoke opens the files, displays the

System Requirements

Model I/III/4 or Tandy 1000 16K RAM Disk Basic or GW-Basic One disk drive Available on The Disk Series

Program Listing 1. Datapoke for Models I/III/4. See p. 116 for information on using the checksums in Listings 1 and 2. 18 CLS:PRINT"DATAPORE WITH CHECKSUM -- BY DAVID GOBEN":PRINT 3989 18 CLS:PRINT"DATAPORE WITH CHECKSUM -- BY DAVID GOBEN":PRINT 20 PRINT:PRINT"THIS PROGRAM CONVERTS A MACHINE LANGUAGE (CMD) PR OGRAM; 36 PRINT"THE SOURCE FILE, TO A BASIC LANGUAGE FORMAT FILE; THE" 48 PRINT"DESTINATION FILE":PRINT:ON ERROR GOTO Ø 50 CLEAR:DEFINT A-Z:Q\$=CHR\$(34) 68 SP\$="":LINE INPUT"SOURCE MACHINE LANGUAGE FILE: ";SP\$:OPEN"I" 4784 ,1,SF\$:CLOSE 70 DF\$="":LINE INPUT"DESTINATION BASIC LANGUAGE FILE: ";DF\$ 4837 3767 1250 78 DF9="1518E INFOT DESTINATION BASIC LARGORD FILE: "JPF\$ 80 IF DF9-SP\$ THEN 138 90 T1\$-SF\$:X=INSTR(SF\$,":"):IF X THEN T1\$-LEFT\$(SF\$,X-1) 100 T2\$-DF\$:X=INSTR(DF\$,":"):IF X THEN T2\$-LEFT\$(DF\$,X-1) 110 IF T1\$-T2\$ THEN IF T1\$-SF\$ OR T2\$-DF\$ THEN 130 128 OPEN*O",2,DF\$:GOTO 140 139 PRINT"MATCHING FILESPECS!!!":FOR X=1 TO 3800:NEXT:PRINT:GOTO 3352 3349 2859 60 140 OPEN"R",1,SF\$:FIELD 1,1 AS A\$:P!=PEEK(VARPTR(A\$)+1)+256*PEEK 4311 148 OPEN"R",1,SF\$:FIELD 1,1 AS A\$:PI=PEEK(VARPTR(A\$)+1)+256*PEEK (VARPTR(A\$)+2) 158 IP PI>32767 THEN P=PI-655361 ELSE P=PI 168 PRINT\$2,"18 'DATA POKE FORMAT CREATED ON DATAPOKE/BAS" 179 PRINT\$2,"28 CLS:PRINT"Q\$"BUILDING '"TI\$"'Q\$":RESTORE" 189 PRINT\$2,"28 CLS:PRINT"Q\$"BUILDING '"TI\$"'Q\$":RESTORE" 190 PRINT\$2,"48 CS=8:L=L+18" 280 PRINT\$2,"48 CS=8:L=L+18" 280 PRINT\$2,"58 READ A\$:IP A\$="Q\$"END"Q\$"HEN CLOSE:END" 218 PRINT\$2,"58 READ A\$:IP A\$="Q\$"-"Q\$"THEN IF VAL(MID\$(A\$,2))= CS THEN 48 ELSE PRINT"Q\$"CHECKSUM ERROR IN LINE"Q\$"L:END" 220 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 240 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 241 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 242 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 243 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 244 PRINT\$2,"88 GOTO 58":PRINT\$2,"98 ''' DATA AREA '''' 256 PRINT"RECORD 1," 277 GOSUB 318:FA=7 THEN 298 288 GOSUB 318:Z=A:FOR Z!=1 TO Z:GOSUB 318:NEXT Z!:GOTO 278 298 FOR Z=1 TO 3:GOSUB 318:NEXT Z:IF CF=8 THEN GOSUB 348 389 PRINT\$2,"END":CLOSE:PRINT:PRINT"...DONE":END 318 A=PEEK(P*X):X=X+1:IF X>255 THEN X=8:Y=Y+1:GET 1,Y:PRINT,"REC ORD"STRS(Y),"; 328 PRINT\$2,QS;MID\$(SRS(A),2):QS=",":CF=8:CS=CS+A 4593 2330 2691 3284 3016 3558 3888 1288

320 PRINTE2,Q5;MID\$(STR\$(A),2);Q\$=",":CF=8:CS=CS+A
330 DC=DC+1:IF DCC15 THEN RETURN
340 PRINTE2,",-"MID\$(STR\$(CS),2):CS=0:DC=8:CF=1
350 PRINTE2,CHR\$(13);Q\$="":PRINTE2,MID\$(STR\$(L),2)" DATA ";:L=L

Program Listing 2. Datapoke for the Tandy 1000. 18 CLS:PRINT DATAPOKE WITH CHECKSUM -- BY DAVID GOBEN PRINT 20 PRINT:PRINT THIS PROGRAM CONVERTS A MACHINE LANGUAGE (COM) PROGRAM; 3989 4795 4897 30 PRINT THE SOURCE FILE, TO A BASIC LANGUAGE FORMAT FILE; THE 40 PRINT DESTINATION FILE PRINT: ON ERROR GOTO 8 50 CLEAR: DBFINT A-Z:QS-CHRS(34) 60 SFS-":LINE INPUT SOURCE MACHINE LANGUAGE FILE: ";SFS:OPEN"I",1 4837 3767 1250 ,SFS:CLOSE 70 DFS="":LINE INPUT DESTINATION BASIC LANGUAGE FILE: ";DFS 78 DFS="1LINE INPUT DESTINATION BASIC DANGUAGE FILE: "; 88 IF DFS=SF\$ THEN 138 98 T1\$=SF\$:X=INSTR(SF\$,":"):IF X THEN T1\$=MID\$(SF\$,X+1) 108 T2\$=DF\$:X=INSTR(DF\$,":"):IF X THEN T2\$=MID\$(DF\$,X+1) 110 IF T1\$=T2\$ THEN IF T1\$=SF\$ OR T2\$=DF\$ THEN 138 128 OPEN*O*,2,DF\$:GOTO 148 128 OPEN"O",2,DF\$:GOTO 148 138 PRINT"MATCHING FILESPECS!!!":FOR X=1 TO 3888:NEXT:PRINT:GOTO 6 4311 140 OPEN"R",1,SF\$,1:FIELD 1,1 AS A\$:RL=LOF(1)/512:IF LOF(1)>RL*512 THEN RL=RL+1 16 PRINT\$2,"16 'DATA POKE FORMAT CREATED ON DATAPOKE/BAS" 176 PRINT\$2,"28 CLS:PRINT"Q\$"BUILDING '"T1\$""Q\$":RESTORE" 186 PRINT\$2,"28 CCS:PRINT"Q\$"BUILDING '"T1\$""Q\$":RESTORE" 187 PRINT\$2,"26 CS=6:L=L+16" 188 PRINT\$2,"26 CS=6:L=L+16" 189 PRINT\$2,"56 READ A\$:IF A\$="Q\$"END"Q\$"THEN CLOSE:END" 190 PRINT\$2,"56 READ A\$:IF A\$="Q\$"SEND"Q\$"THEN IF VAL(MID\$(A\$,2))=C\$ THEN 46 ELSE PRINT"Q\$"CHECKSUM ERROR IN LINE"Q\$"L:END" 190 PRINT\$2,"76 A=VAL(A\$):PRINT\$1,CHR\$(A);CS=CS+A" 191 PRINT\$2,"76 A=VAL(A\$):PRINT\$1,CHR\$(A);CS=CS+A" 191 PRINT\$2,"86 GOTO 56":PRINT\$2,"96 "'DATA AREA ''" 192 PRINT\$2,"180 DATA ";:Q\$=":DC=6:X=6:Y=1:CS=6:L=116 190 PRINT"PRINT"NUMBER OF RECORDS:"RL": WORKING ON..." 190 PRINT"RECORD 1,", 190 GOSUB 316:IF LOC(1) CLOF(1) THEN 276 191 GET 1:X=X+1:IF X>512 THEN X=6:X=Y+1:PRINT"...DONE":END 191 GET 1:X=X+1:IF X>512 THEN X=6:X=Y+1:PRINT"...DONE":END 192 PRINT\$2,O\$,MID\$(STR\$(ASC(A\$)),2);C\$="":CF=6:CS=CS+ASC(A\$) 193 DC=DC+1:IF DCC15 THEN RETURN 193 DC=DC+1:IF DCC15 THEN RETURN 194 PRINT\$2,CRR\$(13);:Q\$="":PRINT\$2,MID\$(STR\$(L),2)" DATA ";:L=L+1 0:RETURN 140 OPEN"R", 1, SF\$, 1:FIELD 1, 1 AS A\$:RL=LOP(1)/512:IF LOF(1)>RL*512 4626 848 2338 2691 1582 3284 7203 3016 2080 3102 3691 1280 2269 3728 4888 3645 1982 2735 4388 End

Micro Smart Inc. says what you want to hear. Service!


MEGADISK PLUS / MEGAPLEXER



MEGADISK PLUS

Drive a hard bargain from 10 to 40 megabytes of reliable high speed systems, the newest technology-hard plated media, automatic ECC error correcting, fan cooling, EMI/ RFI filter, gold connectors thoroughly burned in and tested just to mention a few standard features. Both fixed platter and removeable cartridge systems available starting at a low \$524.95

Megadisk™ Hard Disk Drive Systems



MEGAPLEXER-**NETWORK YOUR** MEGADISK WITH UP TO 10 TRS/80 COMPUTERS

Attach 2 to 10 Model III/IV/4P computers to one megadisk through our easy to use megaplexer-share files, data, programs, and make more efficient use of one megadisk with up to 10 computers. For a novice or expert. It will operate right out of the box.

Four port systems start at a low \$399.95 Plus Cables.

For the IBM/PC, Tandy 1000, TRS/80 Models I/III/4/4P, Compaq, Tava, PC Workalikes, Color Computer, Heath/Zenith, Max/80 Complete with Hardware, Cables, Software and Quikfit Installation

IBM and Compatibles all sizes after formatting

11 Meg Internal Removable Cartridge . . . Starting at \$449.95 22 Meg Internal Removable Cartridge . . . Starting at \$649.95 (For external add \$100)

11 to 46 Meg Internal Fixed Starting at \$299.95 60/90 Meg Internal Fixed Starting at \$Call 11 to 46 Hard Card Starting at \$299.95

TRS80- all drives are external with their own cabinet, power supply and cable.

 20 Meg Hard Drive
 \$679.95

 40 Meg Hard Drive
 \$995.95

TOLL FREE ordering 1-800-343-8841

number of records that it will process, and reports as it works on each record. It saves the new Basic program in ASCII format.

Hex It

If you prefer to have the Data Statements in hexadecimal (hex) format (Models 4 or 1000), you can make the following changes. In line 220, change A = VAL(A\$) to A = VAL ("Q\$" &H"Q\$" + A\$). In line 320, replace MID\$(STR\$(A),2) with B\$.

For the Model 4, insert line 315 B\$= HEX\$ (A): IF LEN(B\$) = 1 THEN B\$ = "0" + B\$. For the Tandy 1000, insert line 315 as above but replace (A) with (ASC(A)).

With the above changes, the data will be printed in hex, but the checksum at the end of the line will still be decimal.

The Rub

Datapoke can turn a 10-page assembly listing into two pages of Data statements (an 80-percent reduction). The disadvantage is that data listings do not show how a program operates as clearly as an assembly-code listing.■

David Goben is a programming consultant. Write to him at 67 Highland Road, Mansfield Center, CT 06250.

TIDBIT #42

Some decimal-to-fraction conversion routines are not applicable to the real world. They produce fractions that most people have no use for, such as 3/200. My routine, Jimsfrac, converts decimals to fractions that are used in the trades: 64ths, 32nds, 16ths, eighths, fourths, and halves.

In most cases, a decimal doesn't convert exactly to a fraction, so lines 220 and 240 round off a decimal to the next 64th. This produces a result that is accurate enough for most industrial and trade purposes.

To convert to fractions in 32nds.

you must change .015625 to .03125 and .984375 to .96875 in line 220. Change .015625 to .03125 in line 240. Finally, you must change 1000000 to 100000, 15625 to 3125, and 64 to 32 in line 280.

To convert to fractions in 16ths, you must change .015625 to .0625 and .984375 to .9375 in line 220. Also, you must change .015625 to .0625 in line 240. Finally, you must change 1000000 to 10000, 15625 to 625, and 64 to 16 in line 280.

> Jim C. Cahlik Parma, OH

> > End

Program Listing. Jimsfrac

```
10 ' JIMSFRAC
20 CLS
                                  BY JIM C. CAHLIK 81/21/87
                                                                                                                                       356
     GOSUB 50:PRINT WS:GOTO 38
                                                                                                                                     1761
    LINE INPUT"ENTER DECIMAL (XXX.XXXXXX) ";U$
A=VAL(U$);B=INT(A);D=A-B;C=(INT(D/.015625))*.015625
                                                                                                                                     2999
                                                                                                                                     3863
    IF D>.984375 THEN B=B+1:C=8:GOTO 86
IF B+C<A THEN C=C+.015625:GOTO 70
U$=STR$(B)+STR$(C):V=INSTR(U$,".")
                                                                                                                                     2202
                                                                                                                                     2075
98 IF V=8 THEN W$=$TR$(B):RETURN
188 C=INT(c*1808080):NU=C/15625:DE=64
118 IF NU>2 AND DE/2=INT(DE/2) AND NU/2=INT(NU/2) THEN DE=DE/2:N
U=INT(NU/2):IF NU>2 THEN 118
                                                                                                                                     2028
                                                                                                                                    5598
120 IF NU=2 THEN DE=DE/2:NU=NU/2
130 W$=STR$(B)+" "+STR$(NU)+"/"+STR$(DE)
                                                                                                                                     1969
2215
140 RETURN
                                                                                                                                       661
```

Circle 202 on Reader Service card.

SAVE YOUR DATA...AND YOUR MONEY WITH OUR **UNINTERRUPTABLE POWER SUPPLY**

When the power goes off your data can be lost and that costs you money. Money to pay for the time it takes to find your latest backup (you do have a backup somewhere, don't you?) and money to pay the repairman for that blown hard drive. The SPS-300 provides protection from power outages and most all types of surges and spikes.

Simply plug your computer and display/printer (up to 300 Watts total load) into the SPS-300's two outlets. When power interruptions occur the SPS-300 switches to its own internal batteries allowing uninterrupted use for up to 30 minutes with a 300 Watt load. The operator has enough time to choose between continuing to use the computer or going through an orderly shutdown thereby preserving the work performed prior to the loss of line power. Operation is completely automatic with both audible and visual power failure alarms.

The SPS-300 is compact, maintenance free and can be located in most any out of the way place. Just plug it in and forget it. This heavy-duty unit is ruggedly constructed to give you years of unattended service. Our one year warranty includes both parts and labor. Our low price lets you give your data (and wallet) the protection they have been needing. Call us and we will ship yours right away. Please add \$20 for shipping and handling in the continental US.

ORDER TOLL-FREE 800-527-0347 800-442-1310

AEROCOMP

USA

Texas

FAX: 214-337-4981 214-637-5400 Telex: 882761 Dallas, Texas 75376

Prices and specifications subject to change without notice.

1986 by Aerocomp. All rights reserved.

2544 West Commerce Street P.O. Box 223957 Dallas, Texas 75212

Clone enolD





ONE YEAR WARRANTY





Tandy 1000 Memory Card


another high quality product from Southwestern Digital

Why spend a bundle on a Tandy board? Our Board is only

\$135.

Features:

- . 512K of Memory
- DMA
- · Expansion Port
- · Gold Edge Cards
- · Easy Installation
- · 30 Day Satisfaction Guarantee Policy



The Southwestern Digital Memory Expansion Plus Card has all the features of the Radio Shack Board but the price; you save almost \$400. Features include 512K installed, burned in, and tested to give you a total of 640K, a DMA circut that is fully tested for hard drive operation, and an expansion port that will work with any of the Radio Shack Memory Plus Expansion Card options. High quality manufacturing, and features such as gold plated card edges make this the logical choice in upgrading your memory.

Multifunction Card for 1000, 1000A

Hard Cards for the 1000, 1000SX, 3000HL

20 Meg					,						,										\$479.
30 Meg																				,	\$629.
45 Meg																					\$799.

Tandy 1000 Add on Boards Serial, Clock, or Both

Tandy 1000, 1000SX, 1000EX

The Southwestern Digital new Add-On boards were developed for use with the Plus Card Port, (a piggy-back type, add on port established by Tandy to eliminate the need for an additional card slot). These cards are fully compatible with the Memory Expansion Plus Card from Southwestern Digital and the Memory Expansion Plus Board from Tandy.

RS232C PLUS Option Board

Mounts on a PLUS expansion board, and features selectivity between COM Port 1 and COM Port 2. The RS232C output connector is the standard Tandy female DB25, and is fully compatible with the Tandy output. **\$59.**

Clock/Calendar PLUS Option Board

Mounts on a Plus expansion board, and features selectivity between two ports so that you can run two clocks at one time. The Clock Calendar Board gives you perpetual time/date so that you don't have to re-input time and date into your application programs as part of your power up routine. \$59.

RS232C-Clock/Calendar PLUS Option Board

Features options of both of the above boards on just one board. \$129.


Tandy 1000SX Computer System

 with 640K, RS232C Serial Port, 20 Meg Hard Drive, (1) 360K Disk Drive,

 Clock/Calender
 \$1399.

 With a 30 Meg
 \$1549.





1-713-480-3296

Southwestern Digital

17333 El Camino Real Houston, Texas 77058

Circle 444 on Reader Service card.

Ordering Information

Call us or mail your order in. We accept Visa, Mastercard, and Certified Funds for quickest shipment. Personal checks are held for clearance. Add \$5, for ground shipment, or \$10 for UPS 2nd day air service. All products carry a 30 day satisfaction guarantee, and are warrantied for a full year.

Strip Your TRSDOS

Purge unprotected files from your system disks in one step.

Remove4 is an assembly-language, automatic-purge utility for the Model 4 that removes all visible, unprotected files from a disk in a specified drive. I wrote Remove4 to solve a simple, yet nagging problem.

The Model 4 TRSDOS disk has little room for user files. You must either write your files to a data disk in drive 1 or strip the TRSDOS disk of unnecessary utilities and SYS files with the Remove or Purge commands.

If you write your files to drive zero, you'll end up with many different TRSDOS configurations. You should immediately make and label a copy of each new configuration, but I often start using the disk for my application before making a backup. (Sound familiar?) Even with the extra space, the disk eventually becomes filled.

Before I wrote Remove4, I had to either back up the original TRSDOS master and configure it the same as my work disk, or back up my work disk and then remove or purge the user files to get a fresh disk. Either way, it was extra work.

Remove4

Once you assemble and execute the utility (see the Program Listing), a screen prompt asks you to type the drive number (zero-7) containing the disk with the unwanted files. Typing Q at this prompt returns you to TRSDOS.

The program checks to see if the chosen drive is in the drive-code table. If it isn't, you'll see a message telling you so, and Remove4 returns you to the drive-number prompt.

If the program recognizes the drive, it then checks to see if the specified drive is ready. If not, you'll get another message, and Remove4 returns to the drive-number prompt.

If the drive is ready, the utility displays the directory of the chosen drive and asks you to verify that you really want to re-

System Requirements

Model 4
TRSDOS 6.x
Editor/assembler
Available on The Disk Series

move all the files. Remove4 lists all visible files, but it will not delete visible protected files. Responding with N or Q returns you to the drive-number prompt.

Typing Y automatically removes the unprotected files one by one. The bottom line of the screen (line 23) displays the file name currently being removed. Don't be alarmed if Remove4 seems to be removing a protected file; once the purge is complete, a directory of the drive will show that all protected files remain.

The program tells you when it has removed all the visible, unprotected files. Pressing any key at this point returns the utility to the drive-number prompt. Here you can either repeat the process on another disk by inserting the disk and typing the appropriate drive number, or type Q to return to DOS.

Remove4 removes files on 5¼- or 8-inch, single- or double-sided DOS and data disks alike. It can handle up to 254 files on any one disk.(This is the maximum number of files that TRSDOS allows.)

Remove4 should work on a hard disk, as long as the number of files on the specified drive does not exceed 254.

To execute, the system disk must have the following TRSDOS files: SYS0/SYS, SYS1/SYS, SYS2/SYS, SYS3/SYS, SYS10/SYS, and SYS12/SYS. This information can be on a disk in drive zero or residing in memory.

Final Notes

I used the Model III EDTASM program patched to work on a Model 4 to create Remove4. You can type it in using any of the currently available Model 4 editor/assemblers.

I've liberally commented the source code, so anyone with some knowledge of assembly or who has the Model 4 technical reference manual should find it easy to follow the flow of the code. I welcome any comments regarding this utility.

Write to Lance Wolstrup at 20311 Sherman Way #221, Canoga Park, CA 91306.

Listing continued

```
Program Listing. Remove4.
                   ..........
           REMOV4/SRC by Lance Wolstrup
20311 Sherman Way #221, Canoga Park, CA
                                                     91306
99139
      00150
00160 ;**
                                        ; ASSEMBLE AT 2600H
00180 START
              CALL
                       CLS
                                        : ERASE SCREEN
                       NOCURS
                                        TURN OFF CURSOR
               CALL
00200
               CALL
                       SCREEN
                                        DISPLAY LINES 0-4 ON SCREEN SCROLL PROTECT TOP 5 LINES
                       PROT
00210
              CALL
00220
              JP
                                         JUMP OVER SUBROUTINES
        ***** SUBROUTINES ***


** EXIT TO DOS **

JIT C***
00230
00240
00250 QUIT
                                        : REMOVE SCROLL PROTECT
00260
               CALL
                       CLS
                       HL, Ø
A, 22
                                        ;HL=0 MEANS NORMAL RETURN TO DOS
00270
              LD
00280
               LD
99299
               RST
                       28H
00300
           ERASE SCREEN
                       A,1CH
00310 CLS
              LD
                                        : PRINT CHRS (28) - HOME CURSOR
00320
              CALL
                       DSP
                       A, 1FH
                                        ; PRINT CHR$ (31) - ERASE TO END OF DISPLAY
00330
              CALL
00340
                       DSP
      ; ** POSITION CURSOR **
00360
                           AND HORIZONTAL (L) HAS BEEN LOADED BY CALLER
        NOTE VERTICAL (H)
                       A,15
B,3
00380
00390
      LOCATE
              LD
                                        ; MOVE CURSOR TO HL - EVEN IF INVISIBLE
00400
               RST
                       28H
                                        : @VDCTL
       ** SCROLL PROTECT TOP 5 LINES **
00420
      PROT
                       B,7
C,5
28H
                                        SCROLL PROTECT FUNCTION
00440
              LD
00450
                                        PROTECT 4 LINES
00460
               RST
                                        : @VDCTL
00470
              RET
      ; ** REMOVE SCROLL PROTECT **
```

00490 UNPROT

LD

The fastest route for maximizing your computer productivity ...



... subscribe to PC RESOURCE

PC RESOURCE is the magazine for computer-savvy people eager to discover new and ingenious no-cost or low-cost ways to get more out of your MS-DOS computer system.

And now, during our special limited time charter offer, you can save over 40% off the cover price!

Each month you get valuable insights and information on using your computer to meet business, financial, and personal needs most effectively.

Buyers' guides, features, and in-depth reviews help you locate the best buys in hardware, inexpensive compatibles, and innovative peripherals. We vigorously test both commercial and public domain software... then make recommendations



MONEY BACK GUARANTEE:

If you are not completely satisfied with PC

RESOURCE, you may

of your first issue.

cancel your subscription

and receive a full refund on

all unmailed issues. Please

allow 6-8 weeks for delivery

based on our findings. Our emphasis	is is
on saving money and making sure yo	u
get the best value for your dollar.	

PC RESOURCE lets you sharpen and add to your computer skills—with tutorials on programming, articles exploring the inner workings of MS-DOS, hands-on advice from the experts, and tips from other readers who have "been there before"

In addition, you can take advantage of "Compatibles Hotline," the computer bulletin board system exclusively for our readers. Post your questions and get answers from our technical staff and other subscribers.

And for the "do-it-yourselfer," PC RESOURCE offers ways to modify, diagnose, or repair your computer. Stepby-step instructions enable you to fix damaged disks, rescue lost data, and keep your disk drives working at peak efficiency! (This section alone is worth the subscription price!)

PC RESOURCE is timely, accurate, and practical — with information you can use on a daily basis. And it is written by the editorial experts of CW Communications, the world's largest publisher of computer magazines.

Make sure you don't miss a single issue of this important resource! Order your copy of PC RESOURCE today! For immediate service call toll-free

1-800-258-5473.

☐ YES!

I want to maximize my computer productivity ... and save over 40% off the cover price. Send me a year's subscription (12 issues) of PC RESOURCE at the charter rate of \$19.97.

☐ Payment enclosed ☐ Bill me Make checks payable to PC RESOURCE

City ______State ____ Zip ____

Canada and Mexico, \$22.97. Foreign Surface, \$39.97. Foreign Airmail, \$74.97. U.S. funds drawn on a U.S. bank, Please allow 6 to 8 weeks for delivery.

elivery. 375EM

Mail to


Name

Address

PC RESOURCE, CW Communications/Peterborough, P.O. Box 950, Farmingdale, N.Y. 11737-0950

Listing continued

```
01230
                                                                                                                   CALL
                                                                                                                           CHROUT
00500
              LD
                       B. 7
                                         SCROLL PROTECT PUNCTION
                                                                                                    01240
                                                                                                                   LD
                                                                                                                           H.2
                                                                                                                                             : POSITION CURSOR AT LINE 2
00510
              L.D
                       C, 0
                                         : PROTECT Ø LINES
                                                                                                    01250
                                                                                                                   LD
                                                                                                                           L. 9
                                                                                                                                             : COLUMN 9
00520
              RST
                       28H
                                         : @VDCTL
                                                                                                                   CALL
00530
                                                                                                    91269
                                                                                                                           LOCATE
              RET
                                                                                                    01270
                                                                                                                   LD
                                                                                                                           HL, MSG3
                                                                                                                                             DISPLAY DESCRIPTION OF PROGRAM
00540 : ** DISPLAY MESSAGES **
                                                                                                                   CALL
                                                                                                                           CHROUT
                                                                                                    01280
00550 CHROUT
              I.D
                       A, (HL)
                                         ; PUT CHARACTER FROM HL INTO A
                                                                                                    01290
                                                                                                                   LD
                                                                                                                           H, 3
                                                                                                                                             : POSITION CURSOR AT LINE 3
00560
              OR
                                         :IS IT TERMINATING BYTE - 0
                                                                                                                                            : COLUMN Ø
                                         ; IF 0 - TERMINATE MESSAGE
                                                                                                    91399
                                                                                                                   TD
                                                                                                                           L.0
00570
              RET
                                                                                                                           LOCATE
                                                                                                    01310
                                                                                                                   CALL
00580
              LD
                       C, A
                                         ; PUT CHARACTER INTO C
                                                                                                    01320
                                                                                                                   LD
                                                                                                                           B. 80
00590
              LD
                       A, 2
                                                                                                    01330 PRT131
                                                                                                                  LD
                                                                                                                           A. 131
                                                                                                                                             ; DRAW HORIZONTAL LINE - STRING$ (80,131)
88688
              RST
                       28H
                                         ; @DSP
                                                                                                    01340
                                                                                                                   CALL
                                                                                                                           DSP
                                         POINT TO NEXT CHARACTER IN MESSAGE
00610
              INC
                       HT.
                                                                                                    01350
                                                                                                                           PRT131
                                                                                                                   DJNZ
00620
               JR
                       CHROUT
                                         GO BACK AND DO IT AGAIN
                                                                                                    01360
                                                                                                                   RET
00630 : ** WAIT FOR KEYPRESS **
                                                                                                    01370 :**** PROGRAM
                                                                                                                         BEGINS HERE ****
00640 INKEY
              LD
                       A, 1
                                                                                                    01380 BEGIN
                                                                                                                  LD
                                                                                                                            HL, DIRBUF
                                                                                                                                             POINT HL TO BUFFER CONTAINING DIR
00650
               RST
                       28H
                                         : OKEY
                                                                                                    91309
                                                                                                                   LD
                                                                                                                           B. 22
00660
              RET
                                                                                                                            A, 20H
                                                                                                    01400
                                                                                                                   LD
00670 : ** DISPLAY
                    CHARACTER **
                                                                                                    01410 CLEAR
                                                                                                                   LD
                                                                                                                                             : PUT SPACES IN 1st 22 BYTES OF DIRBUF
                                                                                                                            (HL),A
00680 DSP
                                        ; PUT CHARACTER INTO C
              LD
                       C, A
                                                                                                    01420
                                                                                                                   INC
                                                                                                                            HI.
00690
              T.D
                       A, 2
                                                                                                    01430
                                                                                                                   DJNZ
                                                                                                                           CLEAR
                                        : @DSP
00700
              RST
                       28H
                                                                                                    91449
                                                                                                                   T.D
                                                                                                                           H,5
                                                                                                                                             : POSITION CURSOR ON LINE 5
00710
              LD
                       A, C
                                        ; PUT CHARACTER BACK INTO A
                                                                                                                   LD
                                                                                                                                             : COLUMN Ø
                                                                                                    01450
                                                                                                                           L,0
00720
              RET
                                                                                                    91469
                                                                                                                   PUSH
                                                                                                                                             :SAVE CURSOR LOCATION
                                                                                                                           HI.
99739
      : ** TURN OFF
                    CURSOR **
                                                                                                    01470
                                                                                                                   CALL
                                                                                                                           LOCATE
00740 NOCURS LD
                       A, 15
                                        :PRINT CHR$(15) - CURSOR OFF
                                                                                                    01480
                                                                                                                   LD
                                                                                                                            A, 1FH
                                                                                                                                             :PRINT CHR$(31) - ERASE TO END OF DISPLAY
00750
              CALL
                       DSP
                                                                                                    01490
                                                                                                                   CALL
                                                                                                                           DSP
00760
              RET
                                                                                                    01500
                                                                                                                   POP
                                                                                                                            HL
                                                                                                                                             ; RESTORE CURSOR LOCATION
00770 : ** TURN ON CURSOR **
                                                                                                    01510
                                                                                                                   CALL
                                                                                                                           LOCATE
00780 CURSOR LD
                       A, 14
                                        ; PRINT CHR$(14) - CURSOR OFF
                                                                                                    01520
                                                                                                                   LD
                                                                                                                            HL, WCHDRV
                                                                                                                                             : PRINT MESSAGE ON SCREEN
00790
              CALL
                                                                                                                   CALL
                                                                                                                            CHROUT
                                                                                                    @1530
99899
              RET
                                                                                                    01540 INKEY1
                                                                                                                   CALL
                                                                                                                            CURSOR
                                                                                                                                             :TURN ON CURSOR
00810 ; ** DISPLAY
                    "PRESS ANY KEY TO CONTINUE" AND WAIT FOR KEYPRESS **
                                                                                                    01550
                                                                                                                   CALL
                                                                                                                            INKEY
                                                                                                                                             :WAIT FOR KEYPRESS
00820 ANYSUB
              L.D
                       H, 23
                                        : POSITION CURSOR AT LINE 23
                                                                                                    01560
                                                                                                                   CP
                                                                                                                            51H
00830
              T.D
                       L. 27
                                        : COLUMN 27
                                                                                                    01570
                                                                                                                   JP
                                                                                                                            Z,QUIT
                                                                                                                                             ; IF Q IS PRESSED - BACK TO DOS
00840
              CALL
                       LOCATE
                                                                                                    91589
                                                                                                                   CP
                                                                                                                            71H
                       HL, ANYKEY
00850
              LD
                                        ; DISPLAY ANYKEY MESSAGE
                                                                                                    01590
                                                                                                                   JP
                                                                                                                            Z.QUIT
                                                                                                                                             ; IF q IS PRESSED - BACK TO DOS
00860
              CALL
                       CHROUT
                                                                                                                   CP
                                                                                                                            30H
                                                                                                    01600
99879
              CALL
                       CURSOR
                                         :TURN ON CURSOR
                                                                                                                            C, INKEY1
                                                                                                                   JR
                                                                                                                                             JUMP IF SMALLER THAN 0
                                                                                                    01610
00880
              CALL
                       INKEY
                                        WAIT FOR KEYPRESS
                                                                                                    01620
                                                                                                                   CP
                                                                                                                            38H
00890
              CALL
                                        TURN OFF CURSOR
                       NOCHES
                                                                                                                            NC, INKEY1
                                                                                                                                             JUMP IF EQUAL OR LARGER THAN 8
                                                                                                    01630
                                                                                                                   JR
00900
                                        ; POSITION CURSOUR AT LINE 5
              LD
                       H,5
                                                                                                                   PUSH
                                                                                                                                             ; SAVE DRIVE NUMBER IN A
                                                                                                    01640
                                                                                                                           AF
00910
              LD
                       L. 29
                                         : COLUMN 29
                                                                                                                            NOCURS
                                                                                                                                             TURN OFF CURSOR
                                                                                                    01650
                                                                                                                   CALL
00920
              CALL
                       LOCATE
                                                                                                    01660
                                                                                                                   POP
                                                                                                                            AF
                                                                                                                                             RESTORE DRIVE NUMBER
00930
              LD
                       A, 1FH
                                        ; PRINT CHR$(31) - ERASE TO END OF DISPLAY
                                                                                                    91679
                                                                                                                   CALL
                                                                                                                           DSP
                                                                                                                                             DISPLAY IT
00940
              CALL
                       DSP
                                                                                                    01680
                                                                                                                   SUB
                                                                                                                            30H
                                                                                                                                             GET TRUE DRIVE NUMBER
00950
               RET
                                                                                                    01690
                                                                                                                   LD
                                                                                                                            (SRCBUF), A
                                                                                                                                             :STORE IT IN SRCBUF
00960 : ** SELECTED DRIVE IS NOT CONFIGURED IN DRIVE CODE TABLE **
                                                                                                    01700
                                                                                                                   LD
                                                                                                                            C.A
00970 NODRY
              LD
                       H,20
                                        : POSITION CURSOR AT LINE 20
                                                                                                    01710
                                                                                                                   LD
                                                                                                                            A, 40
00980
              LD
                       L. 25
                                         : COLUMN 25
                                                                                                                                             : @DCSTAT - IS DRIVE DEFINED IN DCT
                                                                                                    01720
                                                                                                                   RST
                                                                                                                            28H
00990
              CALL
                       LOCATE
                                                                                                                                             : ERROR - SO JUMP TO NODRY
                                                                                                    01730
                                                                                                                   JP
                                                                                                                            NZ, NODRV
01000
              LD
                       HL.NDMSG1
                                         ; DISPLAY NDMSG1
                                                                                                                            A, (SRCBUF)
                                                                                                                                             PUT DRIVE NUMBER INTO A
                                                                                                    91749
                                                                                                                   LD
01010
              CALL
                       CHROUT
                                                                                                    01750
                                                                                                                   LD
                                                                                                                            C,A
                                                                                                                                             PUT IT INTO C
01020
              CALL
                       ANYSUB
                                         DISPLAY ANYKEY MESSAGE
                                                                                                                           A, 33
                                                                                                                   LD
01030
              JP
                       INKEYL
                                        :GO BACK AND ASK FOR DRIVE NUMBER
                                                                                                    01760
                                                                                                    01770
                                                                                                                   RST
                                                                                                                            28H
                                                                                                                                             : @CHKDRV - IS A FORMATTED DISKETTE
01040 ; ** SELECTED DRIVE EITHER CONTAINS NO DISK OR CANNOT READ DISK **
                                                                                                                                             IN SELECTED DRIVE
01050 NODSK
                                         : POSITION CURSOR AT LINE 20
                                                                                                    01780
              LD
                       H, 20
                       L,27
01060
              LD
                                         : COLUMN 27
                                                                                                    01790
                                                                                                                   JP
                                                                                                                            NZ, NODSK
                                                                                                                                             : ERROR - JUMP TO NODSK
01070
              CALL
                       LOCATE
                                                                                                                           A. (SRCBUF)
                                                                                                                                             : PUT DRIVE NUMBER INTO A
                                                                                                    01800
                                                                                                                   LD
                                                                                                    01810
                                                                                                                   LD
01080
               LD
                       HL.NDMSG2
                                         :DISPLAY NDMSG2
                                                                                                                            B.A
                                                                                                                                             · PHT IT INTO B
              CALL
                                                                                                                   LD
01090
                       CHROUT
                                                                                                    01820
                                                                                                                            C. 0
                                                                                                                                             :GET DIRECTORY AF ALL VISIBLE FILES
                                         DISPLAY ANYKEY MESSAGE
                                                                                                    01830
                                                                                                                   LD
01100
              CALL
                       ANYSUB
                                                                                                                            HL, DIRBUF
                                                                                                                                             POINT TO BUFFER
                                         :GO BACK AND ASK FOR DRIVE NUMBER
                                                                                                                   LD
                       INKEYL
                                                                                                    01840
01110
               JP
                                                                                                                            A, 35
01120
      ; ** DISPLAY COPYRIGHT, PROGRAM NAME AND DESCRIPTION ON THE **
                                                                                                    01850
                                                                                                                   RST
                                                                                                                            28H
                                                                                                                                             ; @RAMDIR - GET DIRECTORY RECORDS
                                                                                                                            HL, DIRBUF
01130; ** TOP 3 LINES (0-2) - THEN DRAW VERTICAL LINE ON 4th LINE (3) **
                                                                                                    01860
                                                                                                                   LD
                                                                                                                                             ; POINT HL TO 1st CHR IN DIRBUF
01140 SCREEN LD
                                                                                                                   LD
                                         : POSITION CURSOR AT LINE Ø
                                                                                                    01870
                                                                                                                            A, (HL)
                                                                                                                                             : PUT CHR INTO A
                       H. 0
                                                                                                    01880
                                                                                                                   CP
                                                                                                                            20H
01150
               LD
                       L, 25
                                         : COLUMN 25
                                                                                                                                             : IS IT A SPACE
                                                                                                    01890
                                                                                                                   JP
                                                                                                                           Z, EMPTY
                                                                                                                                             ; NO RECORDS - JUMP TO EMPTY
01160
               CALL
                       LOCATE
01170
                       HL.MSG1
                                         ; DISPLAY COPYRIGHT MESSAGE
                                                                                                    01900
                                                                                                                   LD
                                                                                                                           H,5
                                                                                                                                             : POSITION CURSOR AT LINE 5
                                                                                                                   LD
              CALL.
                       CHROUT
                                                                                                    01910
                                                                                                                           L, Ø
01180
                                                                                                                                             : COLUMN Ø
                                                                                                                   PUSH
01190
                       H, 1
                                         ; POSITION CURSOR AT LINE 1
                                                                                                    01920
                                                                                                                           HL
                                                                                                                                             ; SAVE CURSOR LOCATION
               I.D
01200
                       L, 29
                                         : COLUMN 29
                                                                                                    01930
                                                                                                                   CALL
                                                                                                                            LOCATE
              LD
                                                                                                    01940
                                                                                                                   LD
                                                                                                                            A. 1FH
                       LOCATE
                                                                                                                                             ; PRINT CHR$ (31) - ERASE TO END OF DISPLAY
01210
               CALL
                                                                                                    01950
                                                                                                                   CALL
01220
                       HL, MSG2
                                         DISPLAY NAME OF PROGRAM
                                                                                                                           DSP
```







Tandy® computers are designed, built, supported and serviced by Radio Shack.
Our total commitment assures a high degree of

Tandy 3000 HD product quality and, just as important, customer satisfaction long after the sale.

Quality-built in the USA. Our MS-DOS® personal computer line is made in America in our own

manufacturing plants. We control quality, from initial assembly to completed and tested product.

Nationwide Support. Over 1200 Radio Shack Computer Centers are ready to help you choose the

latest in computer technology, backed by quality support.

Training and specialized software instruction is available at your

Tandy 3000 HL

teg

TANDY COMPUTERS: In Business . . . for Business™

place of business or ours, in 60 major market areas.

We've got what it takes. Like commercial leasing plans. And service performed

Tandy 1000 SX

by technicians who work for the same company that manufactured and sold you your computer.

You expect quality . . . and you get it from Radio Shack.

Radio Shaek


COMPUTER CENTERS

A DIVISION OF TANDY CORPORATION

Circle 75 on Reader Service card.

Listing continued

isting continue	a		T T					
1960	POP	HL	; RESTORE CURSOR LOCATION	02700		POP	HL	RESTORE CURSOR POSITION
1970	CALL	LOCATE		02710		CALL	LOCATE	
1980	LD	A, (SRCBUF)	;GET DRIVE NUMBER	02720		POP	HL	RESTORE BUFFER LOCATION
1990	LD	C, A	; PUT IT IN C	02730		JR	LOOPØØ	GO BACK AND GET NEXT FILE
2000	LD	В, Ø	; SELECT VISIBLE NON-SYSTEM FILES	02740			FER **	
2010	LD	A, 34		02750	EOF	LD	н,22	; POSITION CURSOR AT LINE 22
2020	RST	28H	; @DODIR - DISPLAY DIRECTORY	02760		LD	L,0	; COLUMN Ø
2030	LD	н,23	POSITION CURSOR AT LINE 23	02770		CALL	LOCATE	
2040	LD	L,27	; COLUMN 27	02780		LD .	A, 1FH	;PRINT CHR\$(31) - ERASE TO END OF DISPLA
2050	CALL	LOCATE	**************************************	02790		CALL	DSP	
2060	LD	HL, REMMSG	;DISPLAY REMMSG	02800		LD	н,22	; POSITION CURSOR AT LINE 22
2070	CALL	CHROUT		02810		LD	L,19	; COLUMN 19
2080	CALL	CURSOR	; TURN ON CURSOR	02820		CALL	LOCATE	Control of the Contro
2090 INKEY2	CALL	INKEY	; WAIT FOR KEYPRESS	02830		LD	HL, DONE	DISPLAY DONE MESSAGE
2100	CP	51H	TR A THER DO BROTH	02840		CALL	CHROUT	
110	JP	Z, BEGIN	; IF Q - JUMP TO BEGIN	02850		CALL	ANYSUB	; DISPLAY ANYKEY MESSAGE
2120	CP	71H	TR - THUR MO PROTEI	02860		JP	BEGIN	JUMP TO BEGIN
2130	JP	Z, BEGIN	; IF q - JUMP TO BEGIN					FILES ON SELECTED DISK **
140	CP	4EH	TR N THEN TO DECIN	02880	EMPTY	LD	н,22	; POSITION CURSOR AT LINE 22
150	JP	Z, BEGIN	; IF N - JUMP TO BEGIN	02890		LD	L,0	; COLUMN Ø
160	CP	6EH	TR - THEN TO DECIN	02900		CALL	LOCATE	
170	JP	Z,BEGIN	; IF n - JUMP TO BEGIN	02910		LD	A,1FH	;PRINT CHR\$(31)
180	CP	59H	TR W THEN TO CHENTE	02920		CALL	DSP	
190	JR	Z, CNTNUE	; IF Y - JUMP TO CNTNUE	02930		LD	H,22	; POSITION CURSOR AT LINE 22
200	CP	79H	TR W - TUMB TO CHENTE	02940		LD	L,28	; COLUMN 28
210	JR	Z, CNTNUE	; IF Y - JUMP TO CNTNUE	02950		CALL	LOCATE	
220	JR	INKEY2	JUMP BACK TO INKEY2	02960		LD	HL, NOFIL	;DISPLAY NOFIL MESSAGE
230 CNTNUE		NOCURS	TURN OFF CURSOR	02970		CALL	CHROUT	
2240	LD	н, 23	; POSITION CURSOR AT LINE 23	02980		CALL	ANYSUB	; DISPLAY ANYKEY MESSAGE
250	LD	L, Ø	COLUMN Ø	02990		JP	BEGIN	; JUMP BACK TO BEGIN
260	PUSH	HL	; SAVE CURSOR POSITION		; ****		ESSAGES ****	
270	CALL	LOCATE	PRINT CURC/201 PRINCE NO PUR OR LINE	03010	MSG1	DEFB	21	
280	LD	A, 1EH	; PRINT CHR\$(30) - ERASE TO END OF LINE	03020		DEFB	143	
290	CALL	DSP	PROMODE CURCOR ROCKMION	03030		DEFB	244	
300	POP	HL	; RESTORE CURSOR POSITION	03040		DEFB	245	
310	CALL	LOCATE	DYCOVAN DEMOTE MECCACE	03050		DEFB	246	
2320	LD	HL, REMFIL CHROUT	;DISPLAY REMFIL MESSAGE	03060		DEFB	32 32	
2330	CALL		- DOTAGE UT MO DYDDIID	03070		DEFB		
340	LD	HL, DIRBUF	; POINT HL TO DIRBUF	03080 03090		DEFB	239 32	
350 LOOP00	LD	(BUFLOC), HL	; PUT ADDRESS OF DIRBUF INTO BUFLOC					Coffeend
2360	LD	B, 14	; LENGTH OF FILENAME/EXT:D	03100 03110		DEFM	'1986 Wolstrup	Software.
370 LOOP01	LD	A, (HL)	GET CHARACTER INTO A	03110		DEFB	21	
380	CP	2BH	; IS IT + (+ MARKS BUFFER END)	03130	MCCO	DEFM	**** R E M O V	
2390	JR	Z, EOF	; IF CHARACTER IS + JUMP TO EOF	03140	MSGZ	DEFB	a REMU	V E 4
400	INC	DSP	DISPLAY IT	03150	MCC2	DEFM	IDenaus all mis	sible non-nucleoted 1
410		HL	; NEXT CHARACTER ; REPEAT UNTIL A CONTAINS +		MSGS			sible, non-protected '
2420 2430	DJNZ LD	LOOPØ1 IX,BUFLOC	POINT IX TO BUFLOC	03160 03170		DEFM	g riles on selec	cted diskette.'
440			GET LSB OF CURRENT BUFFER LOCATION		WCHDRV	DEFM		on which drive: '
450	LD	L, (IX+0) H, (IX+1)	GET MSB OF CURRENT BUFFER LOCATION	03190	WCHDKY	DEFB	Remove IIIes C	on which drive:
460		DE DED	POINT DE TO FILE CONTROL BLOCK		NDMSG1	DEFM	Icological drive	e is not available'
476	LD	DE,FCB A,78	POINT DE 10 FILE CONTROL BLOCK	03210	NDMSGI	DEFB	a selected drive	e is not available.
480	RST	28H	; @FSPEC - MOVES FILE FROM BUFFER TO FCB		NDMSG2	DEFM	'Selected drive	e is not ready'
490	LD	DE, 17	, er of be Moved 1188 1 Non Bollink 10 1 CB	03230		DEFB	0	e is not ready
500	ADD	HL, DE	POINT HL TO LRL BYTE		REMMSG	DEFM	'Remove above i	files (Y/N)
510	LD	B, (HL)	PUT IT INTO B	03250		DEFB	0	(1,1)
2520	LD	HL, IOBUF	POINT HL TO IO BUFFER		REMFIL	DEFM	'Removing>	
2530	LD	DE, FCB	POINT DE TO FILE CONTROL BUFFER	03270		DEFB	0	
2540	LD	A,59	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	03280	DONE	DEFM	'All visible, r	non-protected files removed'
2550	RST	28H	; @OPEN - OPENS FILE IN FCB	03290		DEFB	0	non producted randed
2560	LD	A,57	7.44-00	03300	NOFIL	DEFM	'No visible fil	les on disk'
2570	LD	DE, FCB	POINT DE TO FILE CONTOL BLOCK	03310		DEFB	0	
2580	RST	28H	: @REMOVE - REMOVES FILE		ANYKEY	DEFM	'Press any key	to continue '
2590	LD	L, (IX+0)	GET LSB OF CURRENT BUFFER LOCATION	03330		DEFB	0	
2600	LD	H, (IX+1)	GET MSB OF CURRENT BUFFER LOCATION	03340	, ****		****	
2610	LD	DE, 22	1000 1100 00 00111111111111111111111111		SRCBUF		1	; HOLD SELECTED DRIVE NUMBER
2620	ADD	HL, DE	POINT HL TO NEXT FILESPEC		DIRBUF		5589	HOLDS DIR INFO FROM @RAMDIR - ENOUGH
2630	PUSH	HL HL	SAVE BUFFER LOCATION	03370				FOR 254 FILES + 1 BYTE FOR BUFEND
	LD	H, 23	POSITION CURSOR AT LINE 23		BUFLOC	DEFS	2	HOLDS ADDRESS OF CURRENT PLACE IN
2640	LD	L,14	COLUMN 14	03390	DOI DOC	Dut	-	DIRBUF
	TIT.		SAVE CURSOR LOCATION	03400	FCB	DEFS	32	FILE CONTROL BLOCK
2650	DIJCH							
265Ø 266Ø	PUSH	HL	SAVE CORSON BOCKITON					
2640 2650 2660 2670 2680	CALL LD	LOCATE A, 1EH	;PRINT CHR\$(30) - ERASE TO END OF LINE	03410 03420		DEFS END	256 START	; I/O BUFFER - MANDATORY WITH @OPEN SVC



Circle 470 on Reader Service card.

Here's how we did it.

We packaged seven 32K RAM banks (224K) on a neat little module that snaps into the rear expansion port of your Model 100. Now you can have as much RAM memory in one Model 100 as eight 32K Model 100s.

Versatile Memory

Each of our additional 32K RAM banks has it's own command of the software that comes standard in your Model 100. All of the memory banks can be easily and directly accessed from any of the other banks. Transfer your files from bank to bank simply by using the function keys. We'll even display on the menu screen how many bytes any file is when you move the menu cursor over the file name.

You can really use more memory!

Most of us have run out of RAM memory at one time or

another in our Model 100. Imagine how nice it would be to have so much more memory in just one Model 100. Salesmen, journalists, scientists, any Model 100 user can maintain databases in some banks while dedicating other banks to sales letters, spreadsheets or other programs. For all of you the benefit is obvious-you carry more data with you in one small reliable package. (Memory entered in all of the additional RAM banks are backed up by a six year lithium power cell.)



Installation's a snap!

The RAM module simply snaps into the rear expansion compartment of your Model 100 and you're ready to go. There is no programming required. (The PG Design RAM module expands the RAM memory of any Model 100.)

Order Today

PG Design manufactures many fine memory expansion products for Tandy portable computers. All are guaranteed to work as promised or your money back. All are built to last.



Order Today

64K modules-\$300

128K modules-\$425

224K modules-\$575

(M100) 8K modules-\$24.95 ea./3 for \$69

*available for NEC 8201A

(M102) 8K modules-\$10.95

(M200) 24K modules-\$75 ea./2 or more, \$70

We accept Visa, Master Card, personal checks and money orders. We ship within five working days of receiving your order. *Tandy is a trademark of Tandy Corp.

Dealers inquire



Call 313/727-2744

Deskmate Printer Control

Use substitute characters to put your printer through its paces.

Deskmate for the Tandy 1000 does not allow you to place printer control codes within text. You can, however, control your printer within the text by using substitution characters, a procedure involving three steps:

- updating the configuration to include the printer driver;
- creating a table of substitution codes; and
 activating the table and inserting the codes into text.

Update the configuration by adding the following statement to Config.SYS:

DEVICE = LPDRVR.SYS

You can do this with Edlin. The easiest way to create Config.SYS is to copy statements to a file with that name from the console. At the DOS prompt type:

COPY CON CONFIG.SYS DEVICE = ANSI.SYS DEVICE = LPDRVR.SYS

Entering either control-Z or F6 terminates the Copy command and returns you to DOS. Refer to Appendix C of Tandy's MS-DOS Reference Manual (p. 309) for a further explanation of Config.SYS.

Creating the Substitution Characters

The second part of the procedure is more complex, since it uses the escape sequence that Appendix C describes. Before getting into this, identify a set of characters that you do not usually use in text files, such as the open brace ({}), close brace ({}), backslash (\), vertical bar (|), the difference sign (~) and ASCII 168 (¿). Then list the printer modes you want with their decimal and hexadecimal (hex) codes. You can find the codes in your printer manual. (For the DMP 120, they are on p. 35.)

The Table shows control-key conversions. You can find them in the scan-code list in Appendix B of the MS-DOS Refer-

System Requirements

Tandy 1000 Deskmate Printer ence Manual (p. 297). To determine the appropriate conversion, find the hex representation in the column labeled CTRL. The corresponding key is under the column titled Keyboard Legend. You will see the purpose of these codes as you create the table file.

Notice that 01B appears in the CTRL column as both the escape key and the symbol '[(more on this later).

Construct the control-key conversion table using characters you don't usually use in text files.

The table follows the format of the escape sequence:

ESC W n code string

in which "n" is the number of characters in the printer code, "code" is the decimal representation of the substitution character, and "string" is the appropriate printer code. For example, in:

ESC W 01 123 15

the printer code is one decimal character, and in:

ESC W 02 092 27 14

it is two decimal characters. The decimal representations of { and \ are 123 and 092, respectively.

File CHR120.DAT contains the table.

You can construct it using Basic or Edlin with the non-textual control characters you determined earlier. All alphabetic characters must be uppercase, so type:

EDLIN CHR120.DAT

at the DOS prompt. Edlin returns:

New File

where "*" is the command prompt. Enter "I" for Insert, and Edlin returns the line number 1.*. Enter the following after the line number:

control-V [W control-A { control-O

The line appears as typed:

1. * * V[W^A { *O

Continue with the remaining lines as follows:

2.*^V[W^A}^N 3.*^V[W^B\^V[^N 4.*^V[W^B]^V[^O 5.*^V[W^B ~^V[^T 6.*^V[W^B&^V[^S 7.*^C

Entering control-C terminates the insert command. The command prompt, followed by L, lists the following six lines:

> 1. ^[W^A{^O 2. ^[W^A]^N 3. ^[W^B\^[^N 4. ^[W^B]^[^O 5. ^[W^B ~^[^T 6.*^[W^B¿^[^S

The command prompt (*) followed by E exits Edlin.

Substitute character	Printer mode	Decimal	Hex	Control-key conversion
-	start underline	15	OF	40
1	end underline	14	OE	^N
1	start elongation	27 14	1B OE	escape-^N
1	end elongation	27 15	1B OF	escape-10
~	start condensed	27 20	1B 14	escape-^T
. 3	return to standard	27 19	1B 13	escape- ⁴ S

An Explanation

Edlin uses the escape key to void current input. When it does so, all entries disappear. Its equivalent, '[, serves the same purpose. Edlin lets you enter these special codes if you enter control-V followed by [to create an escape. This is why the V disappears when the lines list.

The 'A and 'B commands designate the length of the string according to the format of the escape sequence. Hex values 001 and 002 (under the column heading CTRL of the scan-code table) represent keyboard entries 'A and 'B, respectively.

If you try to display this file using the DOS Type command, you will see a set of completely different characters, including arrows, smiling faces, music notes, and sunshines. These are the display-character equivalents of the ASCII code. The decimal equivalent of escape is 027, which displays as a left arrow.

The last thing to do before entering Deskmate is to activate your control file. Do this with the DOS Print command by entering:

PRINT CHR120.DAT./P

Your printer should advance a blank page. If it prints any characters, an error

If a blank page doesn't advance, an error may exist in the escape sequence of the control file.

probably exists in an escape sequence within the control file. To deactivate this control file, print a file containing 'X, which resets the printer driver.

The Figure shows the in-text command for underlining and the resulting output as an example. Now you can go to work creating your text in Deskmate.

John Heenan designs products with his Tandy 1000 and is a free-lance writer. Write to him at 319 Belmont, Placentia, CA 92970.

{UNDERLINE. One should note that the underline continues under all spaces as well. This will not be true for all printers. On my DWP 210 the underline does not print under the spaces between words. The underline will continue until the End Underline character.}

UNDERLINE.

One should note that the underline continues under all spaces as well. This will not be true for all printers. On my DWP210 the underline does not print under the spaces between words. The underline will continue until the End Underline character.

Figure. Demonstration of the underlining control code and the resulting printout.

CALL FOR ARTICLES

Have you written a program or utility that might be interesting to other 80 Micro readers? Do you know a DOS or programming technique that you'd like to share? Then how about sending it in to 80 Micro for possible publication?

We're looking for people with good ideas. In particular, we'd like to see some useful utilities, small-business and personal management programs, tutorials on Basic and Pascal programming for all levels of expertise, and interesting science, math, and hobby applications.

The procedure is simple. Write us a query letter telling us about your proposed article. We'll tell you whether we think your article is appropriate for 80 Micro. We'll also send you a copy of our author's guidelines, which will give you information on manuscript preparation, style, payment rates, and the like.

Send your letter or proposal to Submissions Committee, 80 Micro, 80 Elm St., Peterborough, NH 03458. No phone calls, please.

xT.CAD cut \$100

xT.CAD PROFESSIONAL by Microdex. Computer Aided Drafting software for technical production and education. Create, edit, modify precise drawings, details. Features include overlays, grids, cursor snap, zoom, pan, block copy, enlarge, reduce, rotate, mirror, clip, merge, text labels, more. Requires hi-res screen and RS-232 interface. Output to pen plotters. Input from keyboard, or optional digitizer or mouse (yes, also on Models III and 4, see below). Friendly, competent support since 1984. Software is backup-free. Was \$345 in 1986 catalog. Model III (48K) \$245.00 Model 4 4p 4d (64K) \$245.00 MS/DOS computers (256K, fast!) \$195.00

xT.CAD BILL of Materials by Microdex. Software utilizes text labels from xT.CAD drawings to automatically generate invoices, parts requests, shipping lists, etc. Includes a mini-editor for customizing of output to line printers.

Model 4 4p 4d or MS/DOS \$ 45.00

GRAFYX Solution by Micro-Labs. Easy to install board provides hi-res for Models III/4/4p/4D similar to Radio Shack boards. Includes popular GBASIC software and manual. In addition to xT.CAD supports many other graphic programs.

Model III (512x192 pixels) \$195.00 Model 4 4p 4d (640x240 pixels) \$195.00

MOUSE interface by Micro-Labs connects to 50-pin I/O port and allows the use of Tandy Color Mouse 26-3025 (not included) with xT.CAD and other programs.

Model III 4 4p 4d \$115.00

CASH PROFESSIONAL by Microdex. Clever cash journal software with automatic double-entry ledger distribution in user-definable categories. Reports by period, account, project, etc. Ideal forsmall business, professional or personal bookkeeping.

Model 4 4p 4d or MS/DOS \$ 45.00

Microdex Corporation 1212 N. Sawtelle Tucson AZ 85716

602/326-3502

Write or call for details.



80 Micro, May 1987 • 91

New for MS-DOS from Hypersoft! PCXZ 1.0 Cross-Zap Utility for PC/MS-DOS

Now, from the Author that brought you Hypercross, Hyperzap and SuperCross comes an amazing new program for owners of Tandy 1000, 1200, 3000 and true PC compatibles. PC Cross-Zap allows you to read all double density TRS-80 type disks on your PC. Not only that, PCXZ offers many of the features that TRS-80 owners have long enjoyed with HyperCross and HyperZap.

PC Cross-Zap is a utility program that runs on your PC or PC-compatible. With it you can copy files to or from TRS-80 disks at will. You can also format a disk, copy disks, explore, read and write sector data, repair bad directories and much more. Long after your TRS-80 is gone you will still be able to read your old disks. Even when you TRS-80 disks are gone you can continue to use PCXZ to read, fix and modify MS-DOS and other disks so your investment will never be lost.

Formats Supported: Model I mixed density: DOS+ 3.4, DoubleDOS, LDOS (SOLE), MultiDOS, NEWDOS 80 V2, TRSDOS 2.7/8. Model I/III Double Density: DOS+ 3.5, LDOS 5.1. Model III: DOS+ 3.4, MultiDOS, NewDOS 80, TRSDOS 1.3 Model 4/4P: MultiDOS, DOS+ 4, TRSDOS 6. Max-80: LDOS 5.1. All formats also supported in double sided, 35, 40 and 80 tracks where appropriate. For 80 track formats you must have an 80 track (720K or 1.2M High Density) drive on your PC.

Main Features: With PCXZ you can format a TRS-80 disk (not the mixed density Model I types). You can copy files from a TRS-80 disk error free, without losing any data. Just like HyperCross 3.0 you can instruct PCXZ to convert your BASIC files on the fly as they are copied. ASCII and word processor text files are converted so they are in the correct format for your PC. Copying can be by file or using wild cards. You can also copy files from PC format back to your TRS-80 disks.

The Disk Zap, fix and copy features are perhaps the most exciting feature in any program ever offered in support of TRS-80 and MS-DOS disk formats. For the first time when you examine a disk the program tells you what you are looking at. For instance if you are inspecting a directory entry you will be told what each byte means as you move your cursor over it. This makes repair and modification a snap because you see the results of the change as you make it. Among the many things you can do are: remove passwords, rename, delete and undelete files. All is easy with the helpful prompts and action keys of PC Cross-Zap. The program comes with a manual that, also for the first time in one place, explains TRS-80 and MSDOS disk formats for all the different DOS versions.

Constant improvements and generous upgrade policy. We are constantly improving our programs, adding new features and increasing performance. Ask, we may have already added the feature you need.

System Requirements: PC, XT, AT or compatible, Tandy 1000 or 1000EX (needs DMA), 1000 SX, 12000, 3000 with at least one 360K or 1.2M drive and 256K minimum memory. PCXZ can read, write and format 40 or 80 track TRS80 disks on a High Density drive. An original program from Hypersott: Get PCXZ \$79.95 ppd. Call for special price for registered Hypercross owners.

Also for your PC: XENOCOPY II and MatchPoint

XenoCopy II runs on your PC and lets you read, write and format up to 275 different non TRS-80 formats. Includes many CP/M formats, CoCo, P-System disks and others.

XenoCopy II file transfer program for the PC \$81.95
Matchpoint—PC is the hardware solution to reading and writing Apple disks on your PC. A half-size card plugs in your PC and does the job software alone cannot. Reads Apple DOS, PRODOS, SOS, CP/M, also NorthStar CP/M and many other CP/M formats. Requires installation. Some disk drives need a minor modification.

TRS-80 Model I/III/4/4P Programs

HyperCross 3.0 - The Proven Standard in File Transfer.

Using HYPERCROSS 3 you can COPY files between TRS-80 disks and those from many CP/M and IBM-PC type computers on your own TRS-80 Model I, III, 4/4P or Max-80. If you have access to more than one kind of computer, or you are changing to a new machine then you need HYPERCROSS to transfer your text files, BASIC, FORTRAN PASCAL or C programs, Viscalc files, general ledger and accounting files, data bases and even binary files. You can FORMAT alien disks, read their directories, copy files to and from them, even copy directly from one alien disk to another.

Formats supported: IBM-PC and MS-DOS compatibles include DOS 1.1, 2.0-3.2 Tandy 2000, single and double sided, 3.5 and 5 inch. CP/M from Aardvark to Zorba, including all popular TRS80 formats such as Holmes, Montezuma, and Omikron. TRS-80 Color Computer format also supported.

HyperCross converts Basic files! Now HyperCross includes a feature to automatically change the tokens in a TRS-80 file to the correct format for CP/M or MSDOS. As you copy, HyperCross automatically converts the Basic file, putting in spaces, changing PRINT @, correcting syntax errors and flagging parts needing manual modification.

correcting syntax errors and flagging parts needing manual modification.

Tried and Tested in 1000s of installations world wide, by Industry, Universities, Government Institutions and nice TRS-80 owners everywhere. Prices include disk, manual, and shipping. Upgrades from any version of HyperCross or SuperCross for old disk+\$5+price difference (\$15 min).

HyperCross 2.0 CoCo reads CoCo format (No Basic convert)	\$49.95
HyperCross 3.0 CP/M reads 40 single sided CP/M formats	\$49.95
HyperCross 3.0 PC reads popular MSDOS 1.1-3.2 formats	\$49.95
HyperCross XT/3.0 reads 90 different CP/M and PC formats	\$89.95
HyperCross XT/3.0-Plus. Reads over 220 formats inc CoCo	\$129.95
Specify TRS-80 Model I (needs doubler), III, 4/4P or MAX-80. Dual Model versions	
3/4 on one disk add \$10 extra.	

Amazing HYPERZAP 3.2G Disk Magic!


Do you want to back up your precious copy of Copycat 3, or SU. Do you want to fix or modify a disk - if so then you need HYPERZAP! On the market for 3 years, HYPERZAP is more than just another disk copying program - it is the program for analyzing, copying, repairing, creating floppy disks of all kinds, It works with TRS-80 formats as well as many others such as CP/M, PC, CoCo etc. Designed to handle mixed density sectors on any track in any sequence. Many features for reading, writing, editing track and sector data. Hyperzap is the tool that lets you be in charge. Make your own self booting disks. Take you own CMD file and turn it into a dual booting Mod 1, III, IV disk. Autopilot mode allows learns, saves and repeats procedures. Disk comes with fascinating examples. Use Hyperzap as a learning tool, find out how things are done!

HYPERZAP 3.2G - nothing else even comes close! \$49.95 ppd

For technical support, call (919) 847-4779

"HYPERSOFT
PO Box 51155, Raleigh, NC 27609
8am-11 pm EST

For orders only, call (800) 541-0900 In CA (800) 334-3030



MEMORY MINDER

Memory Minder is the most comprehensive disk diagnostic program available for microcomputers. It quickly and easily checks the vital operating parameters on your floppy drives, including spindle speed, head alignment, read sensitivity and others. Early detection and correction of possible problems prevents loss of valuable data.

Use Memory Minder to align the drives without the use of an oscilloscope. The users manual helps interpret the screen graphics for each test, and where adjustment is possible, provides general guidelines for adjustment of the drive. No special tools required!



Address

State

City

15100-A CENTRAL SE ALBUQUERQUE NEW MEXICO 87123 505/292-4182

TRS-80 Model III/4 (48 tpi Single Side) \$ 79 (48 or 96 tpi Double Side) \$ 89 (Combo 48 & 96 tpi Double Side) 129 TRS-80 Model I (48 tpi Single Side Single Density) \$ 89 TRS-80 Color Computer (48 tpi Single Side) (48 tpi Double Side) 75 IBM PC, XT, AT and Compatibles \$ 70 Program and Manual Only. Purchase Precision Alignment Diskettes Separately. 508-400 (51/4" 40 Track Drives) 506-400 (51/4" 80 Track Drives) 40 516-400 (1.2 MB AT Drives) 40 305-400 (3.5" 80 Track Drives) \$ 40

We accept Visa, MasterCard and prepayment. Or we can ship COD for cash or certified check via UPS ground within the continental U.S. Add \$4 for shipping. Blue Label and international orders extra.



Let us know 8 weeks in advance so that you won't miss a single issue of 80 Micro. Attach old label where indicated and print new address in space provided. Also include your mailing label whenever you write concerning your subscription. It helps us serve you promptly. ☐ Extend my subscription one additional year for only \$24.97. □ Payment enclosed Canadian and Mexican \$27.97 1 year only, US funds drawn on US bank. Foreign surface \$44.97 1 year only. US funds drawn on US bank. Please allow 6-8 weeks for delivery. If you have no old label handy print old address here. Name Address . State . Zip_ City Print NEW address here Name.

80Micro PO Box 981 • Farmingdale, NY 11737

Zip

Uncharted Territory

ast month, I showed you how to execute a batch file from another batch file and then return. This month, I am going to show you how to spawn a second batch-file job that executes after the current batch file completes. I'll also show you how to execute commands without reloading the DOS command processor and how to change variables in your master environment.


Before I get into these uncharted areas, I want to expand on two topics from last month's column. I discussed accessing DOS environment variables from within a batch file and said that I used this technique to keep my path current without changing the path statement in a massive number of batch files.

For example, suppose my path statement lists 10 subdirectories that DOS is supposed to search. Suppose that I no longer need the files in the third subdirectory in the path and I delete them, removing the subdirectory from the disk. I would have to go through each batch file on the disk and change the path statements to ensure that this subdirectory is not present. If I miss one and use the batch file, I will get a message stating that an invalid drive or directory is in the search path each time DOS has to search for a program not in the current directory.

The simplest solution uses the DOS Set command, which I described last month. You can use this command to access any environment variable, including the Path and Prompt variables. This means that you do not have to worry about finding all of the Path statements in your batch files; set it once in the Autoexec file and forget it.

For example, suppose that my starting path includes the directories C:\, C:\DOS, C:\DOS\UTIL, and C:\GAMES. If I delete all of the files in the Games directory and then remove that directory, I must also take this directory name out of the Path statement or I will get an error when DOS looks for a file.

I have quite a few batch files, and if I forget one of them that contains a change to the path, I create an error condition. Let the Set command do youur work; the command SET PATH = C: \MSC; % PATH% appends the old value of the Path variable to the new string



C:\MSC and stores it back in the environment as your working Path statement. This procedure does not care what the previous path was. Now you can change your Autoexec path at will without worry.

The second topic concerns the example of one batch file calling a second and returning. The second batch file makes changes in its environment that the first batch cannot access because the second batch has an entirely separate environment. Nice as it would seem, you cannot use this technique to pass parameters between invocations of batch files.

I do not think I stressed this inability to change environments enough—each task that operates under MS-DOS gets a private copy of the current environment, and no others can get to this area. But you can still change the master environment; that is one of the topics of this month's column.

DOS Mysteries

MS-DOS has many undocumented features—some are worth exploiting and have remained stable from DOS release to release. Others are less useful and change frequently. One of the more useful features is DOS interrupt 2EH, which provides a rapid entry point into the primary (or first loaded) resident DOS command interpreter. No matter how many layers or shells you have loaded, this in-

Fig. 1. Debug script for creating EXCMD.

AH,[0080]
AH,AH
0144
BX,01C0
BX,1
BX,1
BX,1
BX,1
BX
AH,4A
21
0137
[01BE],SP
[01BC],SS
SI,0081
2E
SP,CS:[01BE]
SS,CS:[01BC]
AH,4C
AL,AL
21
AH,09
DX.0151
21
AH,4C
AL,01
21

Fig. continued

JOHN'S MS-DOS COLUMN

terrupt quickly and easily executes your DOS commands without your reloading Command.COM.

This has several advantages. First, loading Command.COM takes time—time to find it, open the file, and load it. Second, you might have removed the floppy disk with Command.COM on it and now get delayed while DOS waits for you to replace the disk. A disadvantage to this technique is that certain DOS programs use the entire free space of memory, which destroys the transient portion of Command.COM. The worst offender is a Turbo Pascal-compiled program.

Another significant advantage is the ability to modify the master environment to allow this interrupt function to execute a DOS Set command. For example, the command SET VARIABLE1 = STRING sets the environment variable Variable1 to String in the master environment. Note that these changes occur no matter how many levels you are nested because the DOS interrupt 2EH function processor always points to the primary-level command processor.

Using undocumented features can be dangerous, but I consider this case justified. It is present in all DOS releases from version 2.0 to 3.2. Since ADOS for protected-mode operation on the 80286 processors will probably be the next major release, I think you are safe in assuming that interrupt 2EH will remain available to the older DOS versions.

Examining EXCMD

The Program Listing contains the source code for EXCMD, which uses the remainder of its own command line as a command string to pass to DOS via interrupt 2EH. You can key this in directly and assemble it as I indicated in the leading comments. Figure 1 contains a Debug script to use in place of the assembly source code. Type in the statements in Fig. 1 and save them to a file called EXCMD.SCR. Then load Debug and use the command: DEBUG <EXCMD.SCR and press enter.

This is a simple program that illustrates several features. Most importantly, it demonstrates the use of memory-allocation requests to reduce the initial program's size. When DOS runs a COM program, it assigns all the remaining available memory to your task. This is not practical if you want to run any other process as a "child" of your current program, so you must calculate a maximum size you need and release the remaining memory to DOS.

Also, DOS interrupt 2EH has a disastrous variation from version 2 to 3. I initially developed this short program on an IBM PC under DOS 3.2, and every-

Fig. continued	
MOV	AH,09
MOV	DX,017C
INT	21
MOV	AH,4C
MOV	AL,01
INT	21
DB	7,7
DB	'EXCMD - Fatal memory-allocation error!',d,a,'\$'
DB	'EXCMD - Command string required',d,a
DB	'Command execution aborted!',d,a,'\$'

Sample Batch File T1.BAT

dir/w

pause

excmd t2

rem This remark is executed after spawning off batch file T2 rem contents.

pause

Sample Batch File T2.BAT


rem In batch file number 2

pause

dir/p pause

rem All done in batch file T2

Fig. 2. Example batch files.



JOHN'S MS-DOS COLUMN

thing worked fine because the segment registers were protected. DOS 2 modifies all registers with the exception of CS and IP. Therefore, you must protect the stack pointer and segment registers.

Figure 2 contains two simple batch files to show what I initially claimed. If you type these in and execute them, a strange thing happens—batch file 1 runs completely to the end and finishes, and then batch file 2 starts to execute. It is almost as if you entered a command in the type-ahead buffer and then went on, letting the first batch file finish.

The diagram in Fig. 3 is a picture of memory while this example is running. First, DOS requires the amount of memory illustrated in the left box for itself, the basic input/output system (BIOS) code, the command interpreter, and the master environment. This uses 42,640 bytes out of my 512K memory (524,288 bytes). Depending on your DOS version, the number of files and buffers, and the device drivers loaded, your number could be more or less.

As the first batch file begins to execute, DOS creates a small memory block to control the batch file on top of the currently used memory (middle box). This reduces the total memory by 96 bytes for the control block. The extra difference between the left and middle boxes is 16 bytes allocated as a memory control header. Each block of memory allocated bears this header, which points to the beginning of the memory block and the

size, among other information.

The right box shows the picture you get after batch file 2 is executing. Note that the EXCMD program is still resident with its private copy of the environment. The difference of 592 bytes between the middle and right boxes is composed of a 16-byte header and 96-byte block for EXCMD's environment and a 16-byte header and 464-byte block for EXCMD itself.

As soon as both batch files have completed, the memory allocation returns to the starting condition. DOS releases all unused blocks and returns them to the dynamic allocation pool.

Conclusion

EXCMD is another useful tool to add to your stock. You will have to experiment with it to appreciate its power. Batch files are valuable for effective use of your computer, especially if you have a hard disk.

I want to hear your needs and problems. Please write or contact me via Compuserve 73016,1326. I regularly attend the Tandy computer forum (TRS80PRO), and you can leave your questions via Easyplex.■

John B. Harrell III is a naval electronic warfare systems analyst. He has written for 80 Micro for five years and programs in Pascal, C, and assembly language. Contact him c/o 80 Micro, 80 Elm St., Peterborough, NH 03458.

Program Listing. EXCMD.

PAGE ,132
TITLE EXCMD - Fast DOS Command Executer
NAME EXCMD

PROGRAM:

EXCMD executes DOS commands without reloading the DOS command processor. This program uses an undocumented interrupt vector pointing to the system's primary (or first loaded) command processor.

EXCMD uses DOS interrupt vector 2EH, which exists in all current versions of MS-DOS/PC-DOS from version 2.0 to the existing version 3.

Any DOS command, EXE program, COM program, or BAT file can be executed using this simple extension to DOS just as you would from the DOS command prompt.

SYNOPSIS:

EXCMD [command line with optional parameters]

EXPLANATION:

DOS parses the command line above, leaving the bracketed command tail in the command line buffer in the current task's program segment prefix (PSP) beginning at offset 0080H. This first byte is a count of the characters in the command tail minus the ending carriage return. If the character count byte is zero, the command tail is absent.

EXCMD passes this command string contained in the tail directly to the primary command processor for action. Note that some DOS programs may contaminate the transient portion of Command.COM and succeeding DOS commands might not execute properly.

Also note that using any DOS command that modifies the operating system's environment WILL AFFECT ONLY THE

Listing continued

MAC INKER™

MAC INKER™, Automatic Ribbon Re-inker. Re-ink any fabric cartridge or spool for less than 5 cents. Over 70,000 in the field and



we support
ALL printers.
Universal
Cartridge or
Universal Spool
MAC INKER


\$68.50.

re-inkable in 10 colors. Ask for your printer type or for complete listing. Bottle ink \$3.00/each. shipping \$3.00.

PROTEUS™, the 'Siamese' Buffer. It is a Data Switch with buffer on both ports. Switch manually or via software. Saves time, space and money. Or ask

about our MAC
MASTER line

of Universal Buffers and




PROTEUS 64 K-199.00

256 K-299.00 Shipping \$4.00.
Of course we have **Data Switches**,
serial/parallel, 2 way, 4 way, crossed
etc., at most competitive prices (all
lines switched).

CABLES priced \$10-30. We carry cables for all common computers and peripherals. Rapid turn-around on custom orders.

MERCURY MODEM. Really 100% Hayes* Compatible. 300/1200 baud, speaker, full status light display and 2 year warranty. \$149.00



Includes Quick Link Communications Software—fast, quick, easy to learn. \$29.95 (available for IBM PC or Macintosh)

*Hayes is a trademark of Hayes Microproducts.

MAC THE RIPPER. Our newest, original and welcome printer companion. Pulls off paper perforations and tears the sheets apart. Takes little space and will pay for itself almost immediately in saved time and tedium. Ask for brochure. Introductory Price \$299.00. Shipping \$10.00.

Order Toll Free.

Call or write for free brochure.

1-800-547-3303 In Oregon 503-626-2291 (24 hour line)

We are and always will be your

CEmputer Friends®

14250 N.W. Science Park Drive Portland, Oregon 97229 Telex 4949559 Dealer inquiries welcome.



CDA COMPUTER SALES

Tandy 1000 SX **Color System**

System Includes:

NOW ONLY

·Tandy 1000SX with 640K of RAM

\$1369.00

2 Floppy Drives Deskmate Software

List \$1877.00

- Tandy CM-5 Color RGM Monitor
- Tandy DMP-130 NLQ Printer
- Printer Cable • Table Top Printer Stand
 - Save Over
- Package of Computer Paper \$500 !!! Box of 10 Maxell Diskettes
- Perfect Data Head Cleaning Kit

Complete Ready-To-Run System !!!

When ordering specify package #8715

Tandy 20 Megabyte Hard Disk Card

•Easy To Install !!! •Tandy 1000/1200/3000 Compatible List \$799

Now Only \$599

Tandy 1000 Upgrades≡

PBJ MFB-1000 Multifunction Card - 512K with DMA Clock/Calendar, Battery Backup, Serial RS-232 Port, and RAMdisk software. (1000) List \$299 Now Only \$199

Tandy Internal Floppy Drive Kit — Add a second Drive to your Tandy 1000 - easy to install! (1000) Now Only \$149

Zucker Memory Upgrade Kit — Add 512K to your 128K 1000 for a total 640K with DMA - user installable. (1000) List \$149 Now Only \$119

AST I/O Plus — Add Clock/Calendar with Battery Backup and Serial Port. (1000/1000SX) List \$185 Now Only 8139

Zucker Hard Card — 20 Megabyte Hard Card, pre-formatted easy to install. (1000/1000SX)

Now Only \$549 Seagate 20 Megabyte Kit for 3000 HL, complete with easy to install instructions and Western Digital Floppy/Hard Controller. (3000HL)
List \$1198 Now Only \$599

1000SX Memory Chip Set 256K for 1000 SX Easy to install instructions included.

Now Only S38

Tandy Products	NOW OHLY \$38							
Description	List	CDA						
Tandy 3000 HL	\$1699	\$1299						
Tandy CM-5 RGB Monitor	\$ 299	\$ 239						
Tandy CM-11 RGB Monitor	\$ 459	\$ 359						
Tandy EGM-1 Monitor	\$ 699	\$ 559						
Tandy EGA Adapter	\$ 349	\$ 279						
Tandy 1000 SX 384K	\$ 999	\$ 749						
Tandy 1000 SX 640K	\$1098	\$ 789						

	 120 Characters per second 	
П	Column Width 80/	
	Condensed 132	
	Near Letter Quality Mode	
	List \$299 Now Only \$239	•

Epson LX-86

- Epson FX-86E ≡ 160 Characters per second Column Width 80/
- Condensed 132 Letter Quality Mode •IBM Proprinter Compatible List 8549 Now Only \$399

ORDERS ONLY 800-526-5313 IN NJ 201-728-8080

Inquiries & Customer Service 201-728-8082

No-Risk 30 Day Satisfaction Guarantee If you're not 100% satisfied with any hardware or accessories you've purchased from CDA Computer Sales we will refund your purchase price. 100% No questions asked!

CDA COMPUTER SALES

31 Marshall Hill Road

West Milford, NJ 07480

JOHN'S MS-DOS COLUMN

```
Listing continued
                        PRIMARY OR MASTER ENVIRONMENT COPY.
                                                                      Other environments
                         loaded on top of the primary environment will not
                        change.
       ASSEMBLING:
                        To build an executable program file from the assembly source, follow these simple steps after entering the source code:
                         1) MASM EXCMD:
                         2) LINK EXCMD;
                            Disregard the error message stating that there was
                            no stack segment.
EXE2BIN EXCMD EXCMD.COM
                         4) Delete the resulting OBJ and EXE files.
                                                   ;Write string to standard output
;Set memory block to requested size
;Terminate a process w/return code
;DOS command function processor
;Entry point into primary COMMAND.COM
 WriteString = 09H
  SetBlock = 4AH
ExitFunction = 4CH
                    21H
  DosCall
  ExecInt
                  = 2EH
                                        MAIN CODE BODY
   ***********
                SEGMENT PARA 'CODE'
ASSUME DS:CODE, CS:CODE, ES:NOTHING, SS:CODE
  PSP_Count
                          127 DUP(?)
  PSP String DB
                PROC
                          NEAR
                          AH, PSP_Count
                                                    ;Test for command tail present ;Must have a command tail
                OR
                          AH. AH
                JZ
                          CantExecute
                          BX, OFFSET LastByte ; Get last byte address
                MOV
                          BX,1
BX,1
                SHR
                                                    Divide by 16 for paragraphs; Add 1 for partial paragraph; Function to shrink memory
                SHR
                          BX,1
                INC
                           AH. SetBlock
                MOV
                           DosCall
                INT
                                                    ;Fatal memory allocation error
                           FatalError
                           WORD PTR StackPtr,SP
WORD PTR StackSeg,SS
SI,OFFSET PSP_String
                                                           :Save stack pointer
                MOV
                                                           ; and the segment register
;Point to command tail string
                MOV
                                                           ;Call primary COMMAND.COM
;Restore Stack Pointer
                INT
                           ExecInt
                           SP, WORD PTR CS: StackPtr
                           SS, WORD PTR CS: StackSeg
                MOV
                           AH, ExitFunction
                                                     :Return to DOS
                MOV
                                                     ;Set error code zero
                           DosCall
  PatalError:
                                                     ; Set DOS function code
                 MOV
                           AH, WriteString
                           DX,OFFSET ErrorlMsg ; Point to string
                 MOV
                 INT
                           AH, ExitFunction
                                                     :Return to DOS with an "errorlevel"
                 MOV
                                                     ; code set
                 MOV
                           DosCall
  CantExecute: MOV
                                                     ;Set DOS function code
                           AH, WriteString
                           DX,OFFSET Error2Msg ; Point to string
                 MOV
                                                     :Return to DOS with an "errorlevel"
                 MOV
                           AH, ExitFunction
                 MOV
                           AL,1
DosCall
   EXCMD
                 ENDP
                           7,7,'EXCMD - Fatal memory allocation error!',13,10,'$'
                 DB
   Error 1 Msg
                           7.7. EXCMD - Command string required', 13, 10
   Error 2Msg
                 DB
                            'Command execution aborted!',13,10,'$'
   StackSeq
   StackPtr
                 DW
                                                     ;Last byte of program + 1
   LastByte
                 EOU
                           $
   CODE
                 ENDS
                 END
                           EXCMD
                                                                                                   End
```



You've Got L ACCESS

TO YOUR COMPUTER HARDWARE & SOFTWARE **NEEDS. CALL ROSE TODAY!**

QUALITY DISK DRIVES

These drives are complete with power supply, cover and external drive connector. For TRS-80 Model I, III, 4, IBM PC and others. All drives are Double Density and step at 6ms or less. SS means single head, DS is double head. Specify white or silver color cover for no additional charge or my beautiful new Stainless Steel cover for only \$9 additional. Add \$5 per drive shipping unless otherwise specified. All drives have a one year warranty on parts and labor. Bare drives, that is, just the drives themselves are also available for those of you who don't need or want one of my power supplies.

COMPLETE 3.5" - 5.25" - 8" DISK DRIVES Les 40th DS TEAC ED-35B in a dual case

188. 4UTK DS TEAC FD-33D III a dual case
2ea. 40tk DS TEAC FD-35B in a dual case 255
1ea. 80tk DS TEAC FD-35F in a dual case 177
2ea. 80tk DS TEAC FD-35F in a dual case 285
40tk SS Tandon TM100-1 \$ 147
40tk DS Tandon TM100-2157
1ea. 40tk SS TEAC FD-55A in dual case \$ 127
2ea. 40tk SS TEAC FD-55A in dual case 217
1ea. 40tk DS TEAC FD-55B in dual case 137
2ea. 40tk DS TEAC FD-55B in dual case
1ea. 80tk DS TEAC FD-55F in dual case 157
2ea. 80tk DS TEAC FD-55F in dual case 277
Add \$10 S & H per case for these 8" drives.
2ea. SS TM848-1E's in dual case with fan \$ 647
2ea DS TMR48-2F's in dual case with fan

BARE 5.25" & 8" DISK DRIVES

Add \$4 shipping per drive.

40tk SS, Full Size, Tandon TM100-1						.5	99
40tk DS, Full Size, Tandon TM100-2	١.						119
40tk SS, Half-High, TEAC FD55-A .							. 99
40tk DS, Half-High, TEAC FD55-B .							
80tk DS, Half-High, TEAC FD55-F .							129
8" SS, Thinline, Tandon TM848-1E							259
8" DS Thinline Tandon TM848-2E							333

TRS-80 MODEL III/4 DISK DRIVE KITS

Add \$8 shipping per kit.

Internal drive kit complete with disk controller, power supply, mounting brackets, cables and all hardware plus step-by-step instructions. This kit contains everything you need (except the Disk Operating System, drive and a screwdriver) to convert your cassette Model III or 4 to fast reliable disk operation. Don't confuse this quality kit with the high-priced ripoffs. Thousands of satisfied customers cannot be wrong. You can join them for\$ 189 Same as above but with 1-40tk SS drive289 Same as above but with 2-40tk SS drives 388

TRS-80 MODEL I DOUBLE DENSITY CONTROLLERS

Add \$3 shipping.

Aerocomp	"DDC"	Really the best by test	\$ 99
		with LDOS	
		with NEWDOS 80-v2.0	

OTHER DRIVE GOODIES

ч	dd \$2 shipping.		
	TRSDOS 1.3 Disk & Manual for Model III		
	TRSDOS 2.3 Disk & Manual for Model 1		24
	TRSDOS 6.x Disk & Manual for Model 4		34
	LDOS for the Model I or III		69
	NEWDOS 80 v2.0 for the Model I or III		99
	2-drive cable for Model I/III/4		24
	2-drive external cable for IBM PC	 i	40
	4-drive cable for Model I		34
	Extender cable, 7" long	 i	. 9
	5.25 power supply & encl., white or silver		59
	Sainless Steel Covers		12
	8" power supply, fan & enclosure, beige	 1	49

OSE GETS RIG ROS

Complete with Manual

Rose has latched onto this slick version of CP/M 2.2 that allows you to run most of your favorite CP/M programs with ease. It even lets you read and write other manufacturers' disk formats. What could be nicer? They are in stock ready for you to use and enjoy.

TRS-80 SPECIAL EQUIPMENT

12" Green Comp. Monitor. Add \$ 10 for I IL	Э
12" Amber Comp. Monitor. Add \$10 for TTL 8	4
	9
64K 200 nsec RAM Guaranteed 1 year(8 chips) 1	9
64K RAM plus Genuine PAL for Model 4	9
256K 150 nsec RAM 1 yr guarantee (8 chips) 3	9

MEDIA & SUPPLIES

5" Diskettes SSDD, Lifetime Guarantee. 10pk		 .\$	16
5" Diskettes DSDD, Lifetime Guarantee. 10pk		 	19
5" Flipsort, holds 75 Diskettes		 	16
8" Diskettes SSDD, Lifetime Guarantee. 10pk		 	24
8" Disketted DSDD, Lifetime Guarantee. 10pk		 , ,	29
8" Flipsort, holds 50 Diskettes		 	22
5.25" or 8" Head Cleaning Kit		 	. 9
Letter Size 20 lb. Tractor Paper, 2900 sheets .	-	 	25

SPECIAL SOFTWARE DEALS AND SALES

WordStar 3.3 (Specify MM or R/S format) \$ 195
MailMerg [®] , SpellStar [®] , Starindex [®] , all 3 for just 99
WordStar Professional (Above 4 Progams) 275
DataStar* Data Entry & Retrieval
ReportStar® Report Generator 105
InfoStar® Advanced DBMS (Above 2 Programs) 195
dBASE II Complete With Disk Tutorial 345
Super Utility Plus 3.2 by Kim Watt 59
CP/M 2.2 for Model 4 by Monte Zuma 169
Turbo PASCAL by Bor Land. Requires CP/M 44
Turbo Toolbox by Bor Land 45
Turbo TUTOR by Bor Land
Pickles & Trout CP/M 2.2m for the Model
2-12-16. Floppy Version
Same thing but the Radio Shack Hard Disk 219

CP/M & 80 COLUMN for your MODEL III

No need to buy a new computer when you can use the Holmes VID-80 modification and get CP/M 2.2, 64K RAM and 80 column video. This kit is easy to install and requires no soldering. Even a dolt like you can can end up with a complete 64K CP/M computer with an 80 column screen that is still able to run all your existing Model III software. For the first time you will be able to use CP/M programs that normal people do, such as dBASE II and WordStar. The regular price of this kit is \$524. Now Rose will get you going for only Add \$5 shipping ... \$ 299

I'll ship you the Holmes deal above PLUS WordStar 3.3 installed, complete with orignal manuals ready to run for only....\$ 399

ORDER NOW! TOLL-FREE

800-527-3582 **Orders Only Please**

Call in your order or write to us at the address below. Texas residents call us at 214-634-3336 and deduct \$2.00 from your order but you should remind me 'cause sometimes I forget. If you need technical information or service please call the Texas number as the Toll Free lines are just for orders only. Prices are subject to change without notice and are mail order only. I accept AMERICAN EXPRESS, MASTERCARD and VISA and I will not charge your card until I ship your goodies. You can send a check or a money order. I also accept COD orders but they require cash or a cashier's check upon delivery. If shipping charges are not shown please call for the correct amount. Add \$5.00 handling charge if your order is less than \$50.00. Shipping charges quoted in this ad are for the lower 48 states only. Orders to Canadian address add \$20.00 to pay for doing all those papers for customs. Texans add State Sales tax. No tax collected on shipments outside of Texas. Be sure you know what you are buying. SOFTWARE IS SOLD ON A REPLACEMENT BASIS ONLY - NO REFUNDS. If it is defective call us for instructions. Please order from me now---I need the money and I will not jack you around. I reserve the right to charge up to a ten percent restocking charge if you jack me around. All merchandise carries the original manufacturers' warranty and all repairs or adjustments will be made by the manufacturer or his designated representative.

NEXT DAY SHIPMENT of Goods in Stock.

TOTAL ACCESS

2544 West Commerce Street P.O. Box 223957 Dallas, Texas 75212 214-634-3336

User-Supported Word Processors

andy didn't seem to have word processing in mind when it introduced the Model I nearly 10 years ago. It had no lowercase letters, and even the crudest dot-matrix printers were in the \$2,000 range at the time.

Computers and printers have come a long way since then. Word processing is now a popular application. Commercial word processors abound, and a number of public-domain (PD) word processors rival the better commercial versions. I'll describe many of the MS-DOS PD word processors this month. Most are user-supported—also referred to as freeware or shareware. This means that, if you find the program useful, you are expected to make a donation to the author. See my April 1987 Public Works column (p. 122) for more information on user-supported software.


PC-Write

One of the more successful user-supported word processors is PC-Write. It is so successful that its author, Bob Wallace, has founded a company, Quicksoft Inc., to provide support to paid users and to improve PC-Write. This product has been updated many times since its beginning in 1983. The most recent version is 2.71. PC-Write is commonly found on bulletin-board systems (BBSes) around the country, though some do not have the latest version. It's hard to keep up with a program that has been revised so many times.

PC-Write includes an on-line spelling checker and dictionary. Other PD word processors also have this feature, but PC-Write's spelling checker works as you type. If you type a word that is not in its dictionary, PC-Write signals you with a beep. You can then either correct the spelling or add the word to an auxiliary dictionary.

Though the spelling checker is not the best in the world, it is sufficient for most tasks. If you want a better spelling checker, you can install Borland International's Turbo Lightning, a commercial spelling checker and thesaurus. Instructions for doing so are in the manual provided to contributing users.

PC-Write has probably the most extensive and easiest-to-use help utilities of all the PD word processors. These utilities



A number of PD word processors rival the commercial versions.

cover 45 topics ranging from the basics of using the program to footnoting, referencing, inserting headers and footers, and operating the spelling checker. They also tell you what you get for being a supporting user and provide a phone number to call for help. While most of Quicksoft's support service is for registered users, unregistered users may call for help getting started.

Quicksoft's main source of income comes from the extra support it provides. To start, you can buy the two program disks for trial from Quicksoft for \$16. These disks include the full program and instructions, which you print out with a special program provided. If you like the program, you can then either buy the printed hard-bound manual for \$45 or, as they say it, "really buy" PC-Write for \$89, which covers registration.

The 350-page manual is professionally done. For your \$89 you also get telephone

support for one year, a quarterly newsletter, two free updates with disks and upgrade notes, and a \$25 commission when someone else registers and gives the registration number from your disk.

PC-Write is easy to use and learn, making it good for beginners.


PC-Type +

Another prominent shareware author is Jim Button. Along with the late Andrew Fluegelman, who wrote PC-Talk and coined the term "freeware," he pioneered the user-supported concept. Jim is the founder of a company called Buttonware, which produces and distributes shareware programs that he and others wrote. One program distributed through Buttonware is a word processor called PC-Type +.

Buttonware's philosophy is to give the user the complete program and instructions, but to hold back on fully describing some of the more sophisticated features. When you register for PC-Type + by paying \$69.95, you receive a 300-page manual, update notification, the latest version of the program, more detailed help disks, and a year of technical support.

The PC-Type + disk has three levels of help files. The first level uses screen help files that you call from within the program with the F1 key. The second level is a menu of 14 help files that you can

ELECTRONICS







256K MOD 1000 EX 1 DR529.00	10 MEG HARD DISK499.00
384K MOD 1000 SX 2 DR779.00	10 MEG BACK UP
512K MOD 3000 HL 1 DR1139.00	20 + 20 MEG B/U
512K MOD 3000 1 DR1629.00	20 MEG HARD CARD569.00
512K MOD 3000 20 MEG 1 DR2479.00	35 MEG HD PRIMARY2049.00
640K MOD 3000 40 MEG 1 DR2929.00	35 MEG HD SECOND1829.00
512K MOD 6000 15 MEG 1 DR 2629.00	70 MEG HD PRIMARY2679.00
24K MOD 102 PORTABLE	70 MEG HD SECOND
24K MOD 200 PORTABLE 599.00	3½ DRIVE MOD 102149.00
32K MOD 600 PORTABLE1149.00	3½ DRIVE MOD 1000225.00
64K MOD 4D 2 DR839.00	5½ DRIVE MOD 1000170.00
VM-4 MONO MONITOR94.00	360K DRIVE MOD 3000135.00
VM-3 MONO MONITOR	1.2M DRIVE MOD 3000 209.00
VM-1 MONO MONITOR149.00	128K COCO 3
CM-1 COLOR MONITOR399.00	PRINTER SWITCH 80.00
CM-5 COLOR MONITOR219.00	PRINTER CONTROLLER179.00
CM-11 COLOR MONITOR 319.00	8 COLOR PLOTTER
DMP 105 PRINTER 145.00	STANDBY POWER
DMP 130 PRINTER 249.00	300/1200 MODEM BRD155.00
DMP 430 PRINTER479.00	CELLULAR PHONE929.00
DMP 2110 PRINTER889.00	SATELLITE ANTENNA1519.00
DMP 2200 PRINTER1149.00	ROBIE SR ROBOT139.00
DWP 220 DAISY WHEEL	TRACTOR DWP 22079.00
DWP 230 DAISY WHEEL 299.00	TRACTOR DWP 23080.00
DWP 510 DAISY WHEEL549.00	TRACTOR DWP 510159.00
DWP 520 DAISY WHEEL	TRACTOR DWP 520109.00

100% RS COMPONENTS NO FOREIGN DRIVES OR MEMORY FULL WARRANTY
ALL RS SOFTWARE 20% OFF CATALOG PRICE
CASHIERS CHECK OR MONEY ORDER MUST ACCOMPANY ALL ORDERS

(817) 825-4027

NOCONA ELECTRONICS • BOX 593 • NOCONA, TX 76255

select. In the third level, you select help on one of 64 topics.

PC-Type + has no instruction manual on disk; you must become adept at using the help files. The help files are cumbersome and require guesswork to figure out how to access them.

The program and over 750K of supporting files reside on three disks. Most of the files are overlays and aren't resident while the program runs. A 20-megabyte hard drive is almost a necessity when using this program.

PC-Type + has its own spelling checker and 100,000-word dictionary, but it does not check spelling as you type as does PC-Write. PC-Type + does not guess which word you meant to type when it finds one not in its dictionary. PC-Write has this option, but it leaves a lot to be desired. PCMerge, a program to mail-merge files, and PCLabels, a program to print address labels, also come with PC-Type +.

New York Word

A lot of people in my area think that New York Word (NYW), written by Marc Adler, is a good word processor. NYW is a spin-off from a Unix word processor of the same name sold commercially by the author. NYW (version 2.1) not only has its own spelling checker and dictionary, but an automatic-hyphenation option, as well. For those of you who are interested, this option's code uses a cross between the Knuth automatic-hyphenation algorithm and the Gimpel algorithm. The spelling checker has a bug: It doesn't recognize misspelled words that end a sentence. It apparently considers words that end in a period as abbreviations.

NYW also has two calculator modes and can do limited graphics using ASCII line-drawing characters.

Though not as easy to use as PC-Write, NYW is much simpler than PC-Type +. Its on-line help files are easier to access than PC-Type +'s and more extensive than PC-Write's. Learning NYW's commands is probably harder than with PC-Write. If you are familiar with Wordstar, you can configure many of the keys to replicate the Wordstar commands. NYW has a set of utilities that can reconfigure keys to practically any one- or two-key combination. A file is already set up to configure to Wordstar. Another notable feature is the ability to generate a table of contents and an index.

Other than the help files, no instructions are provided on the disk. Registered owners (those who send a donation) receive a 100-page manual. The requested donation is \$35. Registered users also receive mail-merge and label programs. Considering the price, NYW is an excellent value.

Wordplan

One of the newer word processors on the PD scene (version A.00.00) is Wordplan from DEA Software. Public Brand Software (P.O. Box 51315, Indianapolis, IN 46251, 800-426-3475), one of the distributors I wrote about last month, sent it to me. Public Brand gives Wordplan its highest rating: four stars and a trophy symbol meaning tremendous.

New York Word is a spin-off from a Unix commercial word processor.

Actually, DEA calls its word processor a "decision-support system generator." It has extensive math capabilities that are programmed into the text you create. Wordplan can even read 1-2-3 spreadsheet information directly from the spreadsheet file and print out tabulations and totals in a final report. There is no need to cut and paste information from the spreadsheet. DEA requests a \$49.95 donation.

An internal modeling language within Wordplan determines which information from the spreadsheet is pertinent and makes the calculations for you. When you update the information in the spread-

New York Word, \$35 Marc Adler Magma Systems 138-23 Hoover Ave. Jamaica, NY 11435

PC-Type + , \$69.95 Buttonware Inc. P.O. Box 5786 Bellevue, WA 98006 206-454-0479 800-528-8866 (order line only)

PC-Write, \$89 Quicksoft Inc. 219 First North #224 Seattle, WA 98109 206-282-0452

Wordplan, \$49.95 DEA Software P.O. Box 968 Fremont, CA 94537 Disk only for \$10

Table 1. User-supported word processors and where to get them.

sheet, just call it from the Wordplan script that you create. It can also read files from the PD spreadsheet, As-Easy-As, or any DIF file such as from Dbase.

Wordplan does not have an on-line help feature, but you can implement many commands through pull-down menus much like those of Ashton-Tate's Framework II. A script file lets you print out a documentation file using Wordplan. Wordplan's editor is a modified version of Microstar from the Turbo Editor Toolbox by Borland.

Most of the commands are easy to use if you understand Wordstar. Wordplan does not have a spelling checker, though you can interface it with Borland's Turbo Lightning. Though Wordplan is itself a word processor, its documentation states that it can work well with PC-Write. You are probably better off using one of the other word processors if your word-processing needs are simple. Wordplan is best left to its intended special applications and is not for the faint of heart. I'm glad that I had the chance to use Wordplan, though. Its applications are unique.

Next Month

I've covered only the more sophisticated word processors this month. Next month I'll describe a few simpler programs and survey a few word-processing support programs in the public domain. I'll even tell you about a word processor for kids.

As a convenience, I am again offering disks for 80 Micro readers. The cost is \$10 each for PC-Write, PC-Type+, and New York Word disk sets. If you send for more than one disk, just send \$5 per disk and no extra shipping. Please don't ask for anything other than what I offer. It will delay things tremendously. If you want to write me, please do so separately.

Wordplan has a limited distribution system that precludes me offering a disk, though it is on the 80 Micro BBS. You can order a disk from Public Brand Software (disk no. WP10.0) or the author for \$10

All PD software discussed in the Public Works column is available for downloading from the 80 Micro BBS for a period of time at 603-924-6985 (300/1,200 baud, 8-bit words, no parity, 1 stop bit).



Thomas Quindry has written for 80 Micro since 1980. Write Tom at 6237 Windward Drive, Burke, VA 22015. Enclose a stamped, self-addressed envelope for a reply.

The 80 Micro Disk Series



Packed with more productivity, more innovation, more programming fun than ever before!

Yes, you still get all the top-rated TRSDOS programs published each month in 80 Micro, ready-to-run on quality disks. No time-killing keyboarding, no tedious de-bugging. Just load and go!

With the NEW 80 Micro Disk Series (formerly LOAD 80), you'll find new ways to enhance your personal and business productivity. You'll get programs for dozens of innovative applications like project management, special sorting of customer files, financial analyses, graphics for reports and

studies, compiling mailing lists, critical path scheduling and more. Plus powerful utilities that help make your computer do more and run better!

You get 12 monthly disks, for just \$149.95. (Single disks cost \$17.95 each, so you save more than \$65 by subscribing now!)

Complete the coupon below, mail the card opposite, or CALL TOLL FREE 800-258-5473 (NH, 924-9471)

☐ Single disk only, \$17	-	THE 60 MICE	o Disk Series at just \$14	9.95 for 12 monthly pr	ogram uisi
☐ Payment enclosed ☐ M		□ AE			
Card#				Exp. Date	
Signature					
Name					
Address					
City			State	Zip	

Next to your computer,





nothing beats a Tandy printer





IBM® PC compatible

For the best value and selection in top-quality printers, shop your local Radio Shack Computer Center. We've got what you need, whatever your printing requirements.

Versatile business printer

The DMP 2200 (26-1279, \$1695) provides dot-matrix printing at up to 380 characters per second. Supports elongated, double-high, bold, underline, super/subscripts, italics, double strike and bit-image graphics.

Customized type styles

Use the Font Editing Packages (sold separately) to load different

type styles for print quality that rivals a daisy wheel. In the draft mode, the DMP 2110 (26-2810, \$1295) prints up to 240 characters per second.

Low-cost business printer

The DMP 430 (26-1277, \$699) allows a choice of micro, italic and double-high fonts, as well as bitimage graphics. Prints up to 180 characters per second.

Letter quality daisy-wheel printers

The DWP 520 daisy-wheel printer (26-2800, \$995) provides a clean, crisp, "electric-typewriter" look at up to 500 words per minute.

And for letter-quality printing under \$400, the DWP 230 (26-2812, \$399.95) is the clear choice.

See our complete selection of printers today. Circle 75 on Reader Service card.

Send me an RSC-17B Computer Catalog. Mail To: Radio Shack, Dept. 87-A-403A

Mail To: Radio Shack, Dept. 87-A-403A 300 One Tandy Center, Fort Worth, TX 76102

Name _____

Company

City _____

State _____ ZIF _

TANDY COMPUTERS: In Business . . . for Business™



COMPUTER CENTERS

A DIVISION OF TANDY CORPORATION

Pop-Up Printer Codes with Pro-Wam

Vour printer probably has several features that you rarely use—the ability to double-strike or emphasize characters, change fonts or font sizes, or change line spacing, for example. Printers require a sequence of control codes to perform such feats, and unless you are in Basic or using a word processor, it is difficult to send those codes to the printer.

I wanted a program that could access many of my printer's features. I wanted to select those options from TRSDOS Ready, from inside a text editor, or while using other programs. My printer-setup program should remember the codes necessary to select various printer features and let me redefine control-code sequences at any time.

This month's demonstration program comes very close to meeting those requirements and gives me a chance to discuss a number of techniques that I have not mentioned here before.


Although you can use many of the ideas in this month's program regardless of what software you own, it only runs as written with one of the most remarkable Model 4 programs I've seen: Misosys's Pro-Wam (formerly Pronto).

Pro-Wam is a set of pop-up utilities that are always available with a single keystroke. Pro-Wam allows an unlimited number of pop-up utilities, four of which you can designate to be available with two keystrokes. You can run the other utilities from disk.

Pro-Wam supports user-written, popup utilities for the assembly-language programmer. Its documentation tells you how to write your own utility applications, and this month's program demonstrates many of the necessary techniques. You can also make calls to the Pro-Wam window manager from pro-

System Requirements

Model 4, 4P, or 4D
128K RAM
Editor/assembler
(Pro-Create 4.3a or MRAS)
Available on The Disk Series
Pro-Wam



grams written in any langauge; the extensions to Basic in LS-DOS 6.3 combined with Pro-Wam make windowed Basic programs easy to write.

Pro-Wam includes a utility that makes debugging pop-up utilities easier and a file containing macro commands for all of its calls.

Designing an Application

A Pro-Wam pop-up utility (or application, as it is called in the program's documentation) must conform to the following restrictions.

- You must write the program to run in the memory area from 2800–2FFF hexadecimal (hex).
- The program can use any or all of the memory space from 2400-2FFF hex as data space.
- You must save the program as a coreimage file, which means that it cannot contain any TRSDOS loading codes.
- The first sector of the program file must contain specific information as a Pro-Wam signature.

The Pro-Create or MRAS assemblers can handle most of these details without difficulty. Program Listing 1 begins by loading the macro commands in both MACLIB/ASM (see Program Listing 2) and Pro-Wam's Window/Mac file. It then establishes four constants that define its

screen window. SRow and SCOL are the starting row and column for the window; NRow and NCOL define the window's total number of rows and columns.

Pro-Wam places a border around the window when it loads. It saves the screen contents and restores the screen and cursor position when it is finished.

The OPTION CI in line 320 of Listing 1 tells the assembler to create a core-image file (the same as a memory dump) instead of a normal CMD file with loader information. You could specify the assembler switch when assembling the program, but it is easier to place the command in the source code than to remember to specify it each time you assemble the listing.

Erases Old Responses

A program-specific macro command that prints prompts and information in the application window starts in line 340. Each time you invoke the macro, it copies a buffer from memory to the screen, erasing old prompts and responses, then prints the new information on a specified line of the application window.

The program starts on line 430 with the definition of the information sector that must precede every Pro-Wam application. The first six characters must be PRONTO, the next 12 characters must describe the application for the Pro-Wam

THE NEXT STEP

main menu, and the 19th character must be ETX, which terminates strings in TRSDOS programs when you do not want a carriage return. The program reserves the following 205 bytes for expansion. You can use the final 32 bytes of the information sector for invisible copyright information.

The program asks the assembler to use the expression in line 460 to count the bytes that should remain blank. In English, that line says, "Pad the rest of this sector with bytes of zero." The expression following the DC (define constant bytes) pseudo-op is not difficult to understand. It uses the current value of the program counter (the dollar sign [\$]) and simple arithmetic to determine how many more bytes there are in the first sector of the program. Line 500 tests the result to ensure that the expression was written and evaluated correctly.

The program code begins at the Start label in line 530. The @WCreate macro creates a Pro-Wam window, if possible. If it cannot create the window, the program sends a beep through the Model 4's builtin speaker and then exits. Otherwise, it calls the Make_DISP routine to create a copy of the window display in a memory buffer. Any time the program wants to clear prompts or user responses from the screen, it simply asks Pro-Wam to copy that buffer back into its screen window.

The Main Loop Repeats Indefinitely

The main loop, lines 630-730, repeats until you want to exit the program. The loop asks you to press either "P" to send a control sequence to the printer or "D" to define or redefine a control sequence. If you press break while that prompt is on the screen, the program ends and writes any new information back to its file on disk. The main loop repeats indefinitely until you press break.

The rest of the program is a series of subroutines that perform most of the work. The first routine, Make_DISP, converts the current information in the program's data sector into a form that you can understand. Listing 1 stores information for 15 printer-control sequences. It stores each sequence as a nine-character identification string followed by up to eight bytes of printer-control characters.

Make_DISP creates a window buffer in memory, clears the buffer, and places each of the printer codes in that buffer. As it does so, it must change the bytes of the printer-control sequences into ASCII hex values. Invoking the @HEX8 supervisory call (SVC) in TRSDOS makes the job easier.

The program calls the second routine, Close, when you want to exit. Close's first job is determining whether you re-

```
Program Listing 1: Printer-setup application.
```

```
00100 ;=====
                _______
00110 ;
             Printer Setup Application
Requires PRO-WAM (formerly PRO-NTO) from Misosys
00130
             Assemble as PRSET/APP
00140 :
00150 ;====
                                      ______
00160 ;
00170 *LIST OFF
00180 *GET P
                MACLIB/ASM
                                            ; See Listing 2
                                            ;Supplied with PRO-WAM
00190 *GET
                WINDOW/MAC
00200 *LIST ON
00220 SROW
                EOU
                         3
00230 SCOL
                EQU
                         43
00240 NROW
                EOU
                         20
00250 NCOL
                         36
                EQU
00260
00260 ;
00270 EREOL
                EOU
                         1EH
                                            :Erase to end of line
00280 ETX
                         13
00290 CR
                EOU
00310 ;
                OPTION
                         CI
                                            ; Must be core image file
00330 :
00340 PROMPT
                MACRO
                         #STRING, #ROW
                                            ;; Print prompt on bottom line
00350
                @WB2W
                         DISP
                                            ;;Reset screen
                ewscur
                         #ROW, Ø
                                            :: Cursor to beginning of bottom row
00360
00370
                @WDSPLY #STRING
                                            ;;Display string
00380
                ENDM
00400
          Information Sector
00420
                ORG
                                                      :Forces start to 2800h
00440
00450
                          'PRONTO'
                                                      :File identifier
                DB
                          'Set Printer ', ETX
                DB
00460
                         .HIGH.$<8-$+256.0
                                                      ; Pad sector
                DC
00470
          Application starts here at 2800h
00480
00490
                IFNE
                         $,2800H
00500
                                                      ;Test location
                            Something is wrong in the header
00510
                  ERR
                ENDIF
00530 START:
                @WCREAT SROW, SCOL, NROW, NCOL
00550
                         Z, OKAY
                                                      ; If window open, begin
                @@SOUND 8,2
                                                     ;Beep if not okay
; and leave
00560
                                                      :Create window display in memory
                         MAKE DISP
00580 OKAY
                CALL
00590
00600
          Loop until user
          wants out
00620
00630 LOOP
                PROMPT
                         MAIN_PRMT.NROW-1
                                                      ;Get user response
                @WKEYIN Ø
                                                      ;Get user response
                         C, CLOSE
                                                      ;Go if (Break) pressed
00650
                JP
                AND
                         ØDFH
                                                      ;For letter to upper case
00670
                PUSH
                                                     ;Save response
;Send string to printer?
                         AF P
                CALL
                         Z.PRINT
                                                     ;Yes -- go
;Recover response
00690
                POP
                          'D'
99719
                CP
                                                      ;Define a string?
00720
                CALL
                         Z,S_DEFINE
                                                      ; Yes -- qo
99739
                JR
                         LOOP
                                                      ;Loop back and do it again
00740
00753
          Create ASCII display
00760
          in PRO-WAM data area
00780 MAKE_DISP:
                MEMFILL DISP, NROW*NCOL, ' '
                                                      ;Clear display area
                                                     ;Move title to display area
;HL ==> 3rd line
;DE ==> definitions
aasaa
                MOVE
                         TITLE, DISP, TITLE_LEN
HL, NCOL*2+DISP
00820
                         DE, DEF
                         B. 15
                                                      :15 strings max
99849
                                                      ;ID of first string
                LD
00850
                LD
                         (LETTRS) . A
                                                      :Save it
00860 MD_1
                PUSH
                                                      ;Keep loop counter
                         A, (LETTR$)
                                                     ;Get display letter
;Place the ID character
00870
                LD
                         (HL) A
                                                      :Next ID character
00890
                TNC
                          (LETTR$),A
                                                      ;Save next one
00910
                TNC
                                                      ;Point to next location
00920
                         (HL),'.'
                LD
                                                     ;Print period
;Point to next
00930
                INC
00940
                INC
                                                     ;Skip a space
;Exchange pointers
00950
                         DE . HL
00960
                LD
                         BC.9
                                                      :Nine characters in name
00970
                LDIR
                                                      ; Move nine characters
                         DE. HL
                                                     ;HL==> next space, DE==> hex data
;8 data bytes
00980
                EX
                                                     ;Save loop counter
;Skip a space
01000 MD_2
                PUSH
                         BC
                                                     ;Get data byte
;Is it 0?
;Yes -- go
;Else byte in C
                         A. (DE)
01020
                LD
                         Z , MD_4
01040
                JR
01060
                @@HEX8
                                                      Convert to ASCII hex
01070 MD 3
                POP
                                                      ;Get loop counter
                                                                          Listing 1 continued
```

```
Listing 1 continued
 91989
                                                                 ;Bump pointer
;Loop for all bytes
;Complete outer loo
                     DJNZ
                                MD 2
 01090
 01100
01110 MD_4
                                MD_5
                     JR
                     INC
                                HL
                                                                 ; If 0, leave spaces
 01120
                                HL
 01130
                                                                 ;Complete inner loop
;Recover outer loop counter
                     JR
                                MD_3
         MD 5
                                MD 1
                                                                 ;And loop for all strings
;Display is complete
 01150
                     DJNZ
                     RET
 01170
 01180
              Close up, save new definitions
 01190
         CLOSE
                                A. (CHANGES)
 01200
                     LD
                                                                 ;Did user change definitions?
                                                                 ;Test if 0
  01210
                     OR
                                                                 ;No changes made -- leave program
;Set up FCB for open
;Handle OPEN directly to trap
 01220
                                Z,CL 3
                     JR
                     BAFSPEC PROGNAM, FCB
 01230
  01240
                     DEFINE
                                                                                  directly to trap
 01250
                                                                 ;Point to buffer
;LRL = 256
                     LD
                                HL. DEF
 01260
                     LD
                                                                 ;Open the file
;Go if no error
 01270
                     SVC
                                MOPEN
                     JR
                                Z,CL_2
                                                                 ;Else report error
;Wait for keystroke
;Main loop if <Break>
 91298
                     PROMPT
                                OPEN_ERR, NROW-2
                     EWKEYIN
         CL 1
 01310
                     JP
                                C. LOOP
 01320
                     AND
                                ØDFH
                                                                 ;Else make upper-case
;Don't quit?
 01330
01340
                     CP
JP
                                "N"
                               Z,LOOP
                                                                    Then return to main loop
                                                                 ;Do quit?
;Then leave program
;Else wait for correct response
 01350
                     CP
                                Z,CL_3
 01360
                     JR
 01380 CL_2
                     @@POSN
                               DATSEC
                                                                 Position record to data
                     @@WRITE
                                                                 :Write data to disk
                                                                 ;Close the file
;Close our window
                     @@CLOSE
 01400
 01410
01420
         CL 3
                     @WCLOSE
                     RET
                                                                 ;We're done -- control to PRO-WAM
 01430
             Send existing setup string to printer
 01440
 01450
 01460
                    PROMPT
                                                                 ;Display prompt message
;Pick line to print
;Go if <Break>
 01470 PRINT
                               PRT PRMT, NROW-1
                     CALL
                                SELECT_LINE
 01490
                     RET
                                SEND PRT
                                                                 ; Else send value to printer
 01510
                     RET
 01520
 01530
             Select line for printing or definition. Return line ID (0 - 14) in A or CF if <Break>
 91559
 91579
         SELECT_LINE:
 01580
                     @WKEYIN Ø
                                                                 :Get one keystroke
 01590
                     RET
                               C
ODPH
                                                                 ;Return if (Break)
                                                                 ;Force to upper-case
;Loop if too low
 01600
                     AND
                     IFLT_JR 'A', SELECT_LINE IFGE_JR 'P', SELECT_LINE
 01610
                                                                 ;Loop if too high
;Make relative to
 01620
 01640
                    RET
 01650
 91669
             Send setup string to printer
 01670
 01680
         SEND_PRT:
                     @@MUL16 17,A
                                                                ;Offset to selected string
 01690
 81788
                               H,L
                                                                ;Shift result
                     LD
 01710
                     I.D
                               L,A
                                                                   to HL
                                                                 ; DE ==> definitions
;HL ==> beginning of ID string
                     LD
                                DE, DEF
 01730
                     ADD
                                HL, DE
 01740
01750
                     LD
                               DE.9
                                                                ;Characters in string
;HL ==> first data byte
                     ADD
                                HL
                                   DE
                                                                ;Up to 8 data bytes
;Get byte
 01760
                     LD
                               B. 8
                     LD
                                A, (HL)
 01770 SP_1
                     INC
                                HL
                                                                ;Bump pointer
;Is it 0?
 01780
 01790
                    OR
                               A
Z,SP_2
 01800
                     JR
                                                                ;Go if yes
 01810
                     MAPRT
                                                                ;Else print character
;Loop for all characters
                                SP_1
 01820 SP_2
                     DJNZ
 01830
                    RET
 01840
 91859
             Define new setup string
 01860
 01870 S_DEFINE:
                    PROMPT SEL_PRMT1, NROW-2
 01880
                                                                :Ask for string to define
                                SELECT_LINE
                                                                 ;Get user response
 01890
                     CALL
 01900
                    RET
                                                                 :Return on (Break)
                                                                 ; Save response
                                (LETTR$),A
                     PROMPT
                               SEL PRMT2, NROW-2
 01920
                                                                 ; Ask for ID
                                                                 ;Clear ID buffer
                     MEMFILL IDBUF, 10, CR
 01940
                     @WKEYIN 9,IDBUF
JR C,S_DEFINE
                                                                ;Get input
;Loop back if <Break>
                                                                ;Get number of characters
;Were there any?
;Loop if none
;Clear input buf
 01960
                    I.D
                               A.B
                    OR
 01980
                    JR
                                Z.S DEFINE
                    MEMFILL HEXBUF, 24, 0
                                                                ;Ask for hex bytes
;Get input
 02000
                     PROMPT
                               SEL_PRMT3, NROW-2
 02010
                     @WKEYIN 23, HEXBUF
                                                                ;Loop back if (Break)
;Get length of input
                               C,S_DEFINE
 82828
                     JP
 02030
                    LD
                               A.B
                    OR
                                                                 ; Was there any?
 02040
                                Z.S DEFINE
 02050
                     JP
                                                                 : No -
                                                                         loop back
                                                                ;Test input
                                                                                         Listing 1 continued
```

defined any of the control sequences or added any new ones. If you made any changes, Close saves the printer-control data back to disk before returning to Pro-Wam and the program that was running when you invoked Pro-Wam.

There are two ways to save the control information, and each represents a trade-off. If the program saves new control data to a data file, it has to pause to find and read that file whenever you invoke it. On a floppy-based system, you must leave the disk containing the data file in one of the drives at all times.

An Option to Save

In the other option the program saves the control-sequence data into itself, so that the data is available whenever you load the program. This is a handy technique to use for short utilities that need little user-defined data. The program opens the disk copy of itself, finds the appropriate sector, and writes one or more records into itself. The program never loses time looking for a data file when you invoke it, and there is little chance that the data and program files will end up on separate disks.

The disadvantage of the latter method is that Pro-Wam keeps a copy of four selected programs in a back bank of memory. It cannot know that you altered one of those programs, and will not display the new data the next time that you invoke it, unless you reboot or remove Pro-Wam from memory and reload it with its associated files.


Speedy but Inconvenient

In spite of this inconvenience, I chose to implement Listing 1 using the second strategy. I found that once I defined my printer's most common control sequences, I seldom wanted to alter any of them. I appreciate the program's speed (it never has to look for a data file) more than I dislike the inconvenience of having to remove and reload Pro-Wam whenever I want to preserve new control-sequence definitions.

If the Close routine finds that you changed any definitions, it trys to open PRSET/APP (the filespec I use for the application program). If the open operation is successful, Close positions the file to the last sector (which is where the data resides) and writes the new contents of the data area into that sector. If the open operation is unsuccessful, the program reports an error and lets you decide whether to end anyway or return to the main loop (and perhaps load the disk containing PRSET/APP into one of the computer's drives). The program ends by telling Pro-Wam to close its window and then returns control to Pro-Wam.

Most of the remaining routines are

4, 4D, 4P



XLR8er ™ provides the answers

Model 4 System Owners: Extend the life of your Model 4 with the XLR8 upgrade board.

Q. What is an XLR8er?

The XLR8er is a printed circuit expansion card that plugs into your Model 4 where the Z-80 processor chip is now. The XLR8er comes complete with the HD64180 microprocessor (z80 compatible and 8 MHz z80 performance), 256 KB of RAM and utility software for your system, plus full one-year warranty.

Mhat software does the XLR8er

A. The XLR8er is supplied with utilities for one operating system, TRSDOS, CP/M, or LDOS. Additional utility disks are available.

What is involved in installing the XLR8er?

A. Installation is limited to simple plug-in connection and system disassembly and assembly.

\$299.95

Texas residence add sales tax. VISA/MasterCard accepted.

Order today. It is so easy. Just call our 24 hour numbers—800-835-2246 ext. 202 or 800-362-2421 ext. 202 (Kansas residents) and ask for the XLR8 upgrade board.

Owners Manual \$10.00 (full credit toward purchase of XLR8).

H. I. Tech, Inc.

P. O. Box 25404 Houston, Texas 77265 713/682-7317



*Plus shipping and handling. Add applicable tax.

THE NEXT STEP

	continued			
02070		JP	C,S_DEFINE	;Loop back if not okay
02080		CALL		; Move id and hex string
02090 02100			MAKE_DISP A,-1	;Make new display ;Value for change flag
02110			(CHANGE\$),A	Store flag to show change
02120		RET		;And return
02140		hex inpu	at for correct form	
	HEXTEST		HL, HEXBUF	;HL ==> hex input buffer
02170	HEX_1	CALL	ISHEX	; Is first character hex?
Ø218Ø Ø219Ø		RET CALL	C ISHEX	;Go if not ;Is next character hex?
02200		RET	C	Go if not
02210		LD		Get next character
02220 02230		CALL CALL	CR, HEXOKAY ISSEP	;Go if at end ;Valid separator?
02240		RET	C	Go if not
02250			A, (HL)	Get next character
02260 02270	HEXOKAY		CR, HEX_1 A	;Loop back if not end ;Clear carry flag
02280		RET		;We're done
02290 02300	Tect	if (HT.)	is a valid hex	
02310	; char	acter.	is a valid nex	
02320	; If o	kay re	eset CF and inc HL	
02330	; If n	ot okay,	set CF	
02350	ISHEX	LD	A, (HL)	;get character
02360		CP	101	;Special chacter? ;Go if < 0
02370 02380		RET CP	191+1	;Go if < 0 ;Is it decimal?
02390		JR	C, ISH_OK	;Go if okay
02400			ØDFH	;Force a-f to A-F
02410		LD CP	(HL),A	;And put it back ;Between 3B and 40 hex?
02430		RET	C	;Yes go
02440		CP		;Above 46h? ;Reverse carry flag
02460	ISH_OK	RET		Return if error
02470		INC		;Else bump pointer
02480	;	RET		;And return
02500	Test	if (HL)	is a valid	
02510	; sepa	rator ('	is a valid ' <-> '/')	
02520	; Set	CF is not	CF, and inc HL	
	;			
02550	ISSEP	LD		;Get character
02560 02570		CP RET		:Too low? :Yes return
02580		CP		
			/ +1	;Over the top?
02590		CCF	,	:Reverse carry flag
02590 02600		CCF RET	С	Reverse carry flag; Return if not legal
02590		CCF RET LD	C A,	Reverse carry flag Return if not legal Else get a space Convert character to space
02590 02600 02610 02620 02630		CCF RET LD LD INC	C A,	Reverse carry flag; Return if not legal; Else get a space
02590 02600 02610 02620 02630 02640		CCF RET LD LD INC RET	C A,'' (HL),A	Reverse carry flag Return if not legal Else get a space Convert character to space
02590 02600 02610 02620 02630 02640 02650 02660	; Move	CCF RET LD LD INC RET	C A,'' (HL),A	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char.
02590 02600 02610 02620 02630 02640 02650 02660 02670	; Move	CCF RET LD LD INC RET	C A,'' (HL),A	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char.
02590 02600 02610 02620 02630 02640 02650 02660 02670 02680 02690	; Move ; Move	CCF RET LD LD INC RET 	C A,'' (HL),A HL r data into the DEF area	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer
02590 02600 02610 02620 02630 02640 02650 02660 02670 02680 02690 02700	; Move ;XFER_ST	CCF RET LD LD INC RET new uses	C A,' ' (HL),A HL r data into the DEF area HL,IDBUF HL	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address
02590 02600 02610 02620 02630 02640 02650 02660 02670 02680 02700 02710	; Move ; XFER_ST	CCF RET LD INC RET new user RING: LD PUSH LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string
02590 02600 02610 02620 02630 02640 02650 02660 02660 02710 02710 02710	; Move; XFER_ST	CCF RET LD LD INC RET new user LD LD PUSH LD IFNE_JR	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR
02590 02600 02610 02620 02630 02650 02660 02670 02680 02710 02710 02720 02730 02740	; Move ; Move XFER_ST	CCF RET LD LD INC RET RET RING: LD PUSH LD LD LD LFNE_JR LD	C A,' ' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),' '	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '
02590 02600 02610 02620 02630 02650 02660 02670 02680 02710 02710 02720 02730 02740	; Move; XFER_ST	CCF RET LD LD INC RET new user LD LD PUSH LD IFNE_JR	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR
02590 02600 02620 02630 02640 02660 02660 02670 02710 02710 02710 02710 02750 02770 02770 02770	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD INC RET 	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,KFER_2 (HL),' HL XFER_1 A,(LETTRS)	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with
02590 02600 02620 02620 02630 02650 02650 02650 02670 02770 02770 02770 02770 02770 02770	; Move ; Move ; Move XFER_ST	CCF RET LD LD INC RET NEW USE: LD PUSH LD LD IFNE_JR LD IFNE_JR LD LD LD LD LD LD LD LD LD LD LD LD LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length
02590 02600 02620 02630 02640 02660 02660 02670 02710 02710 02710 02710 02750 02770 02770 02770	; Move; XFER_ST. XFER_1 XFER_2	CCF RET LD LD INC RET 	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,KFER_2 (HL),' HL XFER_1 A,(LETTRS)	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result t the
02590 02600 02610 02620 02630 02660 02660 02670 02710 02710 02710 02750 02770 02780 02780 02780 02780	; Move ; Move ; Move XFER_ST	CCF RET LD LD INC RET NEW USE! LD PUSH LD LD IFNE_JR LD INC DJNZ LD DJNZ LD LD LD LD LD LD LD LD LD LD LD LD LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTRS) 17,A H,L L,A DE,DEF	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result t HL DE ==> definitions area
02590 02600 02620 02630 02630 02650 02650 02650 02670 02770 02770 02770 02770 02780 02780 02780 02780 02780 02800 02820	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD LD RET RING: LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTRS) 17,A H,L L,A DE,DEF HL,DE	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space
02590 02600 02620 02630 02630 02660 02660 02670 02710 02710 02710 02750 02770 02780 02780 02780 02780	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD INC RET NEW USE! LD PUSH LD LD IFNE_JR LD INC DJNZ LD DJNZ LD LD LD LD LD LD LD LD LD LD LD LD LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTRS) 17,A H,L L,A DE,DEF	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string
02590 02610 026130 02630 02650 02650 02650 02650 02670 02772 02774 02774 02776 02776 02776 02776 02776 02776 02776 02783 02783 0283 0283 0283 0283 0283 0283 0283 02	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD RET RING: LD PUSH LD LD LD LD INC DJNZ LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer
025900 0261900 026300 0266300 0266700 0266700 0226700 0227720 0227720 0227760 0227760 0227760 0227760 0227840 022840 022840 022840 022840 022840 022840 022840 022840	; Move ; XFER_ST XFER_1 XFER_2	CCF RET LD LD LD INC RET NEW USE: LD PUSH LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all
025999 026190 026130 026230 02630 026590 026790 026790 02770 027720 027720 027720 027720 02780 02780 02880 0000 0000 0000 0000 0000 0000 0000 0000	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD INC RET RING: LD PUSH LD LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer
025990 02610 02612 02628 02638 02640 02659 02669 02678 02678 02778 02778 02774 02774 02774 02774 02774 02778 027888 0278	; Move ; Move ; Move ; Move ; Move XFER_ST	CCF RET LD LD LD INC RET NEW USER LD PUSH LD LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF A,(HL)	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character
025990 026120 026120 026120 02630 02630 02630 02650 02672 02720 02720 02720 02720 02730 02720 02730 02	; Move; Move; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD RET RING: LD PUSH LD LD INC DJNZ LD	C A,' ' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,KFER_2 (HL),' ' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF A,(HL) HL	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer
025990 02616 026280 026380 026380 026580 026580 02670 02680 027740 027740 027740 027740 02780 02780 02780 02780 02780 02780 0280 02880 02880 02880 02880 02880 0280 0280 02800 02800 02800 02800	; Move ; Move ; Move ; Move XFER_ST	CCF RET LD LD LD INC RET RET LD PUSH LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTRS) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL BC,9 HL BR,8 HL,HEXBUF A,(HL) HL '',XFER_3 CR,XFER_4	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result To HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Get next if a space Go if at end
025990 026120 026120 026120 02630 02630 02630 02650 02672 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02720 02830 02	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD RET RING: LLD LD	C A,' ' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),' ' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF A,(HL) HL ' ',XFER_3 CR,XFER_4 BC CR	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Rump pointer Get next if a space Go if at end Else save counter
025990 02616 026280 026380 026380 026580 026580 02670 02680 027740 027740 027740 027740 02780 02780 02780 02780 02780 02780 0280 02880 02880 02880 02880 02880 0280 0280 02800 02800 02800 02800	; Move; YFER_ST. XFER_1 XFER_2 XFER_3	CCF RET LD LD LD INC RET RET LD PUSH LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTRS) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL BC,9 HL BR,8 HL,HEXBUF A,(HL) HL '',XFER_3 CR,XFER_4	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result To HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Get next if a space Go if at end
025990 026130 026130 026230 02630 02640 02650 02670 02670 02770 02770 02770 02770 02770 02770 02770 02770 02780 02770 02780 0280 02	; Move ; Move ; XFER_ST. XFER_1 XFER_2	CCF RET LD LD LD INC RET RING: LD PUSH LD LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL HL,HEXBUF A,(HL) HL ',XFER_3 CR,XFER_4 BC '0' 10 C,\$+4	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Bump pointer Get next if a space Go if at end Else save counter Convert to binary Is it 0 - 9 ? Yes skip next instruction
025990 02610 02612 0262 0263 0263 0263 0263 0263 0265 02660 0267 0277 0277 0277 0277 0277 027	; Move ; Move ; Move ; Move ; Move XFER_ST	CCF RET LD LD LD INC RET RING: LD PUSH LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF A,(HL) HL '',XFER_3 CR,XFER_4 BC ''0' 10 C,\$+4 7	;Reverse carry flag ;Return if not legal ;Else get a space ;Convert character to space ;Point to ASCII buffer ;Save address ;Size of ID string ;Get character ;Go if not CR ;Else replace with '' ;Point to next character ;Loop for all 9 characters ;Get string we're working with ;Multiply by entry length ;Shift result ; to HL ;DE ==> definitions area ;HL ==> string space ;Move pointer to DE ;Size of ID string ;Get pointer ;Move it all ;Max number of entries ;HL ==> hex input buffer ;Get character ;Bump pointer ;Get next if a space ;Go if at end ;Else save counter ;Convert to binary ;Is it 0 - 9 ? ;Yes skip next instruction ;Else convert A - P
025990 026130 026130 026230 02630 02640 02650 02670 02670 02770 02770 02770 02770 02770 02770 02770 02770 02780 02770 02780 0280 02	; Move ; Move ; YFER_ST. XFER_1 XFER_2	CCF RET LD LD LD INC RET RING: LD PUSH LD LD IFNE_JR LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL HL,HEXBUF A,(HL) HL ',XFER_3 CR,XFER_4 BC '0' 10 C,\$+4	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with '' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Bump pointer Get next if a space Go if at end Else save counter Convert to binary Is it 0 - 9 ? Yes skip next instruction
025900000000000000000000000000000000000	; Move; YFER_ST. XFER_1 XFER_2 XFER_3	CCF RET LD LD LD RET RING: LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL BC,9 HL HL HL '',XFER_3 CR,XFER_4 BC ''g' 10 C,\$+4 7 A A A	;Reverse carry flag ;Return if not legal ;Else get a space ;Convert character to space ;Point to ASCII buffer ;Save address ;Size of ID string ;Get character ;Go if not CR ;Else replace with '' ;Point to next character ;Loop for all 9 characters ;Get string we're working with ;Multiply by entry length ;Shift result ; to HL ;DE ==> definitions area ;HL ==> string space ;Move pointer to DE ;Size of ID string ;Get pointer ;Move it all ;Max number of entries ;HL ==> hex input buffer ;Get character ;Bump pointer ;Get next if a space ;Go if at end ;Else save counter ;Convert to binary ;Is it 0 - 9 ? ;Yes skip next instruction ;Else convert A - P
025990 026120 026120 026120 02623 02630 02630 026530 026530 026530 02672 02720 02720 02720 02730 02730 02730 02730 02730 02730 028300 028300 00830 008300 008300 008300 008300 008300 008300 008300 008300 008300 0	; Move ;	CCF RET LD LD LD RET RING: LLD LD	C A,' ' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,KFER_2 (HL),' ' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL B,8 HL,HEXBUF A,(HL) HL ' ',XFER_3 CR,XFER_4 BC 'g' 10 C,\$+4 7 A A A A	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Sump pointer Get next if a space Go if at end Else save counter Convert to binary Is it 0 - 9? Yes skip next instruction Else convert A - P Multiply by 16
025900000000000000000000000000000000000	; Move; YFER_ST. XFER_1 XFER_2 XFER_3	CCF RET LD LD LD RET RING: LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DE DE,HL BC,9 HL BC,9 HL HL HL '',XFER_3 CR,XFER_4 BC ''g' 10 C,\$+4 7 A A A	;Reverse carry flag ;Return if not legal ;Else get a space ;Convert character to space ;Point to ASCII buffer ;Save address ;Size of ID string ;Get character ;Go if not CR ;Else replace with '' ;Point to next character ;Loop for all 9 characters ;Get string we're working with ;Multiply by entry length ;Shift result ; to HL ;DE ==> definitions area ;HL ==> string space ;Move pointer to DE ;Size of ID string ;Get pointer ;Move it all ;Max number of entries ;HL ==> hex input buffer ;Get character ;Bump pointer ;Get next if a space ;Go if at end ;Else save counter ;Convert to binary ;Is it 0 - 9 ? ;Yes skip next instruction ;Else convert A - P
025990 026130 026230 026230 026400 026530 026500 026500 026700 02700 027700 027700 027700 027700 027700 027700 027700 027700 027700 027800 028800	; Move; Move; XFER_ST. XFER_1 XFER_2 XFER_3	CCF RET LD LD LD INC RET RING: LD PUSH LD	C A,'' (HL),A HL r data into the DEF area HL,IDBUF HL B,9 A,(HL) CR,XFER_2 (HL),'' HL XFER_1 A,(LETTR\$) 17,A H,L L,A DE,DEF HL,DEF DE,HL BC,9 HL HL,HEXBUF A,(HL) HL '',XFER_3 CR,XFER_4 BC '0' 10 C,\$+4 7 A A A A A A C,A	Reverse carry flag Return if not legal Else get a space Convert character to space Point to next char. Point to ASCII buffer Save address Size of ID string Get character Go if not CR Else replace with ' Point to next character Loop for all 9 characters Get string we're working with Multiply by entry length Shift result to HL DE ==> definitions area HL ==> string space Move pointer to DE Size of ID string Get pointer Move it all Max number of entries HL ==> hex input buffer Get character Bump pointer Get next if a space Go if at end Else save counter Convert to binary Is it 0 - 9 ? Yes skip next instruction Else convert A - F Multiply by 16

short and easy to understand. Print (lines 1470–1510) asks which control sequence you want to print and then calls a second subroutine (Select_Line) to send that sequence to the printer.

Select_Line waits for you to type a character that selects one of the 15 possible printer codes and then returns that value to the routine that called it. Another subroutine, Send_PRT, finds the selected printer-control bytes in memory and sends them to the printer, skipping over any zero bytes in the process.

The S_Define routine lets you define a control sequence. S_Define asks you which of the 15 sequences you want redefined and prompts for both a nine-character title and eight hex bytes. You type in each byte as two hex digits followed by a space or other separator. (The legal separators are any ASCII characters less than zero—the same separators that TRSDOS allows for a log-on date.)

After you enter the new information, S_Define calls Make_Disp to create a new display buffer in memory, and sets the Change\$ flag byte to indicate that you made a change. If you press break to avoid defining a new control sequence, you will not alter the display buffer or the Change\$ byte.

S_Define calls a routine called Hextest to validate your input. Hextest, which calls two shorter routines, scans through the list of control bytes that you typed in and verifies that each is either a valid hex digit or a valid separator. If it finds an invalid character, Hextest returns with the carry flag set to indicate an operator error.

The last long routine, XFER_String, stores your new definition in the data area in a form that you can copy back to disk. The only difficult part of this routine is the code that converts ASCII hex into bytes (TRSDOS has no SVC to make the conversion). When the XFER_String routine finds the carriage return at the end of your input, it pads the remainder of the identification string with spaces and the remainder of the printer-control sequence with zero bytes.

The Data Sections

Pro-Wam's set of macros includes a command called \$DS. \$DS defines space inside the data area from 2700–27FF hex. Listing 1, however, requires more data space than that. The label that \$DS uses, Data\$, intializes to the very beginning of the data area (2400 hex).

The \$DS macro assigns each of the temporary values space in the data area. At the end of that data section, it checks Data\$ to ensure that the program has not overflowed the data area.

The second set of data definitions includes various messages and the

A GAME THAT TEACHES LOTUS 1-2-3... REALLY!

Templetes of Doom is a unique computer program that makes a game out of learning. It is a James Bond satire that is fun for all levels of spreadsheet users. It teaches with puzzles that require the use of spreadsheet commands and formulas. There are four levels of help available, but at the price of penalty points. The game can be played alone or used as a classroom supplements. Lotus Magazine called it "truly enjoyable and very funny".

Site license packages available for classroom instructons. It costs \$49.97 plus \$2.50 shipping (add 6.5% tax if from California). Thirty day money back guarantee. Pay by check, PO, VISA or MasterCard. May also be ordered under the name "Learning Templates". Lotus version also runs on VP-planner, The Twin and most "work-a-likes". Versions available for Excel, VIP Professional and SuperCalc4. Call (415) 952-2375 or write Solar Systems Software, 8105 Shelter Creek, San Bruno,CA 94066. Please Specify your spreadsheet and computer.





You have a large technical audience that speaks English and is in need of the kind of microcomputer information that **CW Communications/Peterborough** provides.

Provide your audience with the magazines they need and make money at the same time. For details on selling 80 Micro, inCider, AmigaWorld, and RUN contact:

Marjorie Rubin-Acct. Executive Boarts International
747 3rd Avenue New York, NY 10017
(212) 688-2778

Circle 452 on Reader Service card.

You already own half of a great printer Now



Now for \$79.95 you can own the rest. You see, today's new dot matrix printers offer a lot more.

Like an NLQ mode that makes their letters print almost as sharp as a daisy wheel. And mode switching at the touch of a button in over 160 styles. But now, a Dots-Perfect upgrade kit will make your printer work like the new models in minutes— at a fraction of their cost.

And FX, JX and MX models will print the IBM character set, too.

So, call now and use your Visa, MasterCard, or AmerEx. Don't replace your printer, upgrade it!

1-800-368-7737

(Anywhere in the United States or Canada)



Dots-Perfect

letter without Dots-Perfect



(714) 945-5600

& Dresselhaus

8560 Vineyard Ave., Ste. 405, Rancho Cucamonga, CA 91730

An upgrade kit for EPSON FX, JX, RX, & MX printers

NEW from MICROLITE CORPORATION SWAP-6000 Memory Expansion

Your users deserve Superior Performance!

Many items to increase productivity with your TANDY 6000 and other UNIX/XENIX Computers, including:

- PBG 200/300 Graphics by Pacific Basin Graphics
- XROFF Desktop Publishing by Image Network
- TERM Communications by Century Software
- Laser Printers...Plotters
 Hard Disk Upgrades...
 High Speed Modems...
 Graphics Terminals
 ...and more!

Write or call Today... for our full line brochure and more details on the new Swap-6000.

MICROLITE

Department M 1021 Sutherland Street Pittsburgh, PA 15204 (412) 771-4901

Zij
11



January 1984: Tandy's Model 2000 and an MS-DOS overview; also, an Assembly language tutorial.

February 1984: The Creator—new and improved data base management, also, tabulate and analyze opinion polls.

March 1984: Hinrich's word processor, a III to 4 conversion program, and a Machine-language arcade game.

April 1984: CP/M digest, Model III/4 conversion program, pie and bar chart program, and new Scripsit characters.

May 1984: Telecommunications special, VisiCalc enhancements, Pascal, and a program that eases math anxiety.

June 1984: Tape to disk transfer program, award-winning graphics, and a business report analyzer.

July 1984: Guide to Disk Operating Systems, GW-Basic, and a Machine-language minimizer.

August 1984: Games issue, Model 4 ED-TASM, dBase II, Scripsit extras, and quality sales reports.

September 1984: Disk drive repair and maintenance and a guide to Editor/Assemblers.

October 1984: Bar codes, educational programs for teachers, and speech synthesis.

November 1984: Special utilities issue, cassette Basic enhancements, and a hybrid text editor.

December 1984: Gift guide, football strategy game, wind chill calculator, and an easy data base manager.

January 1985: Basic compiler, Scripsit enhancements, custom graphics characters, and TR\$DOS 1.3 patches.

February 1985: Line and bar graph program, CW Basic, and easy Assembly-language programming.

In each back issue, you'll also find our regular features, reviews of popular software and hardware, and dozens of useful programs that are yours for the typing

Each back issue costs \$3.50 plus \$1 shipping and handling. On orders of 10 or more back issues, there is a flat \$7.50 shipping and handling fee. Quanities are limited. Send your orders to 80 Micro, Attn: Back-Issue Orders, 80 Pine St., Peterborough, NH 03458.

THE NEXT STEP

Change\$ flag, which you must initialize to zero (no change). There is nothing unusual about these definitions.

The last section of the data area is unusual. Padding the program with zero bytes moves the program counter to an even page and sector boundary. The program calculates which will be the final sector, knowing that its first sector loads at 2700 hex. Finally, the REPT macro intializes 15 sequences of nine spaces and eight zero bytes.

This technique of defining data at the end of a program doesn't work the same way for most CMD programs. The source code has no control over the loader information required in a TRSDOS program file. The technique only works for programs that you can save as core-image files without loader codes.

Debugging and Using the Program

When you finish assembling the program, test it and, if necessary, debug it using the PRun utility included with Pro-Wam. Load Pro-Wam into memory and then enter PRUN PRSET to test the program. It should run normally, let you define printer sequences, and send those sequences to your printer.

If the program doesn't work, enter PRUN PRSET (D) to run the program under Debug.

When you are sure the program works correctly, add it to the set of four programs that Pro-Wam loads automatically. When you define a new set of control codes, the program first expects an identification string of nine or fewer characters and then expects you to enter the hex control codes in a specific form. You must follow each two-character hex byte with a space or other separator. If you omit the separators, the program rejects your entry and asks you to enter the control codes again.

If you want to remove a definition from the list, enter a single space as the identification string and 00 as the hex sequence. The program interprets this as a command to erase the previous printer code.

Pro-Wam is available from Misosys Inc., P.O. Box 239, Sterlind, VA 22170-0239, 800-647-6797, for \$59.95.■



Write Hardin Brothers at 280 N. Campus Ave., Upland, CA 91786. Enclose a stamped, self-addressed envelope for a reply. You can also contact Hardin on Compuserve's WE-SIG (PCS-117).

```
Listing 1 continued
                                                                  ;Is it 0 - 9
;Yes -- skip next
;Else convert A - F
;Merge in first byte
03060
                                10
                                C, $+4
03080
                    SUB
                                A,C
                    ADD
83188
                                                                   ;Save value
;Bump pointer
                    T.D
                                (DE) , A
03110
                    INC
                                DE
                                                                   Recover count
And loop back
Pad with 0 bytes
03120
                    POP
                                XFER_3
                    DJNZ
03140 XFER_4
03150
                    LD
                                (DE) A
                    LD
                                                                   ; Save it
                                                                   ;Bump pointer
;And loop back till done
03160
                    INC
                                XFER_4
03170
                    DJNZ
03180
03190 :---
03200 ; Data definitions
63216
03220 DATAS DEFL
                                                                  ;Set DATA$ to beginning of data area ;Put in PRO-WAM data area
                                2400H
03230 $DS
03240 DISPLEN EQU
                                NROW*NCOL
03250
                    SDS
                                DISP, DISPLEN
03260
                    SDS
                                LETTRS, 1
03270
03280
                                IDBUF, 10
                    SDS
                    SDS
                                HEXBUF.24
03290
                                DATA$,27FFH
                    IFGT
03300 OVER
                   DW
ERR
                               DATAS
                                  DATA AREA OVERFLOW
93329
                    ENDIF
03330 TITLE
                               DB
                                                    Printer Setup Application'
03340 TITLE_LEN
03350 PROGNAM
                                           $-TITLE
'PRSET/APP',0
                               DB
03360 MAIN_PRMT
                                            '<P>rinter setup or <D>efine -->',ETX
03370 PRT_PRMT
03380 SEL_PRMT1
                                           'Print which sequence (A-O) --> ',ETX 'Define which sequence (A-O) --> ',ETX
                               DB
                               DB
                                           'Description --> ',ETX
'Hex sequence --> ',CR
'Cannot open PRSET/APP to save ',LF
'new data. Quit anyway (y/n) -->',ETX
g ,No changes yet
03390 SEL_PRMT2
03400 SEL_PRMT3
                               DB
                               DB
03410 OPEN_ERR
                               DB
03420
03430 CHANGE$
                               DB
03440 ;------
03450 ; Force to next sector
03460 ;-----
03470
                    DC
                                .HIGH.$.SHL.8-$+256,0
                    IFGT
                                $,2DFFH 'Program is too long'
03490
                       ERR
03500
                    ENDIF
03510 DATSEC
03520 DEF
                                 .HIGH.S-27H
                                                                 ;Sector holding DEF
                               15
9,''
                    REPT
03530
                    DC
DC
                                                                  ;9 characters for each seq. ;8 bytes for each seq.
03540
03550
                    ENDM
03560
                    END
                                                                                                               End
```

Program Listing 2: Macro commands for Listing 1.

```
00100 :
            Macro Commands Used with PRSET/APP
00130 ; Name this file Maclib/Asm or add new
           macros to your own Maclib/Asm file
00150 ;-----
00160 ;-
            @@CLOSE -- Close a file or device

₱FCB defaults to value in DE

AF is altered
00170 :
00190 ;
00200
00210 PACLOSE MACRO
                            #FCB
00220
                  DEFINE
                             @CLOSE, 3CH
00230
                  IFEO
                            88,1
                    PUSH
00240
                               DE
                               DE, #FCB
00250
                     LD
99269
                  ENDIF
                             @CLOSE . CHECK
00280
                  IFEO
                  ENDIF
00300
00310
00320 :
00330
            DEFINE -- Define a lable unless it
00340 :
00350
                  is already defined.
00360
00370 DEFINE MACRO
                            #LABEL. #VALUE
                  IFNDEF
00390 #LABEL EOU
                            #VALUE
                  ENDIF
00410
                  ENDM
00420
00430
            @@FSPEC -- Move filespec or devspec
    to an FCB or DCB
rest Z / NZ after using!
#Fname and #FCB are both required.
If #Fname is already in HL, use HL as filename
DE is set to #FCB
AF is altered.
00440
00460
00480
00490
00500
00510
       @@FSPEC MACRO
                            #FNAME, #FCB
                  DEFINE
                            @FSPEC, 4EH
                                                                       Listing 2 continued
00530
```

FOR TRS-80 MODELS 1, 3, 4, 4P IBM PC/XT, AT&T 6300, ETC.

THREE TOUGH QUESTIONS

WITH ONE EASY ANSWER:

- 1. WHEN IS A COMPUTER
 LANGUAGE NOT A LANGUAGE?
 MMSFORTH includes DOS,
 Assembler and high level
 commands and extraordinary
 utilities, extends to become any
 other language (or application), is
 an interpreter and a compiler, and
 is remarkably fast and compact!
- SAME DISKS IN IBM PC AND TRS-80 MODEL 4?

 MMSFORTH disks run on those and Compaq, and TRS-80 Model 3, and Tandy 1200, and TRS-80 Model 1, and AT&T 6300, etc., with your choice of formats up to 200K single-sided or 400K double-sided!

2. WHICH SOFTWARE RUNS THE

3. WHO OFFERS SOURCE CODE WITH ITS LANGUAGE, UTILITIES, DATABASE, WORD PROCESSOR AND COMMUNICATIONS SOFTWARE?
Nearly all MMSFORTH software

includes source code.

MMSFORTH

All the software your computer may ever need.

The total software environment for IBM PC/XT, TRS-80 Model 1, 3, 4 and close friends.

- Personal License (required):
 MMSFORTH V2.4 System Disk \$179.95
 (TRS-80 Model 1 requires lowercase, DDEN, 1 40-track drive.)
 Personal License (additional modules):
 - Personal License (additional modules):
 FORTHCOM communications module \$49.95
 UTILITIES \$49.95
 GAMES \$9.95
 EXPERT-2 expert system \$9.95
 DATAHANDLER \$9.95
 DATAHANDLER \$9.95
 FORTHWRITE word processor \$99.95
- Corporate Site License
 Extensions from \$1,000
- Bulk Distribution . . . from \$500/50 units.
- Some recommended Forth books:
 FORTH: A TEXT & REF. (best text!) \$ 21.95
 THINKING FORTH (best on technique) . . . 16.95
 STARTING FORTH (popular text) 19.95

Shipping/handling & tax extra. No returns on software.

Ask your dealer to show you the world of
MMSFORTH, or request our free brochure.

MILLER MICROCOMPUTER SERVICES 61 Lake Shore Road, Natick, MA 01760 (617) 653-6136

```
@@MULl6 -- Multiplies 16-bit by 8-bit value
    If values aren't specified, defaults to
    values in HL and C
    Result in HL and A
                                                                                          01580 ;
Listing 2 continued
                                                                                          01590 :
       00540
                         RPHSH
                                   BC, HL
#FNAME, HL
                                                                                          01600 ;
                                                                                          01610 ;
                         IFNE$
        00560
                           LD
                                      HL, #FNAME
                                                                                          01620
                         ENDIF
                                                                                          01630 @@MUL16 MACRO
                         LD
                                   DE. #FCB
                                                                                                           DEFINE @MUL16,5BH
        00580
                                                                                          01640
                                   @FSPEC
                                                                                                           PUSH
                                                                                                                     88,2
                         RPOP
        00600
                                   HL, BC
                                                                                          01660
                                                                                                           IPEO
                                                                                                                       HL, #VAL16
A, #VAL8
                         ENDM
        00620 :
                                                                                          01680
                                                                                                             LD
        99639
                                                                                                              LD
               ; @@HEX8 -- Convert 1 byte to ASCII Hex
        00640
                                                                                          01700
                                                                                                           ENDIF
        00650 ;
                                                                                                           SVC
                                                                                                                     @MUL16
DE
                     #Byte defaults to value in C
       00660 ;
                     #Buf defaults to value in HL
                                                                                         01730
01740 ;
                                                                                                           ENDM
        00680 @@HEX8 MACRO
                                   *BYTE, *BUF
        00690
                         DEFINE
                                   @HEX8,62H
                                                                                         01750 ;
                                                                                                      @@OPEN -- Opens an existing file
        00700
                         IFGT
                                   %%,Ø
BC
                                                                                          01760 ;
                                                                                                      or device
Aborts on all errors except changed LRL
                          PUSH
        00710
                                                                                          01770 ;
                                   A, #BYTE
C, A
                                                                                          01780 ;
        00720
                                                                                                      *Buffer is required.

*LRL defaults to 0 (256)

*FCB defaults to current value in DE
        99739
                          I.D
                                                                                          01790
                         ENDIF
        00750
                         IFEO
                                   88.2
                                                                                          01810 :
                                                                                                      AF is altered.
                                   HL, #BUF
                                                                                          01830
        00770
                          LD
        00780
00790
                         ENDIF
                                                                                          01840 @@OPEN MACRO
                                                                                                                     *BUFFER, *LRL=0, *FCB
                                                                                                           DEFINE
                                   @HEX8
                                                                                                                     @OPEN, 3BH
                         SVC
                         IFGT
                                                                                                                     BC, HL
HL, #BUFFER
        99899
                                                                                         01860
                                                                                                           RPUSH
                          IFEQ
        00810
        00820
                           POP
                                    HL
                                                                                          01880
                                                                                                           LD
                                                                                                                     B, #LRL
                          ENDIF
                                                                                                           IFEQ
                                   BC
                                                                                                                       DE. #FCB
        00840
                          POP
                                                                                         01900
                                                                                                             LD
                                                                                                           ENDIF
                                                                                         01910
                                                                                                                     @OPEN
                                                                                         01920
        00860
                         ENDM
                                                                                                           SVC
                                                                                         01930
01940
                                                                                                           RPOP
JR
                                                                                                                     HL, BC
Z, $1?
        008800 ;---
       00890; IFEQ_JR -- Performs a JR if A = #Value
                                                                                         01950
                                                                                                           CP
                                                                                                                     2AH
                                                                                                                               ;; Check for LRL change
                                                                                                                     2,$1?
                                                                                         01960
                                                                                                           JR
        00910 IFEQ_JR MACRO #VALUE,#JUMF
00920 CP #VALUE
                                                                                                                     C,A
A,lAH
                                                                                                                               ;; Else error code to C
;; @ERROR SVC number
                                                                                         01970
                                                                                                           LD.
                         CP
JR
                                                                                                           LD
                                  Z, #JUMP
        99939
                                                                                         01990
                                                                                                           RST
                                                                                                                     28H
                                                                                          02000 $1?
        00950 :
                                                                                         02010
                                                                                                           ENDM
                                                                                         02020 ;
        00970 ; IFGE_JR -- Performs a JR if A >= $Value
                                                                                         02030 :-
                                                                                         02040; @@POSN -- Positions file to record number
02050; #REC defaults to value in BC
02060; #FCB defaults to value in DE
        00980
        00990 IFGE_JR MACRO #VALUE,#JUMP
                         CP
JR
                                   #VALUE
NC,#JUMP
                                                                                         02060 ;
02070 ;---
        01000
        01020
                         ENDM
                                                                                         02080 @@POSN
                                                                                                           MACRO
                                                                                                                     #REC. #FCB
                                                                                                           DEFINE
                                                                                                                     @POSN, 42H
        01040 :---
                                                                                         02100
                                                                                                           IFGT
                                                                                                                     88.0
                                                                                                                      88,2
DE
        01050; IPLT_JR -- Performs a JR if A < *Value 01060;-----
                                                                                         02110
02120
                                                                                                             PUSH
        01070 IFLT_JR MACRO #VALUE,#JUMP
                                                                                         02130
                                                                                                             LD
                                                                                                                       DE. #FCB
                         CP #VALUE
JR C,#JUMP
        01080
        91998
                                                                                         02150
                                                                                                            PUSH
        01100
                        ENDM
                                                                                                                      BC, #REC
        01110
                                                                                                           ENDIF
                                                                                         02170
                                                                                                           SVC
                                                                                                                     @POSN, CHECK
        01130 : IFNE_JR -- Performs a JR if A <> #Value
                                                                                         02190
                                                                                                           IFGT
                                                                                                                     88,0
        01150 IFNE_JR MACRO #VALUE,#JUMP
                                                                                                                      88.2
                                                                                         02210
                                                                                                            IPEO
                         CP
JR
                                   #VALUE
                                                                                         02220
                                                                                                             POP
                                   NZ, #JUMP
                                                                                                            ENDIF
        01170
                                                                                         02230
                                                                                         02240
02250
        01180
                         ENDM
                                                                                                           ENDIF
        01190 :
                                                                                                           ENDM
                                                                                         02260 ;
        01200
        01210 ; MEMFILL -- Fill memory with a constant byte
                                                                                         02270
                                                                                         02280; @@PRT -- Send a character to the printer
02290; If #CHAR not spcified, default to value in C
02380;-----
        01220 ; All three parameters required 01230 ;----
        01240 MEMFILL MACRO
                                   #ADDR, #LEN, #BYTE
                                                                                         02310 @@PRT
                                                                                                                     #CHAR
                                   BC,DE,HL
HL,#ADDR
DE,#ADDR+1
        01250
                         RPUSH
        01260
01270
                         LD
                                                                                         92329
                                                                                                           DEFINE
                                                                                                                     @PRT. 06H
                                                                                                           IFEQ
                                                                                                                     88,1
        01280
                                                                                         02340
                                                                                                            PUSH
                                                                                                                     BC
                                                                                                                     A, CHAR
        01300
                         LDTR
                                                                                         02360
                                                                                                            LD
                                                                                                                     C,A
        01310
                                   HL, DE, BC
                                                                                                           ENDIF
        01320
                         ENDM
                                                                                         02380
                                                                                                           SVC
                                                                                                                     PPRT
        01330 ;
                                                                                         02390
                                                                                                                     88,1
        01340 ;--
                                                                                         02400
                                                                                                            POP
                                                                                                                     BC
       01340;

01350; MOVE -- Moves a block of memory from

01360; #src to #dest. Block is #len bytes long.

01370; All three parameters must be specified.

01380;
                                                                                                           ENDIF
                                                                                                           ENDM
                                                                                         02430
                                                                                         02450 ;
        01390 MOVE
                         MACRO
                                   #SRC, #DEST, #LEN
                                                                                                      RPOP
                                                                                         02460 ;
                                                                                                        Pops 0 to 6 registers from the stack
                         IFLT
                                    TOO FEW PARAMETERS IN MOVE
        01410
                          ERR
                                                                                         02470
                                                                                                        Example: RPOP BC,DE,HL,IX
        01420
                         ENDIF
        01430
                                   BC.DE.HL
                         RPUSH
                                                                                         02490 RPOP
                                                                                                           MACRO
                                                                                                                     #R1, #R2, #R3, #R4, #R5, #R6
                                                                                                           IFGT
POP
        01440
01450
                         LD
IFGT
                                   BC, #LEN
#SRC, #DEST
                                                                                          02500
                                                                                                                     %%,0
#R1
                                                                                         02510
       01460
01470
                          LD
                                                                                         02520
                                                                                                           ENDIF
                                                                                         02530
                                                                                                           IFGT
        01480
                          LDIR
                                                                                         02540
                                                                                                            POP
                                                                                                                       #R2
        01490
                                                                                                           ENDIF
                         ELSE
                          LD
                                    HL, #SRC+#LEN-1
DE, #DEST+#LEN-1
                                                                                                                     %%,2
#R3
        01500
                                                                                         02560
                                                                                                           IFGT
        01510
        91529
                          LDDR
                                                                                         02580
                                                                                                           ENDIF
                         ENDIF
                                                                                         02590
                                   HL.DE.BC
                                                                                         02600
                                                                                                             POP
        01540
                         RPOP
                                                                                                                       #R4
        01550
                                                                                         02610
                                                                                                           ENDIF
        01560 :
                                                                                                           IFGT
                                                                                                                     88,4
#R5
       01570
                                                                                         02630
                                                                                                             POP
                                                                                                                                             Listing 2 continued
```

sting 2	continued			POP	BC	
82648	ENDIF	03100 03110		ENDIF		
02650		03110		ENDM		
02660	POP #R6	03120	7			
02670	ENDIF	03130	;			
02680	ENDM	03140	2	invoke a	TRSDOS 6 SVC	
02690	ENDIF ENDM	03150	7	II "Check	" is specified	, exit
02700	;	83708	7	enrough e	SERROR II Nº II	ag is returned
02710	; RPUSH	031/0	3	from TRSL	105.	, exit ag is returned
02720	Pushes 8 to 6 registers onto the stack					
02730	; Example: RPUSH BC,DE,HL,IX	03790	SAC	HACRO	* ANTH	A - CVC
92749	;	03200		DCT	200	;;A = SVC Number
02750	RPUSH MACRO #R1, #R2, #R3, #R4, #R5, #R6	03210		TROT	99 1	" More than one are
02760	IFGT 40,0	93220		101	7 612	Go if no error
92//8	PUSH #R1 ENDIF	83248		LD	C. A	**Put error code in
02/89	ENDIF	93250		I.D	A. LAH	** BERROR SVC number
02/90	IFGT %%,1 PUSH #R2	83268		RST	288	;;A = SVC number ;;Perform SVC ;;More than one arg, ;;Go if no error ;;Put error code in ;;@ERROR SVC number ;;Exit through @ERRO ;;Here if no error
02800	PUSH #RZ	83278	\$12	EOH	S	: Here if no error
02810		83288	***	ENDIF	*	//
02830	IFGT %%,2 PUSH #R3	83298		ENDM		
82848		03300				
82858	IFGT \$8,3	03310	;			
Ø286Ø	PUSH #R4	83328	, 0	OWRITE W	Write a record	to a file.
82878		83338	1	#UREC defa	ults to value :	in HL
02880					LRL = 256)	
		03340		APCR dof	aulen os nelna	in DE
02900	ENDIF	03350	3			
02910	PUSH #R5 ENDIF IFGT %%,5 PUSH #R6 ENDIF	03360	eewR	ITE MACRO	#UREC, #FCB	
82928	PUSH #R6	93378		DEFINE	@WRITE, 4BH	
02930	ENDIF	03380		IFGT	88,8	
82948	ENDM	03390		IFEQ	88,2	
02950		93499		PUSH	DE	
82968		03410		LD	ewrite, 4BH %%, 0 %%, 2 DE DE, #FCB	
02970	; @@SOUND Sound through built-in speaker	83428		ENDIF		
02980	; If #tone & #dur are not specified, values	03430		PUSH	HL	
02990	default to current contents of B				HL, #UREC	
03000	;	03450 03460		ENDIF		
03010	eesound macro #TONE, #DUR	03460 03470 03480 03490		svc	@WRITE, CHECK	
03020	DEFINE @SOUND,68H IFGT %%,8	03470		IFGT	11,6	
03030	IFGT %%, Ø	03480		POP	HL	
03040	· PUSH BC	03490		IFEQ	88,2	
03050	IFGT %%, B PUSH BC LD B, *DUR<3+*TONE ENDIF SVC @SOUND	83588		POP	DE	
03060	ENDIF	83518		ENDIF		
03070	SVC @SOUND	83520 83538		ENDIF		
03080	IFGT %%, Ø			ENDM		Enc
		83548	3			Ent

Circle 186 on Reader Service card

PROfix * IVTM RESTRUCTURE&TRANSFER

NEW!

For PROFILE® 4 PLUS

NEW!

VISA

Model 4 — TRSDOS® 6.2

49.95

For PROFILE® III PLUS ALSO Model III/4 LDOS® or TRSDOS® 1.3 \$49.95

For PROFILE® PLUS Model II/12

\$89.95

PROfix allows you to reorganize your data base TO MEET TODAY'S NEEDS, and then moves ALL or SELECTED fields and/or records of existing data into your new file structure.

FEATURES

- WORKS WITH HARD DISK OR FLOPPY
- CREATE ENTIRELY NEW FILES—selected fields, records
- PROVIDES ARCHIVING hard disk to floppy
 RE-ARRANGE FIELDS even across segments
- DROP OR ADD FIELDS
- SHORT OR ADD FIELDS
 SHORTEN YOUR FILE drop unused expansion records
 CHANGE FIELD LENGTHS R/L justify data
 CHANGE NUMBER OF SEGMENTS
 CREATE SORTED FILE drop deleted fields
 LITERAL INSERTION specified fields

- ◆ COMPLETE USER MANUAL with examples

-TO ORDER-Send \$49.95 (Model III/4) or \$89.95 (Model II/12) Plus \$2.50 for Handling and Postage Check, M.O., VISA/MC or COD (for charge card, give expiration date, number)

-To- BLUE RIDGE SOFTWARE

230 Chesterfield Road

Lynchburg, VA 24502

Call (804) 239-0574

\$1.00 off on phone orders! Virginia residents add 4% sales tax Most orders filled within 24 hours (allow 2 weeks for checks to clear)

PLEASE SPECIFY VERSION

LDOS is a registered trademark of Logical Systems, Inc.

Profile, TRSDOS are registered trademarks of Tandy Corp.

Circle 434 on Reader Service card.



TWX 510-226-0449

(516) 423-3232

A-Draw gives you reduction and enlargement, plus magnification.

Continued from p. 43

velop new drivers and add them to future releases. It took them two attempts to provide an adequate driver for my DMP 200 and a third to perfect it. They couldn't give me italics, which the printer doesn't support, but gave me the complete set of foreign and technical characters by graphically creating the ones my printer didn't have. The service is free.

A-Draw

A-Draw is as good as any stand-alone paint program I've used. You have free-hand drawing with a complete kit of brushes, along with functions for adding, positioning, and sizing lines and basic shapes. You can paint by spraying or by filling with a variety of preset patterns or ones you design. Although the program doesn't support color printing, you work with two four-color palettes on the screen. A-Draw gives you magnification for detail work and reduction and enlargement.

Cut-and-paste operations let you remove, copy, flip, turn, or reposition parts of your drawing. You can also save parts of it, as well as bring previously saved drawings into the one you're working on. A-Plus comes with a library of 100 drawings to get you started.

A Text function lets you create headlines. Each of the seven fonts supplied with the program comes in five styles, including shadow and outline, and you can combine styles to produce more. The font sizes are preset, but once you have the text on the screen, you can reduce or enlarge it.

At present, A-Draw does not support an external input device such as a joystick, pad, or mouse.

A-Plus keeps its own internal directories. If you go looking through an A-Plus work disk on the DOS level, you won't find the file you called "Letter to Aunt Mae" with the DIR command, nor much else you'd recognize. On the other hand, with 20 characters allowed within the program to name directories and documents, you have room for meaningful labels.

Graphically, A-Plus represents your subdirectories as loose-leaf binders and your individual documents as divisions inside them. You select a binder from a stack of them on the right side of the screen, and an open binder on the left shows you the files it contains. Your binders and files are always available to you as menus, and it's easy to page through them to find what you need.

File-management utilities make using DOS for housekeeping practically unnecessary. Without leaving A-Plus, you can copy, move, rename, and delete files singly or in batches. You can copy and move files between binders on the same disk or from disk to disk. Because A-Plus automatically maintains an archive copy of each file, it's difficult to kill a file accidentally. To completely trash one, you must remove the second copy separately. Another utility lets you import and export text in ASCII format. Finally, you have utilities for formatting new work disks and for making complete disk backups.

Tandy Trouble

A-Plus does not support the Model 1000 keyboard. You won't be able to use your arrow keys, and you'll have to get used to using your numeric keypad for cursor movement only. Keys like home and insert are inoperable and become the 7 and zero keys, respectively. And you won't be able to type four characters at all, most seriously the backslash. Model 1200 and 3000 keyboards operate normally. (According to Savtek, the next upgrade will accommodate the Model 1000.)

Tandy printers, because of the way they handle line feeds, present a problem printing text and graphics together. With some of them, like my DMP 200, you can solve the problem by setting a DIP switch or a software switch. With others, the only solution will be to use a non-Tandy cable or modify a Tandy cable by cutting the wire to pin 14. Also, if you configure your system with the Mode LFOFF command, you'll have to turn DOS's line feeds back on before using A-Plus.

Conclusion

If I were looking at this product from the point of view of a professional writer's tool, I'd have reported several shortcomings. For instance, I'd complain about the way the program handles paragraph formatting, particularly double-spacing, or the lack of command macros. Within the context for which A-Plus is intended, however, I found little to fault: For the moment, the only illustrations you can use in A-Write are those created by A-Draw. If this is a failure, it's a small one.

A-Plus ETG is a fine piece of work, beautifully conceived and impressively executed. More than that, this package is a lot of fun to use. I suppose that could be dangerous.

More Interference Than Interface

*

Autodos 2.0 runs on the Model 1000/1200/3000 (128K) and requires one disk drive. The Software Company, P.O. Box 872687, Wasilla, AK 99687. 907-745-6267. \$34.95.

Autodos is a minimal shell that lets you issue DOS commands and start programs by menu selection. The memory-resident program maintains control of the operating environment so that when you complete a command or exit from a program, its menu screen returns in place of the DOS prompt. The screen displays the current drive and directory as well as the date and time.

The DOS menu lists system commands and utilities and prompts you for parameters when they are needed. The Run menu shows only the EXE, COM, and BAT files in the current directory. You select a command or program by entering a number.

If only it were so pat. The installation procedure is the crankiest I've ever used. It took three attempts to get the program properly installed. If that wasn't indication enough of trouble, the program didn't clear the screen on startup but laid its menu screen over what was already there.

The DOS menu's value is limited. It makes sense that, to execute an external command such as Diskcopy, Diskcopy. COM must be available. It seems to make sense that Autodos has to load Command.COM to process many internal commands. It makes sense until you discover that you can't look at a directory unless Command.COM is in the system path. On a floppy-disk system, that translates into slower operation and a lot of disk shuffling.

The DOS menu's shortcomings go deeper. Take the familiar example of a DIR command: From Autodos, you type a number and press enter. Then, in response to a prompt, you type the path name and switches, just as you would from the system prompt, and press enter again. Nothing in the Autodos prompt saves you from looking in the DOS manual if you don't know the command's syntax. (In fact, with other commands the prompts confused more than they illuminated.) And simple arithmetic shows a net savings of exactly one keystroke with Autodos. I wasn't impressed.

The Run menu is a bit more useful. If you can't remember where you've put a program or its exact spelling, you can browse through directories. Since the Autodos menu shows you only the executable files, the searching should be easier. Unfortunately, to change drives

EXPRESS CHECKOUTS

and directories you first have to go to the DOS menu and use CHDIR, a clumsy way to go. Also, if a floppy disk does not contain system files (i.e., if you didn't format it with the /S switch), one program will not show up in the menu. With several of my disks, the ignored program was the primary program, rendering the disks unusable under Autodos.

The documentation does warn of this shortcoming. It also warns you not to run Basic or BasicA from Autodos, which puts all your Basic programs out of reach.

Autodos provides two other utilities. One reads a key or key combination you press and returns the ASCII codes and characters generated. The other displays the computer's character set.

On the face of it, Autodos's simple-shell concept seemed a good and useful idea. After I worked with it for a while, it proved anything but a convenience. The Software Company claims that version 2.1, the third revision I received in a six-week period, eliminates some of the problems I discussed. I was unable to install version 2.1.

—Наггу Вее

Scrolling Nowhere

Omniscroll III/IV runs on the Models III/4 and requires one disk drive and either TRSDOS 1.3 or Newdos/80 2.0. Lyons Products, P.O. Box 272, Titusville, PA 16354, 814-827-9892. \$19.95.

If you happen to get the product-description flyer with Omniscroll III/IV, you find that it is a screen-scrolling utility for the Model III, or 4. However, Omniscroll III/IV's printed documentation says more about licensing problems than what the program does. The documentation does not even include the vendor's full address.

Moreover, Omniscroll's text files describe the program only as running on the Model III. I infer from the references to Model I TRSDOS and Newdos that the program also runs on the Model I. Since the disk is in Model III format, I don't know how the average user gets Omniscroll to a Model I disk. The on-disk documentation also makes no reference to Model 4 DOSes, so I don't see how it will run in the Model 4 mode.

The flyer claims that Omniscroll is good for animated graphics from interpred Basic, and that it can serve as a foundation for windowing programs. Since the on-disk documentation does not address it, I fail to see how the program can help you with animated graphics unless you already have expertise in that area.

Omniscroll comprises two demonstration programs containing routines for selective scrolling. You can modify the routines and add them to your Basic programs. The routines scroll text up or down, right or left, and even diagonally within a selected window area created by your Basic program.

You scroll by setting Basic variables to certain values and calling a USR function to a machine-language subroutine, which your Basic program pokes into memory. Each USR-function call shifts the windowed area one space right, left, up, or down, so you do all scrolling by programming a For. . .Next loop for multiple calls of the subroutine.

Omniscroll also provides five flowchart text files, a documentation file, an assembly listing in text form, and two programs to print out the documentation or display it on your screen. To understand the flowcharts, you must imagine what they would look like compared to five flowchart patterns (without words) printed on the reverse side of the one-page printed documentation.

Omniscroll is strictly a hacker's program, requiring much analysis of the demos. The program's author does not follow good practices for developing reusable program modules; i.e., you cannot simply merge the routines for use in your programs. The routines do not use unique variable names, and they are numbered 220–1210 for one demonstration program and 60–1210 for the other.

The documentation tells you what the demos do and doesn't give you good programming information. You must dissect the demos for this. The author uses most of the documentation to describe his machine-language listing.

Omniscroll is an unprofessional product. Printing your own documentation is acceptable only if the program is freeware or in the public domain. The Basic program that prints the documentation does not paginate or include a left margin; two more lines of Basic code would do this.

Omniscroll would better serve as a magazine article describing a programming technique. But for sale? Never.

-Thomas L. Quindry

Beginner's Gothic

Moonmist runs on the Tandy 1000/1200/3000 (128K) and requires one disk drive. Infocom Inc., 125 Cambridge Park Drive, Cambridge, MA 02140. 617-576-3190. \$39.95.

A letter from your old friend, Tamara Lynd, is a pleasant surprise in your otherwise harried life. After all, being an attractive, celebrated, brilliant, young detective is demanding. So you smile, perhaps with a touch of envy, as you learn how Tamara's trip to Europe has turned suddenly into a storybook romance. "You'll never believe what's happened!" she writes. "I'm living in a castle in Cornwall, engaged to marry a British Lord!"

Her words bubble from the page as she tells you of the ancient castle, complete with its ghost and buried treasure; of her fiance, Lord Jack Tresyllian; and of all the other stuffy, charming, scheming, sinister characters who populate her new life.

Lord Jack himself is no gadabout, she assures you, nor is the life of a British peer carefree. For one thing, Jack's former girlfriend drowned in the castle well soon after he broke off the romance because of her affair with his best friend. Her body was never found. And Jack inherited more than a castle and a title from Uncle Lionel. The family's debts forced Lord Jack to open the castle to the public to keep what remained of the family heirlooms from the likes of a too eager London antiques dealer.

Tamara's second letter, however, is another story. "Help!" she begins. Someone, it seems, is trying to kill her.

Moonmist has all the elements of a classic Gothic mystery fit for a Holmes or a Whimsey. If you've never tried interactive fiction, if you've been looking for a text adventure to begin with, Moonmist's Tresyllian Castle might be the place to start. The objectives are clear, the puzzles are well-defined, and none of them require the often frustrating and defeating leaps of logic for which adventure games are notorious.

However, gamers with any experience will be disappointed. Moonmist is too easy. Its setup—the set piece at the beginning that leads you by hand to the first hints and clues—goes too far. By the time the program leaves you on your own, the promising mystery has been reduced to the level of a pulp romance.

Moonmist offers four scenarios based on the same characters, plot, and setting. Each begins with the same opening sequence, varied only by the specific clues you are given. Each ends with a different villain, treasure, and rationale.

In theory, that's not a bad idea. In practice, because the four stories share not only the same premise but also the same map, props, and devices, it doesn't work. Once you've solved the first story, about all that's left for the other three is the drudgery of searching the same territory for only slightly different quarry. And nowhere is there the least hint that your character is in any danger.

The highly entertaining presentation,

ENHANCE YOUR TANDY

The **Full House** will expand your Tandy 1000 to its **full** I/O and memory configuration for only \$315.

Features:

2 parallel ports (centronics) 2 serial ports (R\$232) Real Time clock/calendar Memory, up to 512K DMA Controller

The **Full House** is actually a combination of two boards that can be joined into **one**. You have the option of buying either the I/O or memory section first and **later combining the two without using an additional slot**. Each can also be used separately.

Full House I/O \$170 Full House Memory (256K) \$130 Full House Memory (512K) \$165 Full House Combination (512K)

Shipping & Handling \$6

Dealer inquiries welcome.

Mastercharge/Visa accepted.

To order, in California call: 800 626-9541 ext. 1131

Elsewhere: 800 452-4445 ext. 1131

Call now to get the value and flexibility that **nobody else** offers.

SJS Engineering P.O. Box 998 Millbrae, CA 94030

Circle 297 on Reader Service card.

EXPRESS CHECKOUTS

for which Infocom games are famous, is not enough by itself to invent excitement and sustain interest. Moonmist is a passable demonstration of the techniques and possibilities of text adventures, but no more than that.

—Наггу Вее

Up the Corporate Ladder

Managing for Success (formerly American Dream) runs on the Tandy 1000/1200/3000 (256K) and requires one disk drive. Blue Chip Software Inc., 6744 Eton Ave., Canoga Park, CA 91303, 818-346-0730. \$59.95.

Managing for Success is a corporatemanagement simulation that you can play for amusement or training. It comes on two disks with a softcover manual. The program is copy-protected; you must use disk A to start the game even if you've moved the program to a hard drive. Replacement copies are free for 90 days. \$22.50 thereafter.

Whether or not Managing for Success has educational merit, it is fun to play. It places you in a top management role in an initially profitable robot-manufacturing company. You control seven areas: engineering, material control, quality control, finance, production, marketing, and research. The program advises you of the state of the economy as play progresses: It tracks changes in GNP, inflation, hourly wages, and prime interest rate. Each simulation lasts six years, incrementing one month at a time. You can save a game in progress.

To help you make decisions about the business, you receive detailed reports from the various divisions. Such items as product-cost analysis, labor use, shipment forecasts, and income statements are available on demand and appear automatically every quarter. Memos also appear occasionally, reporting on progress in certain areas or warning about dangerous trends.

Managing for Success also has a capable graph-generating module that lets you custom-design graphs of any two items you choose. For convenience, certain graphs are available predesigned from the major departments.

The program's main screen displays the most important financial information, such as the revenue for the month, profit, units shipped, and projected cash balance. The only other item I wish this screen had is the previous month's data for comparison.

Various factors are within your control. In some departments (research and development, quality control, engineering), you can only increase or decrease

the budget. In others, you have more choices. In the finance department you can discount receivables to prompt those who owe you money to pay more promptly. You can also change the number of days you take to pay your creditors. In marketing, you can go from commissioned reps to salaried salesmen, increase advertising, run special promotions, or hire a market-research firm.

As you make changes, it can be difficult to make a profit on each unit because there is little margin on the robots and the competition's price forces you to remain at a reasonable level. Even gentle tinkering can catapult you into the red in a short time. As in the real world, sometimes it is hard to understand how to correct problems.

Many factors affect sales: the uniqueness of the product, quality, customer satisfaction, price, and promotion. It's a challenge to balance these factors. One nice feature is the worksheet section, which lets you test changes you are considering before you take any action.

I was confused by a discrepancy between the figure given as the break-even price of the robots in the marketing section and the unit cost of the robots as listed in the reports section. The logical conclusion would be that these figures should be the same. But one month I lost money with each sale (selling at less than my unit cost), yet the break-even price shown was below my selling price, indicating that I should have made money.

I found no explanation for this in the manual, but a call to the company's support line resulted in the answer. The break-even price is based on sales projections for the coming month, whereas the unit cost is based on actual sales for the previous month.

You can change many factors, from the name of the company to the initial bank-account balance, in Managing for Success from an auxiliary program. This feature keeps the simulation interesting after repeated plays.

The manual enhanced the educational aspect of the program. It is a complete introduction to the manufacturing business. The manual explains all terms found in the simulation, suggests strategies, analyzes each department's function, and emphasizes pitfalls. It is clearly written and designed.

The fun of Managing for Success is its complexity and the intertwining of all the factors causing the corporation's success or failure. Whether learning to master the game will also help in the real world is unknown, but it certainly helps you acquire perspective and insight into the complexities of the corporate environment.

-Wynne Keller

MS-DOS

Student Lotus

In a joint marketing agreement with the Lotus Development Corp., Addison-Wesley Publishing Co. has introduced the 1-2-3 Student Edition, a fully functional version of 1-2-3 customized for instructional applications. The package includes teacher and student manuals that provide lab exercises for college courses.

The software includes all the features and functions of the professional version, except that the Student Edition is limited to a 64-column by 84-row spreadsheet, while the full 1-2-3 has 256 columns and 8,192 rows.

The suggested retail price for the 1-2-3 Student Edition is \$49.95. Contact Addison-Wesley Publishing Co., Reading, MA 01867, 617-944-3700.

Circle 550 on Reader Service card.

Full Text and Graphics Layouts

Ingram Software Inc. is distributing White Science's desktop publishing package, Pagebuilder. Besides its text-handling abilities, the program offers advanced graphics abilities, including complete line drawings, charts, and graphs.

Pagebuilder can read datainterchange format (DIF) files from Lotus or other spreadsheet programs, data-exchange format (DXF) files from Autocad and other CAD programs, and ASCII text files from popular word-processing programs. It supports kerning and justification.

The program supports fully proportional fonts ranging from 3–72 points and can work with Canon- and Ricohengine laser printers; Calcomp, Kurta, and Summagraphics digitizing tablets; PC and Microsoft Mouse; and scanner input devices.



The 1-2-3 Student Edition has many features of its big brother.

Pagebuilder sells for \$495 from Ingram Software Inc., 2128 Elmwood Ave., Buffalo, NY 14207, 800-828-7250 (east), 800-847-6383 (west). Circle 551 on Reader Service card.

Automate Your Business

Automate is an order-entry and billing software package that updates inventory and records sales, costs, margins, and markups.

When you make a sale, you type in the number sold and the stock number. The program checks the inventory and enters an item description, the price, tax, and the line and invoice totals. You can also enter payments on account, payments to vendors, and charges for merchandise, labor, or services. Once you've typed in the information, Automate writes the invoice, records the sale, and updates the inventory.

The program sorts the charge-invoice file chronolog-

ically and writes the entries to customer files. You then call up each file and make any necessary changes, and Automate writes and addresses individual customer statements.

Automate sells for \$149.95 and requires an MS-DOS machine with a color-graphics adaptor, 256K, and two disk drives. Contact RHM & Associates, 913 Helen St., Midland, MI 48640, 517-631-9334.

Circle 552 on Reader Service card.

Welcome Aboard, Captain Kirk

You are Captain James T. Kirk, of the starship Enterprise. While exploring an unmapped sector of space near the Great Transtellar Rift, the Enterprise comes under sudden attack. Your entire stock of raw protein substance (the base material of synthesized foods) is damaged, and you've got to beam down to the nearest class M (oxygen-nitrogen atmosphere) planet to find

food before your crew starves.

Thus begins Simon & Schuster Software's newest interactive fiction adventure. It's called The Promethean Prophecy, and it sells for \$39.95 from Simon & Schuster Software, One Gulf + Western Plaza, New York, NY 10023, 212-373-8882.

Circle 553 on Reader Service card.

Financial Help From J.K. Lasser

J.K. Lasser's Your Income Tax is a book and software package with 27 forms and schedules updated to meet the revisions in the income-tax laws. On-screen help information and references to paragraphs in Lasser's book should answer your questions.

By asking specific questions, the program determines which forms and schedules apply to your tax situation. Then it walks you through each step of the filing process. The screen displays a form 1040.

You can call up a calculator as you work or move back and forth between 1040 line numbers and related forms and schedules. The program automatically transfers your calculations to your 1040.

When you've finished, Your Income Tax computes your return and prints it directly onto your 1040. (It can print 27 other forms and schedules also.)

Your Income Tax sells for \$69.95 and requires 128K, a disk drive, and DOS 2.0 or higher. If you bought the program last year and still have proof of purchase, you can get the update for \$29.95.

J.K. Lasser's Your Money Manager is a home-accounting and small-business tool that helps organize and maintain financial records. It includes a check writer, financial statements, balance sheets, and budget reports.

The program features an on-screen; four-function cal-

How to Use 80 Micro Program Listings

Basic program listings in 80 Micro include a checksum value at the end of each line. This value is the sum of the ASCII values of all characters and spaces in the line, excluding remarks. You can use these values to test the accuracy of your typing.

- Type in program code exactly as listed, omitting the indentations (when program lines continue to a second or third magazine line). The '* characters, checksum values, and comments may be omitted.
- Save the program in ASCII format with the command SAVE "file name", A.
- ●Load and run Checksum (see Program Listing). (For the Tandy 1000, change line 10 to: 10 CLS:LOCATE 2,25:PRINT "VER-IFY CHECKSUMS ON PROGRAM" '* 3544.) The program will prompt you for the name of the file to be verified and give you the option of sending the line numbers and checksum values to the printer or to the screen.

When printing to the screen, Checksum lists 20 lines and then waits for you to press the enter key.

 Compare the displayed line numbers and checksum values with the checksums shown in the listing. Correct errors in lines having checksum values that don't match.

> —Beverly Woodbury, Technical Editor

```
Program Listing. Checksum.
10 CLEAR 1000:CLS:PRINT@140, "VERIFY CHECKSUMS ON PROGRAM"
20 PRINT:PRINT:INPUT "Enter Name of File to verify";F$
30 PRINT:PRINT:PRINT "List Checksums to:"
40 PRINT TAB(20) "<Printer":PRINT TAB(20) "<S>creen"
                                                                                                                                                                                     4245
                                                                                                                                                                                     3233
                                                                                                                                                                                     3628
        PRINT: PRINT: PRINT TAB (30); "?
                                                                                                                                                                                     2148
726
60 K$=INKEY$
70 IF K$="p" OR K$="p" OR K$="s" THEN 80 ELSE 60
80 PRINT K$:IF K$="p" OR K$="p" THEN LP=1
90 OPEN "1",1,F$:B$=CHR$(34)
                                                                                                                                                                                     3269
                                                                                                                                                                                     1521
100 IF EOF(1) THEN CLOSE:GOTO 390
110 LINE INPUT#1,L$:L=VAL(LEFT$(L$,6))
                                                                                                                                                                                     2000
120 IF Z=2 AND L=0 THEN 100 ELSE Z=2
130 A=VARPTR(L$):GOSUB 270:Q=PEEK(A)
                                                                                                                                                                                     2089
130 A=VARPTR(L$):GOSUB 270:Q=PEEK(A)
140 LS=PEEK(A+1):MS=PEEK(A+2):A=MS*256+LS:GOSUB 270
150 IF INSTR(L$,"") THEN GOSUB 280
160 IF RIGHT$(L$,1)=" "THEN IQ=Q:GOSUB 370
170 FOR K=1 TO Q:P=PEEK(A):CS=CS+P:A=A+1:NEXT K
180 IF CS=0 THEN 100
190 IF CS<100000! THEN D$="-"
200 IF CS<100000 THEN D$="-"
                                                                                                                                                                                     3115
                                                                                                                                                                                     2038
                                                                                                                                                                                     1131
                                                                                                                                                                                     1538
1481
190 IF CS<18000 THEN D$="-"
200 IF CS<18000 THEN D$="-"
210 IF CS<18000 THEN D$="-"
220 IF CS<1800 THEN D$="-"
230 IF LP=1 THEN LPRINT "Line";L;D$;CS,:CS=0:GOTO 100
240 PRINT "Line";L;D$;CS:CS=0:X=X+1
                                                                                                                                                                                     1466
                                                                                                                                                                                     1451
                                                                                                                                                                                     2282
250 IF X=20 THEN X=0:PRINT TAB(30) "Press <ENTER> to continue." ELSE 100
                                                                                                                                                                                     4924
260 K$=INKEY$:IF K$<>CHR$(13) THEN 260 ELSE 100
         IF A>32767 THEN A=(65536!-A)*-1:RETURN:ELSE RETURN I=INSTR(L$,"'"):IQ=I-1
IF LEN(L$)=INSTR(L$,"'") THEN 100
                                                                                                                                                                                     3275
                                                                                                                                                                                     2095
300 LQS=STR$(L):LQ=LEN(LQ$):IF LQ+2=>I THEN 100
310 Ql=INSTR(L$,B$):IF Ql>I OR Ql=0 THEN 370
320 Q2=INSTR(Q1+1,L$,B$):IF Q2>I THEN I=INSTR(Q2,L$,"'")
                                                                                                                                                                                     2839
2593
                                                                                                                                                                                     3297
320 IF I=0 THEN RETURN
340 Q3=INSTR(Q2+1,L$,B$):IF Q3>I OR Q3=0 THEN 370
350 Q4=INSTR(Q2+1,L$,B$):IF Q3>I OR Q3=0 THEN 370
350 Q4=INSTR(Q3+1,L$,B$):IF Q4>I THEN I=INSTR(Q4,L$,"'")
360 IF I=0 THEN RETURN
370 FOR I=1Q TO 1 STEP-1:C=ASC(MID$(L$,I,1)):IF C<33 THEN NEXT I
380 RL$=LEFT$(L$,I):Q=LEN(RL$):RETURN
                                                                                                                                                                                     1386
                                                                                                                                                                                     2869
                                                                                                                                                                                     3308
                                                                                                                                                                                     1389
                                                                                                                                                                                     3847
                                                                                                                                                                                     2323
390 PRINT:PRINT "CHECKSUM/BAS now in Memory"
400 PRINT "Reload the PROGRAM that you are working on? (Y/N)";
410 INPUT Q$:IF Q$="Y" OR Q$="y" THEN CLS:LOAD F$
                                                                                                                                                                                     3248
                                                                                                                                                                                     4890
2967
                                                                                                                                                                                           End
```

80 MICRO'S LIST of ADVERTISERS

MAY 1987

lead	ler Service Number Page	Reac	ler Service Number	Page	Read	ler Service Number	Page
82	Aerocomp		CW World	21	107	Misosys, Inc.	37, 39, 41
82	Aerocomp		Foreign Dealers	107	100	Montezuma Micro	27
202	Aerocomp		80 Best of 1986	53	411	Montezuma Micro	
102	Aerocomp		80 Micro Disk Series	101	416	Montezuma Micro	57
17	Alpha Products		Moving	108	424	Montezuma Micro	
30	Allwrite (Prosoft) 9		PC Resource Subscription	85	167	National Computer Supply	18
41	Anitek Software Products		Reader Service	92	232	Nocona Electronics	
78	ATD		Subscription		205	PG Design Electronics	89
59	Atmospheres	361	Electric Software Corp	3	124	Perry Computers	64
52	BCCompco	45	Electric Webster	1	308	Powersoft	
45	Beaman-Porter42	358	Exec-PC, Inc	39	449	Professor Jones/Frogg House .	39
01	Big D Computers50	214	Fort Worth Computers	30, 31	30	Prosoft	
86	Blue Ridge Software	•	GE Information Services	CII	478	Purple Computing	61
78	CompuServe	9	H & E Computronics	CIV	75	Radio Shack 24	
33	CDA World of Computers	540	Hannah Tanning Inc	44, 45	371	Seatronics	41
57	Computer Friends	455	Hard Drive Specialists		297	SJS Engineering	114
18	Computer Plus	209	H.I. Tech	106	245	Software Sales	
42	Computer Supplies of Peterborough 73	175	Howe Software	63	188	Spectre Tech	122
91	Comtrek Computer Components 60	46	Hypersoft	92	296	Solar Systems Software	
45	Cornucopia Software	101	J & M Systems, Ltd	92	444	Southwestern Digital	83
97	DAC Software CIII	534	Jameco Electronics	117	189	Tab Sales	
82	DFW Computer Center		Logical Systems		434	Telebyte Tech	
14	Digital Vision	250	Marymac Industries, Inc	75	81	Total Access	
04	DiskCount Data	225	Merritt Computer		227	Trisoft	121
52	Dresselhaus Computer Products 107	464	Micro Labs, Inc	43			
85	Educational Micro Systems		Micro Smart	78, 79, 81	Ene for	rther information from our adv	ertleare
	80 Micro	299	Microdex			use the Reader Service card.	er tiber s,
	Classified 41, 121	346	Microlite	108		advertiser prefers to be conta	cted directly
49	Classified Ads	137	Miller Microcomputing	109	IIIIa	advertiser prefers to be conta	cied directly
		100			Adver	tising Sales (603) 924-7138	
						(ising Sales (603) 924-7136	
						Coast Sales (415) 328-3470	

DER SERVICE

This card valid until July 31, 1987.

A	. How would you describe your in 1. I own an MS-DOS, IBM cor 2. I intend to purchase.	nterest in MS-DO: npatible system.	S, IBM Compatible S 3. I'm interested plans to purch 4. Not interested	but have no immediate
В	On a scale of 1 (no interest) to 5	(great interest), p		
	types of programs published in 1. Business applications	80 Micro:	4. Money man	agement applications
	2. Science/math application 3. Home management application	ins lications	5. Games 6. Programmin	ng Utilities
C	. Excluding yourself, how many p 1. □ One 2. □ Two	people read your 3. ☐ Three 4. ☐ Four	copy of 80 Micro? 5.	. □ Five or more
D	. What type of TRS-80/Tandy Cor 1. Model I	nputer do you ow 6. Model 16/	n? Check all that ap	ply. 1. □ Model 2000
	2. Model II/12 3. Model III 4. Model 4/4P/4D 5. Model 4D	7. Model 100 8. Model 600 9. Model 100 10. Model 120	0/200 1; 00	2. Model 3000
E	. How long have you owned your 1. Less than 1 year 2. 1-2 years 3. 2-3 years	TRS-80/Tandy Co 4. ☐ 3-4 years 5. ☐ More than 4		
F.	Do you subscribe to an informat 1. ☐ Yes	tion utility, such a 2. No	as Compuserve, Dow 3.	Jones News Retrieval, etc.? Not now, but intend to within 12 months.
G	. Do you plan to purchase another 1. Yes	er TRS-80/Tandy C 2. □ No	Computer during the 3.	next 12 months? Don't know
н	. Where do you use your TRS-80/ 1. At home for pleasure 2. At home for business	Tandy Computer?	Check all that apply	y. nce applications in any loca-
	3. At work		tion	ice applications in any loca-
I.	The articles in 80 Micro are: 1. Too simple	2. Too comple	х 3.	☐ Just right
J.	How many purchases have you 1. \square 0	made based on a 2. 1-3		licro? 4 or more
K.	. Which of the following columns (always read).	do you read? Ple	ease rate them on a s	scale of 1 (seldom read) to 5
	1. Side Tracks 2. Feedback Loop	5. The N	Next Step 's MS-DOS Column	9. Reviews 10. New Products
	3. Pulse Train 4. The Art of Programming	7. Fine	Lines	11. Hot CoCo
L.	If you are not a subscriber, pleas	se circle 500.		
М	. If you would like a one year sub Card. Each subscription costs year only). Please allow 10–12 v	scription to 80 Mi \$24.97. (Canada 8	icro, please circle 50 k Mexico \$27.97, Fore	on the Reader Service
	year only). Please allow 10-12 v	veeks for delivery		
	DEADER	OTT		
	READER		RVICI	E
T		1987.	S, IBM Compatible S 3. I'm interested	ystems? but have no immediate
T A.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5	1987. Interest in MS-DOS Inpatible system. (great interest), p	5, IBM Compatible S 3. □ I'm interested plans to purch 4. □ Not interested	ystems? but have no immediate ase.
T A.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase.	1987. Interest in MS-DOS Inpatible system. (great interest), p 80 Micro:	S, IBM Compatible S 3. I'm interested plans to purch 4. Not interested lease rate your inter	ystems? but have no immediate ase est in seeing the following agement applications
A.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in 1. Business applications 2. Science/math applicatio 3. Home management appl Excluding yourself, how many p	terest in MS-DOS npatible system. (great interest), p 80 Micro: ns ications	S, IBM Compatible S 3. I'm interested plans to purch 4. Not interested lease rate your inter 4. Money mana 5. Games 6. Programmin	ystems? but have no immediate ase est in seeing the following agement applications
A. B.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in 1 1. Business applications 2. Science/math application 3. Home management appl Excluding yourself, how many p 1. One 2. Two What type of TRS-80/Tandy Com	1987. terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications eeople read your o 3. □ Three 4. □ Four uputer do you own	S, IBM Compatible S 3. I'm interested plans to purch 4. Not interested dlease rate your inter 4. Money mans 5. Games 6. Programmin copy of 80 Micro? 5.	ystems? but have no immediate ase est in seeing the following agement applications ig Utilities Five or more
A. B.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in: 1. Business applications 2. Science/math application 3. Home management appl Excluding yourself, how many p 1. One 2. Two What type of TRS-80/Tandy Com 1. Model II/12	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications eople read your of 1.	S, IBM Compatible S 3. I'm interested plans to purch 4. Not interested lease rate your interested 4. Money mans 5. Games 6. Programmin copy of 80 Micro? 7. Check all that app 68/6000 11/200 12	ystems? but have no immediate ase set in seeing the following agement applications g Utilities □ Five or more
A. B.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications eeople read your c 3. Three 4. Four puter do you ow puter do you ow Model 16/1 7. Model 16/0 8. Model 800 9. Model 000	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more
B. C. D.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in 1. Business applications 2. Science/math application 3. Home management appl Excluding yourself, how many p 1. One 2. Two What type of TRS-80/Tandy Com 1. Model II 2. Model III 3. Model III 4. Model 4/4P/4D 5. Model 4D	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your of 3.	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more
B. C. D.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your of 3.	S, IBM Compatible S 3. I'm interested plans to purch plans to purch d. Not interested lease rate your interested 4. Money mans 5. Games 6. Programmin copy of 80 Micro? 5. 7. Check all that app (6B/6000 11 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 12 / 200 13 / 200 14 / 200 15	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more
T A. B. C. D. E. F.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your of 3.	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000
T A. B. C. D. E. F.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in: 1. Business applications 2. Science/math applicatio. 3. Home management applications 2. Science/math application 2. Two What type of TRS-80/Tandy Com 1. Model II 2. Model III1 3. Model III1 3. Model III1 5. Model III 5. Model IVI 5. Model IVI 5. Model IVI 6. Model IVI 7. Less than 1 year 8. Less than 1 year 9. Less than 1 year 1. Less than 1 year 1. Less than 1 year 1. Yes 1. Do you subscribe to an informat 1. Yes	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your of 3.	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000
T A. B. C. D. E. F. G.	his card valid until July 31, How would you describe your in 1.	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your 03. Three 4. Four puter do you own 6. Model 1601 7. Model 1001 10. Model 1200 TRS-80/Tandy Co 4. 3-4 years 5. More than 4 Ion utility, such as 2. No TRS-80/Tandy C 2. No Tandy Computer?	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. next 12 months? Don't know
T A. B. C. D. E. F. G. H.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in 1. Business applications 2. Science/math application 3. Home management appl Excluding yourself, how many p 1. One 2. Two What type of TRS-80/Tandy Com 1. Model 2. Model 4. Model 5. Model 4. Model 5. Model 4D How long have you owned your 1. Less than 1 year 2. 1-2 years 3. 2-3 years Do you subscribe to an informat 1. Yes Do you plan to purchase anothe 1. Yes Where do you use your TRS-80/T 1. At home for pleasure 2. At home for business 3. At home for business The articles in 80 Micro are:	1987. Interest in MS-DOS patible system. (great interest), p 80 Micro: Inside system. Insi	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. next 12 months? Don't know ce applications in any loca-
T A. B. C. D. E. F. G. H. J. J.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications eeople read your 03. Three 4. Four puter do you ow 6. Model 16/1 7. Model 100 10. Model 100 10. Model 100 10. Model 300 10. TRS-80/Tandy Co 4. 3-4 years 5. More than 4 ion utility, such a: 2. No TRS-80/Tandy Co 2. No TRS-80/Tandy Co 2. No TRS-80/Tandy Co 2. TRS-80/Tandy Co 2. TRS-80/Tandy Co 3. TRS-80/Tandy Co 4. TRS-80/Tandy Co 5. TRS-80/Tandy Co 7. TRS-80/Tandy Co 7. TRS-80/Tandy Co 8. TRS-80/Tandy Co 9. TRS-80/Tandy Co	S, IBM Compatible S 3.	ystems? but have no immediate ase. set in seeing the following agement applications g Utilities Five or more bly. Model 2000 Jones News Retrieval, etc.? Not now, but lintend to within 12 months. next 12 months? Don't know Just right icro?
T A. B. C. D. E. F. G. H. J.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications ecople read your composition of the system of the sy	S, IBM Compatible S 3.	ystems? but have no immediate ase. set in seeing the following agement applications go Utilities Five or more bly. Model 2000 Jones News Retrieval, etc.? Not now, but lintend to within 12 months. mext 12 months? Don't know Just right icro? Just right icro? does in mediate as well
T A. B. C. D. E. F. G. H. J. K.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in: 1. Business applications 2. Science/math application 3. Home management appl Excluding yourself, how many p 1. One 2. Two What type of TRS-80/Tandy Com 1. Model II 2. Model III 3. Model III 4. Model III 5. Model III 5. Model III 7. Model III 8. Model III 9. Where III 9. Where III 10. Where III 11. Yes Do you subscribe to an informat 11. Yes Where do you use your TRS-80/T 11. At home for pleasure 22. At home for pleasure 23. At work 14. Too simple How many purchases have your II. Uwis IIII Which of the following columns (always read).	terest in MS-DOS patible system. (great interest), p 80 Micro: ns ications eeople read your of 3.	S, IBM Compatible S 3.	ystems? but have no immediate ase. set in seeing the following agement applications g Utilities Five or more by. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. mext 12 months? Don't know ce applications in any loca- Just right icro? 4 or more cale of 1 (seldom read) to 5
T A. B. C. D. E. F. G. H. J. K.	his card valid until July 31, How would you describe your in 1. I own an MS-DOS, IBM con 2. I intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	1987. Interest in MS-DOS patible system. (great interest), p 80 Micro: Inside system. (great interest), p 80 Micro: Inside system. Insid	S, IBM Compatible S 3.	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. next 12 months? Don't know ce applications in any locations of 1 (seldom read) to 5 9. Reviews 10. New Products
T A. B. C. D. E. F. G. H. J. K.	his card valid until July 31, How would you describe your in 1. 1 own an MS-DOS, IBM con 2. 1 intend to purchase. On a scale of 1 (no interest) to 5 types of programs published in:	1987. Interest in MS-DOS patible system. Interest in MS-DOS pati	S, IBM Compatible S 3. □ I'm interested plans to purch 4. □ Not interested elease rate your interested sease rate your interested elease rate your elease el	ystems? but have no immediate ase. est in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. next 12 months? Don't know ce applications in any loca- Just right icro? 4 or more cale of 1 (seldom read) to 5 9. Reviews
T. A. B. C. D. E. F. G. H. J. 1 J. K.	his card valid until July 31, How would you describe your in 1.	1987. Interest in MS-DOS patible system. (great interest), p 80 Micro: Insications recopie read your compositions of the system of the syste	S, IBM Compatible S 3.	ystems? but have no immediate ase. set in seeing the following agement applications g Utilities Five or more bly. Model 2000 Model 3000 Jones News Retrieval, etc.? Not now, but intend to within 12 months. mext 12 months? Don't know ce applications in any localicro? 4 or more cale of 1 (seldom read) to 5 9. Reviews 10. New Products 11. Hot CoCo

Reader Service: To receive more information from any of the advertisers in this issue, circle the number of the Reader Service Card that corresponds with the Reader Service number on the ad in which you are interested. You will find numbers. Complete the entire card, stamp and drop into a mailbox. In 4-6 weeks you will hear from the advertiser directly.

301 306 311 316 321 302 307 312 317 322

451 456 461 466 471 452 457 462 467 472

MAY 1987 5

1 6 11 16 21 151 156 161 166 171 2 7 12 17 22 152 157 162 167 172

313 318 323	453 458 463 468 473
314 319 324	454 459 464 469 474
315 320 325	455 460 465 470 475
336 341 346	476 481 486 491 496
337 342 347	477 482 487 492 497
338 343 348	478 483 488 493 498
339 344 349	479 484 489 494 499
340 345 350	480 485 490 495 500
361 366 371	501 506 511 516 521
362 367 372	502 507 512 517 522
363 368 373	503 508 513 518 523
364 369 374	504 509 514 519 524
365 370 375	505 510 515 520 525
386 391 396	526 531 536 541 546
387 392 397	527 532 537 542 547
388 393 398	528 533 538 543 548
389 394 399	529 534 539 544 549
390 395 400	530 535 540 545 550
411 416 421	551 556 561 566 571
412 417 422	552 557 562 567 572
413 418 423	553 558 563 568 573
414 419 424	554 559 564 569 574 555 560 565 570 575
415 420 425	555 560 565 570 575
436 441 446	576 581 586 591 596
437 442 447	577 582 587 592 597
438 443 448	578 583 588 593 598 579 584 589 594 599 580 585 590 595 600
439 444 449	579 584 589 594 599
440 443 430	360 363 360 363 000
	Title
	7:-
State	
	State

Reader Service: To receive more information from any of the advertisers in this issue, circle the number of the Reader Service Card that corresponds with the Reader Service number on the ad in which you are interested. You will find numbers. Complete the entire card, stamp and drop into a mailbox. In 4-6 weeks you will hear from the advertiser directly.

80 micro

1	6	11	16	21	151	156	161	166	171	301	306	311	316	321	451	456	461	466	47
2	7	12	17					167					317					467	
3	8	13	18					168					318					468	
4	9	14	19					169					319					469	
5		15	20					170					320					470	
	10	10	20	2.5	133	100	100	170	175	303	310	313	320	323	*55	400	400	470	•"
26	31	36	41	46	176	181	186	191	196	326	331	336	341	346	476	481	486	491	49
27	32	37		47				192					342					492	
28	33	38	43					193					343					493	
	34	39	44					194					344					494	
30	35	40	45					195					345					495	
				50	100	100	100	100	200	500	-	040	040	550	400	400	400	400	
51	56	61	66	71	201	206	211	216	221	351	356	361	366	371	501	506	511	516	52
52	57	62	67	72	202	207	212	217	222	352	357	362	367	372	502	507	512	517	52
53	58	63	. 68	73	203	208	213	218	223	353	358	363	368	373	503	508	513	518	52
54	59	64	69	74	204	209	214	219	224	354	359	364	369	374	504	509	514	519	52
55	60	65	70	75	205	210	215	220	225	355	360	365	370	375				520	
_										-	_								
76	81	86	91	96	226	231	236	241	246	376	381	386	391	396	526	531	536	541	54
77	82	87	92	97	227	232	237	242	247	377	382	387	392	397	527	532	537	542	54
78	83	88	93	98	228	233	238	243	248	378	383	388	393	398	528	533	538	543	54
79	84	89	94	99	229	234	239	244	249	379	384	389	394	399	529	534	539	544	54
80	85	90	95	100	230	235	240	245	250	380	385	390	395	400	530	535	540	545	55
_			_	_						-		_			-				
	106				251	256	261	266	271	401	406	411	416	421	551	556	561	566	57
	107				252	257	262	267	272	402	407	412	417	422	552	557	562	567	57
				123				268		403	408	413	418	423				568	
	109				254					404	409	414	419	424	554	559	564	569	57
105	110	115	120	125	255	260	265	270	275	405	410	415	420	425	555	560	565	570	57
				146	276								441					591	
				147	277								442					592	
	133				278								443					593	
				149	279								444					594	
130	135	140	145	150	280	285	290	295	300	1 430	435	440	445	450	580	585	590	595	60

City	State	Zip	
Telephone ()			
80 micro	MA	Y 1987	5

Address

Title_

PLACE STAMP HERE

80 Micro P.O. Box 306 Dalton, MA 01227


> PLACE STAMP HERE

80 Micro P.O. Box 306 Dalton, MA 01227

ELECTRONICS

Mail Order Electronics • Worldwide • Since 1974


ZUCKERBOARD 20 MegaByte Hard Disk Drive Board for the Tandy 1000 and 1000SX 2 Year Warranty!



FEATURES: · A microprocessor-controlled servo mechanism guarantees high performance and maximum reliability • 20 MegaBytes formatted capacity • Compact design • DC power only (+12V and +5V) • Access time: 85ms • Pre-formatted with MSDOS · Uses only 1 slot · 2-year warranty · Just Plug In and Go!

T20MB SX20MB 20 MegaByte Hard Card for TANDY 1000..... \$579.95 20 MegaByte Hard Card for TANDY 1000SX. \$589.95

ZUCKERBOARD



Expansion Memory Half Card and Clock/Calendar for the Tandy 1000SX


NEW!

The Zuckerboard Memory Half-Card provides an extra 256K of memory for the Model 1000SX, bringing your 384K Tandy 1000SX to 640K. Optional

battery backed 20-year clock/calendar, TAN-C @ \$39.95 (not included, see below) 2-yr. warranty. Documentation included. Made in the U.S.A.

TSX256K Includes 256K RAM. \$119.95

Multifunction Board with



Clock/Calendar for the Tandy 1000SX NEW!

The Zuckerhoard Multifunction Board provides an extra 256K of memory bring-

ing your 384K Tandy 1000SX to the maximum of 640K. Board comes complete with serial port (expandable to two, see below: TESP \$39.95) and is addressable up to 4 COM. RAM Disk Printer Spooler Software and 20-year battery backed clock/calendar are also included. Made in the U.S.A. 2-year warranty and documentation included.

TESP

M256K Includes 256K RAM. \$189.95

Second Serial Port for M256K. \$ 39.95



Expansion Memory Half Card and Clock/Calendar for Tandy 1000

Expands Tandy 1000 (128K Version) to as much as 640K using 256K DRAM chips • Includes DMA controller chip · Optional clock/calendar plugs onto board (not included) · Made in the U.S.A. · 2-year warranty

TAN-EM256K TAN-EM512K

Clock/Calendar Option (Only).....\$ 39.95 \$ 99.95 Includes 512K RAM and Manual. \$129.95 \$119.95

ZUCKERBOARD

Multifunction Board with Clock/Calendar for Tandy 1000

· Expands Tandy 1000 (128K Version) to as much as 640K · Comes with RS232 serial port, RAM Disk Printer Spooler and on-board DMA controller chip • Made in U.S.A. • 2-year warranty

MTAN-256K MTAN-512K Includes 256K RAM and Manual. \$179.95 Includes 512K RAM and Manual. . . . \$209.95 \$199.95



ZUCKERBOARD

Expansion Memory Secondary Card for Tandy 1000

This board is designed for use with the Tandy 1000 that already has the DMA function built in or is equipped with an external DMA card.

ameco

E-X-P-A-N-D TRS-80 MEMORY

PURPLE

TRS-80 MODEL I, III All kits come with complete documentation

TRS-16K3 200ns (Model III) (8 ea. 5290N-3 Dynamic RAMs). . . \$5.95 TRS-16K4 250ns (Model I) (8 ea. 5290N-4 Dynamic RAMs).... \$5.49

TRS-80 COLOR AND COLOR II

TRS-64K-2 (8 each 4164-200 Dynamic RAMS)......\$7.95 New Models only -

TRS-Co-Co Includes (2) 50464's (41464's) Dynamic RAMs. \$10.95


TRS-80 MODEL 4, 4P AND 4D

Expands Model 4 from 16K to 64K or Model 4 (Gate Array \$7.95 Version), 4P & 4D from 64K to 128K (8 ea. 4164-200 Dyn. RAMs)

TRS-64K-2PAL Expands Model 4 (Non-Gate Array Version)..... \$14.95 from 64K to 128K (8 ea. 4164-200 Dynamic RAMs + PAL Chip)



M1008K



MOOOR

TRS-80 Model 100 · NEC · Olivetti

TRS-80 Model 100 8K Expansion -M1008K. \$19.95 ea. or 3/\$54.95

TRS-80 Model 102 8K Expansion -M1028K.....\$9.95

NEC Model PC8201A 8K Expansion NEC8KR...... \$19.95 ea. or 3/\$54.95

Olivetti Model M10 8K Expansion -OM108K......\$19.95 ea. or 3/\$54.95

TANDY 200 Tandy Model 200 24K Expansion M200R. \$59.95 ea. or 2/\$109.95

\$20 Minimum Order - U.S. Funds Only Shipping: Add 5% plus \$1.50 Insurance California Residents: Add 6%, 61/2% or 7% Sales Tax

Prices Subject to Change

Send stamped, self-addressed envelope to receive a Sales Flyer - FREE!





Send \$1.00 Postage for a FREE 1987 JAMECO CATALOG

c 1987 Jameco Electronics

5/87

1355 SHOREWAY ROAD, BELMONT, CA 94002 • PHONE ORDERS WELCOME 415-592-8097 Telex 176043

culator; on-line help; and transaction windows for recording checks, deposits, and regular or irregular payments. It lets you allocate transactions for both recordkeeping and tax purposes.

Your Money Manager can prepare, display, and print reports of your financial position at any time. A variety of graphs help you analyze current and projected trends. If you use the program to maintain accurate records throughout the year, you can enter the information into Your Income Tax.

Your Money Manager sells for \$89.95 and requires 128K, one disk drive, and DOS 2.0 or higher.

Contact Simon & Schuster Software, One Gulf + Western Plaza, New York, NY 10023, 212-373-8882.

Circle 554 on Reader Service card.

Financial Forecasting

Taxcalc's Business Planning Model for Forecasts and Projections is a spreadsheet template to help CPAs prepare cash flow, break-even analysis, budgeting, and other prospective financial statements. It uses what-if analysis that lets you compare several scenarios based on different assumptions about the future.

The template creates prospective financial statements that conform to the latest format and data-collection standards (effective Sept. 1, 1986) of the American Institute of Certified Public Accountants.

Business Planning Model for Forecasts and Projections lets you create monthly, yearly, or quarterly forecasts within a 12-month period. A goal-setting area helps you determine break-even points in an analysis, and a decisions area lets you manage surplus and deficit financing.

The template works with Lotus's 1-2-3 and any other spreadsheet that loads 1-2-3 files on an IBM PC or compatible. You can use the 1-2-3 graphics to create a graph of your analysis.

Business Planning Model for Forecasts and Projections requires two disk drives and 640K and sells for \$250. Contact Taxcalc Software Inc., 4210 West Vickery Blvd., Fort Worth, TX 76107, 817-738-3122.

Circle 556 on Reader Service card.

Statistical Forecasting

Walonick Associates has released a forecasting module that adds exploratory data analysis, time-series forecasting, and quality-control analysis to Statpac Gold, the company's statistical-analysis software.

The module provides graphics for time plots, 4253HT robust-smoothed time plots, box plots, aggregate box plots, spread-versus-level plots, and autocorrelation function plots. The Statpac Gold package contains three regression-modeling techniques. The module adds 11 forecasting methods: seven smoothing techniques, two methods of decomposition, and two ARIMA techniques.

The smoothing techniques include moving averages, exponential smoothing, harmonic smoothing, and the Holt's and Winter's methods. The module also provides Census X-11 and SABL (robust) decomposition methods for long-term seasonal forecasting, adaptive-filtering, and Box-Jenkins ARIMA programs.

Statpac Gold sells for \$595. Add \$195 for the forecasting module. Contact Walonick Associates, 6500 Nicollet Ave. South, Minneapolis, MN 55423, 800-328-4907.

Circle 558 on Reader Service card.

Hiring Software

The Logical Decision Assistant helps employment interviewers select the most qualified applicant by focusing attention on the five most critical elements of a position and comparing applicants to those elements. You choose the elements, which can include such qualities as education, communication skills, accuracy, and experience.

The program requires 256K and sells for \$395. A demonstration disk sells for \$25. Contact Young Associates, 15720

Winchester Blvd., Los Gatos, CA 95030, 408-395-6441. Circle 559 on Reader Service card.

Hard-Disk Security

Version 4.0 of the Onguard system operates as an extension of DOS, regulating each user's access to a MS- or PC-DOS hard drive. Onguard gives one person control over who uses the hard disk and what data and programs each user can access. It also provides a comprehensive audit trail, allowing the system manager to monitor hard-disk use.

Onguard 4.0 features revised documentation, drive A boot protection, the Privacy Plus encryption program, and the Master Key encryption-key recovery program.

Privacy Plus lets you encrypt your files and directories. Using English commands or full-screen pop-up menus, you can lock and unlock your data. Master Key lets the system manager decrypt encrypted data without disclosing the Master Key.

Onguard sells for \$295 from United Software Security Inc., 8133 Leesburg Pike, Vienna, VA 703-556-0007.

Circle 557 on Reader Service card.

Program-Development Screens

High Screen 3.4 is an enhanced program-development tool you can use with all programming languages. Its features include sophisticated screen generation; automatic field checking; and help, window, and pull-down menu management.

You can choose a field-byfield or full-screen mode for each data-entry screen, scroll vertically within a zone, and call High Screen functions from batch files or DOS.

High Screen does not generate code; it creates language-and program-independent screens and uses a resident module to interface these screens with the applications you've developed. Therefore, you can change screens without modifying the program, and you can use the same screen developed

while writing an application in one language to rewrite the program in another.

High Screen 3.4 is royalty free and not copy-protected. It sells for \$129, and registered owners of earlier High Screen versions can upgrade for \$20.

The High Screen Unloader uses a hierarchical structure to let you selectively unload resident programs from RAM. It's available for \$20 to High Screen users.

Contact Softway Inc., 500 Sutter St., Suite 222, San Francisco, CA 94102, 415-397-4666.

Circle 555 on Reader Service card.



The Mouse Base provides a non-skid surface on which to use your mouse.

Etc.

Mouse Base

Mouse Base is a durable nylon and sponge-rubber nonskid mouse pad that improves tracking and protects the mouse and the desk. It measures 11³/₄ by 8¹/₂ inches and sells for \$9.95 from Computer Coverup Inc., 2230 South Calumet, Chicago, IL 60616, 312-326-3000.

Circle 563 on Reader Service card.

PC Law

Lawlink is the American Bar Association's law-office software program that integrates several legal programs into a single-menu system. It also includes a communications package.

Lawlink lets lawyers create a series of customized menus and then switch between

such programs as a word processor and a data base. The communications element provides access to ABA/net and legal data-base services.

ABA members can buy Lawlink for \$60. It's \$120 for non-members. Contact the Law Office of the Future Project, American Bar Association, 750 North Lake Shore Drive, Chicago, IL 60611, 312-988-5026.

Ctrcle 560 on Reader Service card.

Star Gazing

Skyshot is a program that determines ground azimuths from observations of celestial objects. You plug in your measurements (from up to eight observations) and ephemeris values, and the program calculates the azimuth bearing.

Skyshot lets you choose any of three celestial observations methods: direct-altitude observation, hour-angle observation of sun, or polaris observations. The program

READER SERVICE CARD.



A wrist strap to prevent static charges.

works independently or as an accessory to MTI Software's Series 800, Series 2000, or Series 3000 survey packages.

MS-DOS and CP/M versions of Skyshot sell for \$125 from MTI Software, P.O. Box 1659, 600 B St., Santa Rosa, CA 95402, 707-523-1600.

Circle 567 on Reader Service card.

Get a Charge Out of This

Scooter Products' Anti-Static Wrist Strap is an elas-

tic fabric wrist band that you wear while working with sensitive chips and circuits to prevent static charges from affecting them.

The strap has a conductive inside surface connected to a 1-megohm resistor (for the wearer's protection) that, in turn, connects to a 10-foot, telephone-type coiled cord. A banana plug at the other end of the cord inserts into an alligator clip that you attach to a conductive work surface.

The Anti-Static Wrist Strap comes in small (Model SS801-S) and large (Model SS801-L) and sells for \$14.95 from Scooter Products, Ohm/Electronics Inc., 746 Vermont St., Palatine, IL 60067, 800-323-2727 (in IL, 312-359-6040). Circle 571 on Reader Service card.

Spike Out

The model MPS(22)-2 Portable Computer Protection System insulates your portable computer from ac and modem line spikes, electrical noise, RFI, and static. The unit provides standard and CEE-22 electrical sockets, a standard phone RJ-11 modular socket/plug, and a staticdischarge plate.

The MPS(22)-2 sells for \$185 from Electronic Specialists Inc., 171 South Main St., Natick, MA 01760 800-225-4876. Circle 564 on Reader Service card.

232×2

The Black Box 232 Line Booster receives and retransmits the 12 most commonly used signals of the RS-232C interface. This doubles the RS-232's specified 50-foot signaltransmission distance. The device is data-rate and data-format transparent, and you can power it from the interface or a detachable power supply.

The Centronics Line Booster does all that the Black Box does, and it accommodates the Centronics-compatible printer interface. It supports the interface's 16 most common signal lines and lets you

Circle 189 on Reader Service card.



Improved TABCO PARALLEL Printer Switch

connect 2 printers to one computer! PSM-C/2P - Manual

printer switch. Prolongs the life of your printer/ interface connectors. Saves time & money! Use your existing printer cable to connect TAB SWITCH to your computer. Comes complete with two 3.5' cables to connect your printers. Straightforward design makes it easy to set-up & use. 1 year limited warranty.

Other models available Dealer inquiries invited. \$2.50 Shipping/ Handling. Florida residents add 5% sales tax

See your dealer

ORDER TODAY Only \$69.95

Cables built-in (optional lengths available)

Nothing else to buy Fingertip control Call 1-800-874-1551 Just flick your switch

TAB SALES CO.

704 W. Michigan Ave. Pensacola, FL 32505

P.O. Box 8098

Ph: 904-438-6507

double the cable length to 10-15 feet.

Either device sells for \$99, and you install it in the center of the RS-232 or Centronics cable. Contact Black Box Corp., P.O. Box 12800, Pittsburgh, PA 15241, 412-746-5500.

Line Backers

The Networx Power Backers 330 and 450 provide uninterruptible power to protect computer data and memory against blackouts and power sags. They also contain fast-response circuitry that guards against surges, spikes, and radio-frequency and electro-magnetic interference. During a power failure, the Model 330 can restore power within 2 milliseconds, and the Model 450 can do so within 4 milliseconds.

Depending on how a system is configured, the Power Backers can maintain power for up to 30 minutes, giving you enough time to shut



Networx's Power Backers provide uninterruptible power.

down your system. The Power Backer sounds an alarm 2 seconds before its battery is exhausted.

The Model 330 provides a peak-output current of 6 amps and sells for \$499. The Model 450 provides a 9-amp peak-output current and sells for \$799. Contact Networx, 203 Harrison Place, Brooklyn, NY 11237, 718-821-7555.

Circle 569 on Reader Service card.

disks.

A box of 10 MF2-HD disks sells for \$69.95. For more information contact Maxell Corp. of America, 60 Oxford Drive, Moonachie, NJ 07074, 201-641-8600.

Circle 566 on Reader Service card.

1MB, 5\(\frac{1}{4}\)-inch disks and 1.6MB, 5\(\frac{1}{4}\)-inch and 8-inch

Bus Terminal

Bizcomp's external Intellimodem 2400 and its internal Intellimodem 2400 PC are fully Haves-compatible. 2,400-baud modems that include a bus so you can plug in future modifications. Both modems are also compatible with Bell 103/212/V.bis specifications and support 1,200 and 110-300 baud communications. They include audible call-progress monitoring with adjustable volume controls and loop-through RJ-11 connectors for connecting telephone sets.

These modems also feature

800 South 17 Box 246

Summersville, MO 65571 • (417) 932-4196
WE PAY UPS GROUND SHIPPING on PREPAID ORDERS.
PLEASE INCLUDE STREET ADDRESS for UPS DELIVERY

FOREIGN ADD 15% U.S. FUNDS.
MISSOURI RESIDENTS ADD 5% SALES TAX

Micro Disks

Maxell's MF2-HD high-density 31/2-inch, micro-floppy disk features 2-megabyte (MB) unformatted or 1.6MB formatted capacity. The disks use a thin coating of high-coercivity epitaxial magnetic material and are housed in a precision cartridge to reduce output fluctuation. They are software compatible with

Circle 152 on Reader Service card.

NEW PRINTERS ADDED! FIND YOURS BELOW. Good This Month	BBC	NE	SAL	E			EXA	CT RE	PLACE	MENTS
PRINTER MAKE, MODEL NUMBER Contact us if your printer is not listed. We have many more in stock. We can probably RELOAD your old cartridges.	RIBBON SIZE Inches by Yards	man	CARTR from the val sufacturers n our own s Ready to u	rious or made shop.	You SE CARTRI put OUR		rused us. WE NSERTS	DROI EXAC mad	RTS EZ-L P IN, NO W T REPLAC le in our ow dges NOT i	NDING! EMENTS n shop.
C ITOH Prowriter 1550-8510, NEC 8023-8025, APPLE DMP-IMAGEW	1/2 x 18	\$15/2	\$42/6	\$ 78/12	\$7/1	\$6 ea	2 or more	\$15/3	\$54/12	\$288/72
IBM PROPRINTER (Standard Paper) (4201) PC (Standard Paper) (5152)		\$18/2 \$14/2	\$51/6 \$36/6	\$ 96/12 \$ 66/12	\$8/1 \$7/1	\$7 ea \$6 ea	2 or more 2 or more	\$18/3 \$15/3	\$66/12 \$54/12	\$360/72 \$288/72
RADIO SHACK-TOSHIBA-COMMODORE-PANASONIC-RICOH Carbon Film - DWP 210, DIABLO HYTYPE II Black (1445)		\$18/3	\$60/12	\$342/72	\$5 ea 3-11	\$4 ea		\$24/6	\$45/12 \$42/12	\$252/72 \$234/72 \$234/72
DW II, DWP 410-510, RICOH 1200-1300-1600 Black (1419) Red, Green, Blue, Brown Colors (1419) Fabric (Long Life), DWP 210, DIABLO HYTYPE II Black (1458)	1/4 x 130	\$18/3 \$21/3 \$18/2	\$60/12 \$72/12 \$51/6	\$342/72 \$414/72 \$ 96/12	\$5 ea 3-11 \$6 ea 3-11 \$8/1		12 or more 12 or more 2 or more	\$24/6 \$30/6 \$21/3	\$42/12 \$54/12 \$78/12	\$234/72 \$234/72 \$432/72
DW II, DWP 410-510, RICOH 1200-1300-1600 Black (1449) DMP-100, LP VII, COMMODORE 1525, GORILLA BANANA (1424)	1/4 x 25	\$18/2 \$18/2	\$51/6 \$51/6	\$ 96/12 \$ 96/12	\$8/1			\$21/3	\$78/12	\$432/72
DMP-200, 120, (430 Inserts & Reloads Only) (1296) (1483) DMP-400-420, LP VI-VIII, PANASONIC KXP-130-109 DMP-500 (130 Inserts & Reloads Only) (1236) (1482)	5/16 x 14	\$20/2 \$15/2 \$22/2	\$57/6 \$42/6 \$63/6	\$108/12 \$ 78/12 \$120/12	\$7/1 \$7/1 \$7/1	\$6 ea \$6 ea	2 or more 2 or more 2 or more	\$15/3 \$15/3 \$15/3	\$54/12 \$54/12 \$54/12	\$288/72 \$288/72 \$288/72
DMP-2100, TOSHIBA P1340-1350-1351-351 (1442 DMP-2200, C ITOH 3500 (1233)	1/2 x 20 1/2 x 52	\$15/2	\$42/6 \$35 eac	\$ 78/12 h	\$7/1 \$18/1	\$6 ea \$16 ea	2 or more 2 or more		\$54/12 \$57/6	\$288/7: \$108/1:
LP III-V, CANON A 1200 (New Only) (½ x 5) (1414)		\$15/2	\$42/6 \$63/6	\$ 78/12 \$120/12	\$7/1	\$6 ea	2 or more	\$15/3	\$54/12	\$288/7
EPSON LQ 1000 MX-FX-RX 70-80-85, LX 80-90 (5/16 x 7) MX-FX-RX 100-185-286, LQ 800 (1/2 x 18) LQ 1500 (1/2 x 14) DX 20-35 Carbon Film (Multistrike), OLIVETTI ET-121-221	1/2 x 18 1/2 x 20 1/2 x 30 5/16 x 290	\$22/2 \$14/2 \$18/2 \$21/3		\$ 66/12 \$ 96/12 \$ 414/72	\$7/1 \$8/1	\$6 ea \$7 ea		\$15/3 \$18/3	\$54/12 \$66/12	\$288/7 \$360/7
NEC Spinwriter-Carbon Film - 2000-3500 (Reloads BCCOMPCO Only) - 5500-7700 (Can Reload Most Types)	5/16 x 145	\$18/3 \$18/3	\$60/12 \$60/12	\$342/72 \$342/72	\$5 ea 3-11 \$5 ea 3-11	\$4 ea	12 or more	\$24/6 \$24/6	\$42/12 \$42/12	\$234/7 \$234/7
- 5000-7700 (can Reload All) - 5500-7700 (Can Reload All)	1/4 x 145 1/2 x 14 1/2 x 13	\$18/2 \$15/2	\$51/6 \$42/6	\$ 96/12 \$ 78/12	\$8/1 \$8/1	\$7 ea \$7 ea	2 or more 2 or more	\$15/3	\$54/12 \$54/12	\$288/7 \$288/7
Pinwriter P1-P2-P6, P-5 (1/2 x 14) P3-P7	1/2 x 20 1/2 x 27	\$25/2 \$30/2	\$69/6 \$84/6	\$126/12 \$156/12	\$7/1	\$6 ea \$7 ea	2 or more 2 or more	\$15/3	\$54/12 \$66/12	\$288/7 \$360/7
OKIDATA Pacemark 2350-2410 Black Microline 182-183-192-193 (Call for 292-293 prices) ML-80-82-83-92-93 (Call for ML-84 Prices)	1/2 x 100 Inker Loop 1/2 x 16	\$20/2 \$21/6	\$25 eac \$57/6 \$36/12	\$108/12 \$198/72	\$20/1 SE	ND CHE	2 or more CK, MONEY			
MANNESMAN-TALLY MT-160, RITEMAN INFORUNNER (Inker Loop	9mm x 11	\$19/2	\$54/6	\$102/12	VISA		SCCO			daster Card

9mm x 13

Inker Loop

5/16 x 82

5/16 x 17

\$20/2

\$16/2

\$20/2

\$18/3

\$15/2

\$57/6

\$57/6

\$60/12

\$42/6

\$108/12

\$ 84/12

\$108/12

\$342/72

\$ 78/12

BROTHER HR-15-25-35

COMREX DX-15. II

MT-180-290


PANASONIC KXP-1080-1090-1091-1092-1592-1595

-SPIRIT 80 (SP80) COMMODORE 1526 (Multistrike)

Fabric

Carbon Film (Multistrike)

(Call for Comrex 420 Prices)



The Intellimodem 2400 is fully Hayes-compatible.

Bizcomp's adaptive echocanceller technology, which removes echo from the phone lines but retains data clarity when the signal you're receiving is weak.

The Intellimodem 2400 and 2400 PC sell for \$599 each and include a telephone network cord, user guide, and two-year limited warranty. For more information contact Bizcomp Corp., 532 Mercury Drive, Sunnyvale, CA 94086, 408-733-7800.

Ctrcle 561 on Reader Service card.

Six Line Filters

PMC Industries' six ac line filters suppress noises from 55-70 dB and high-voltage transients/surges from line to line and line to ground. The units also feature 6-foot shielded line cords (where used), filters enclosed in individual modules, lighted on/off switches, resettable circuit breakers, and multiple filters.

Some units have suppression banks of outlets.

Prices for these line filters range from \$79.95-\$249. They are available from PMC Industries Inc., 6335 Ferris Square, San Diego, CA 92121, 800-242-9353.


Circle 570 on Reader Service card.

Sidekick

The System Sidekick mounts on the side of your computer work station to hold the system unit vertically and give you more work space. Sidekick's steel frame can be adjusted from 4 to 7 inches and has a textured-putty finish.

It comes with a clampmounting system, and screw mounts are available. The System Sidekick sells for \$79.95 from Lintek Computer Accessories, 426 North Park NE, Grand Rapids, MI 49505, 800-822-9110.

Ctrcle 565 on Reader Service card.



PMC's ac line filters suppress notses.

Classifieds

GET THE ATTENTION YOU DESERVE

Tell more than 200,000 dedicated, interested TRS-80 users about your product or service with an efficient and economical **80 Micro** classified ad.

You'll reach the most people in the market for the least amount of money!

With 80 Micro's well-established audience of involved buyers, sellers, and swappers, your ad is bound to get fast results!

For more information, write to:

80 Micro

Attn. Classified Manager 80 Elm Street Peterborough, NH 03458

Circle 227 on Reader Service card.

Pickles & Trout

available from

TriSoft

All your Tandy Model-II, -12, -16, and -6000 CP/M-2.2 and CP/M-68K needs!

From:
TriSoft
1825 East 38½ St.
Austin, Texas 78751

1-800-531-5170 (512) 472-0744

HIIIIDIGITAL VISIONIIIH

NEW FOR TANDY 1000/1200 COMPUTERS

COMPUTEREYES

Finally — an inexpensive way to capture real-world images on your computer's graphics display! COMPUTEREYES'" interfaces to any standard video source (video camera, VCR, etc.) to capture images for use with graphics programs, desktop publishing, picture databases, entertainment, etc. Hundreds of applicationsl

COMPUTEREYES" features include.

- · Half-card size
- · Simple menu-driven software control of all functions-capture routines, brightness and contrast adjustments, disk access
- Keyboard-controlled video switching to allow previewing the video source on the computer monitor
- . Works with standard CGA or EGA graphics capabilities - no additional boards needed
- · Images compatible with almost all graphics handling programs
- Available as a complete system including quality video camera

See your dealer or order direct. Mass. residents add 5% sales tax. Mastercard, Visa accepted. To order, or for more information, write or call:



ONLY \$249.95

Available for

- TANDY and IBM PC compatibles
- · Apple II, II+, Ile and Ilc
- Commodore 64/128
- Atari 800/800XL/130XE
- Atari ST (\$249.95-full) color digitizer)

Consult factory for pricing

66 Eastern Avenue

DIGITAL VISION, INC. Dedham, MA 02026

(617) 329-5400

Circle 188 on Reader Service card.

Model III, 4 & MS/DOS Stuff!

Special Offer: Buy any two versions to just \$59.95

Complete Business Graphics Toolkit Automatically chart spreadsheet files or for the Model 4 (TRSDOS), Model 4 (CP M) and the Model III.

you'll ever need for your Model III or 4 imputer. Hi-Res board not required

Freehand drawing: Draw lines, boxes. circles, and write on the screen in large characters. Full block operations are supported - move, fill, copy and more!

Business graphics: Create horizontal and Special offer - buy any two versions at vertical bar charts, pie charts and xy plots. the same time for just \$59.95

use hand-entered data

Slide shows: Sequence your graphics REMBRANDT is the only graphic software on-screen using eleven cinematic special effects like wipes, fades and spirals

> Hard copy: Print your graphic screens on most dot-matrix and daisy wheel printers. REMBRANDT is only \$39.95 and is available for the Model 4 TRSDOS Model 4 CP/M or Model III — please specify.

TWIST & SHOUT!

Two great pieces of software at one low price! TWIST lets you print out your spreadsheets (or any file) sideways on your dotmatrix printer. No more culting and pasting to put together a fragmented output SHOUT prints giant banners in letters from two to eight inches high using four special type styles Supports most printers including

Anadex, Apple, C. Iloh. Centronics, DEC, Data Products, Epson, HP, IBM, IDS, MPI, NEC. Mannesman Tally. Okidata, Radio Shack Smith Corona, Toshiba and more. Write for list



SHOUT YOUR MESSAGE IN A BANNER! umin. \$34.95 Special offer: buy any two versions for just \$49.95 available for all MSDOS, TRSDOS & CPM computers



Woodland Hills, CA 91364

Express Order by mail or call our 24 hour toll-free order line from the US or Canada 22458 Ventura Blvd., Suite E

800-628-2828 (Ext. 918)

We accept VISA. MasterCard and American

818-716-1655 (9-5 PST) Add \$4 per order postage Overseas \$12

NEW PRODUCTS

New Products Index

MS-DOS

Reader Service Number	ce Company	Page	
550	Addison-Wesley Publishing Co.	115	
551	Ingram Software Inc.	115	
552	RHM & Associates	115	
553	Simon & Schuster Software	115	
554	Simon & Schuster Software	115	
555	Softway Inc.	118	
556	Taxcalc Software Inc.	118	
557	United Software Security Inc.	118	
558	Walonick Associates	118	
559	Young Associates	118	

Etc.

Reader Service Number	Company	Page
560	American Bar Association	118
561	Bizcomp Corp.	120
562	Black Box Corp.	119
563	Computer Coverup Inc.	118
564	Electronic Specialists Inc.	119
565	Lintek Computer Accessories	121
566	Maxell Corporation of America	120
567	MTI Software	119
568	Near Future Computer Co.	122
569	Networx	120
570	PMC Industries Inc.	121
571	Scooter Products	119

New Products listings are based on information supplied in manufacturers' press releases. 80 Micro has not tested or reviewed these products and cannot guarantee any claims.

DIFFERENT TRACK

The Key That Doesn't Stick

The WP key is a simple way to write-protect your disks: a plastic strip that you stick into the corner of a 51/2-inch disk to fill the write-protect slot. When you want to remove the protection, just slide the key out-no tearing a sticky tab and scraping off the leftover pieces, no paper tabs lost inside you disk drive, no accidentally damaged disks.

Want to protect the same disk again? Slide the key back in. They're reusable and guaranteed for life. A package of 10





WP key write-protection.

keys sells for \$1.39, plus 50 cents for shipping, which covers up to five packages. Write to Near Future Computer Co., P.O. Box 1726, Walla Walla, WA 99362.

Circle 568 on Reader Service card.

THEGASSIFIED

BUSINESS OPPORTUNITIES

PERSONAL COMPUTER
OWNERS CAN EARN
\$1000 to \$5000 monthly
selling simple services
performed by their computer. Work at home in
spare time. Get free list of
100 best services to offer,
Write: A.I.M.A.G., P.O.
Box 60369, San Diego, CA
92106-8369.

SOFTWARE

Profile users! PROAID III+/4+ provides many features for reports from single or multiple files. Model III/4's. \$49. Clay Watts Software, 68C North Loop, Cedar Hills, TX 75104. 214-291-1171.

THE STOCK EXCHANGE

-The ultimate stock market challenge! 1000/1200/3000...\$34.95-NY add 8.25%. Praxis Software, PO Box 2307, Grd Ctl Sta, NY NY 10163. 1-800-PRAXIS-S, NY 1-212-365-2170.

WORD PROCESSING-EXPRESS, comparable to all top-of-the-line word processors. . .\$49.95. Features: Indexing, Footnoting, Mailmerge, Spellcheck, Graph Generation, Calculator and more! Easy! Call for info! 1000/ 1200/3000/PC/MS-DOS, NY add 8.25%. Praxis Software, PO Box 2307, Grand Central Station, NY, NY 10163. 1-800-PRAXIS-S, NY 1-212-365-2170.

TANDY ORIGINAL SOFT-WARE 60-90% off models 1/3/4, 2/12/16/160, 100, PC 1/2/3/4, CoCo, MC10. \$1.00/Large SASE for list: Software Box 1013, Brice, Ohio 43109 LOW VISION EDITOR I/III Graphic Fonts \$20.00 (201) 277-3365.

\$\$\$WIN with Thoroughbred, Harness, Greyhound Handicapping Software. . \$29.95, enhanced . . . \$49.95. Professional Football Handicapping System. . . \$39.95. Free information. Software Exchange, PO Box 5382M, W. Bloomfield, MI 48033. (800) 527-9467.

Make Great Connections!
Omniterm Professional
Communications Software for TRS-DOS and MSDOS. Ask your Radio
Shack Dealer or contact
Lindbergh Systems, P.O.
Box 3604, Ann Arbor, MI
48106, 313-971-9733.

QUALITY MUSIC SOFT-WARE Create melodies and lyrics on your Tandy 1000, IBM PC, or compatible. Easy-to-use, fun, and educational. \$54.95. Please write or call for details. Questar Products Ltd., 1252 Westover Trace, Acworth, GA 30101, (404) 429-1196.

Templates of Doom, makes a game of learning Lotus 1-2-3. \$49.95 plus \$2.50 8/H. 30 day money-backguarantee. Solar Systems Software, 8105 Shelter Creek, San Bruno, CA 94066, (415) 952-2375.

COMMUNI-CATIONS

NationServ BBS (618) 847-2291.

Telecommunicator BBS 717-632-4385.

CO-CO PERIODICALS

ONE THOUSAND MAGAZINE "Especially For Your Tandy 1000!"

Monthly support for your Tandy 1000 personal computer is here! Beginner's Luck, MS-DOS, Basic Listings, Editorials and reviews are just SOME of the topics covered on a monthly basis in One Thousand Magazine! We also have a software library available to all subscribers!

Available on newstands everywhere! 12 Monthly Issues: \$20 Send to:

One Thousand Magazine 2153 Muren Blvd, Suite A Belleville, II 62221-4136 618-277-3526

COCO-ADS, Color Computer Magazine with programs, articles, reviews, public domain programs, and more. Send for sample issue. PD Software PO Box 13256-M Houston, TX 77219.

FOR SALE

Complete Model 1 System. Call (212) 777-0434.

CONVERSION SERVICES

Media Conversion for Tandy Models to over 800 systems including Magtape, Micro Computers, Mini Computers, Word Processors and Typesetters. Pivar Computing Services, Inc., 165 Arlington Hgts. Rd., Number 80, Buffalo Grove, IL 60089. 312-459-6010.

HARDWARE

Clone Kits, Modems, Hard Drive Kits, disk drives, pritners, memory, and IC's. Distributor pricing to end users and dealers. For catalog call 1-800-833-2600, in Ohio call 513-531-8866. FREE SHIPPING.

MEGABYTE EXPANSION BOARD FOR MODELS 4/4P. \$119.95 with RAM-Drive software. Memory, shipping extra. Details: RAI, Box 7084, Hampton, VA 23666.

BARCODE READERS for IBM compatibles. Printing software included. Satisfaction guaranteed. \$349.00 OEM/DEALER inquiries invited. LAGADO SOFTWARE (916) 965-0856.

5MH: SPEED UP FOR MODELS 4/4P. \$24.95, (\$2 S&H). Non-gate array models. Details, contact: RAI, Box 7084, Hampton, VA 23666.

issue

Get the attention you deserve. For only \$5 per word, your ad will be seen by over 100,000 dedicated TRS-80/Tandy users. Ads must be received by the 20th of the month 3 months prior to publication date. Send yours today. Consecutive 3 month prepay Special \$5/Word.

Total	Number	of	Words	×	\$ 5/issue =	

Make Checks Payable to 80 Micro NO AD ACCEPTED WITHOUT PAYMENT

Classifieds, c/o MCSS 11 Northeastern Blvd., Suite 210 Nashua, NH 03062

Shhh! Top Secret

he CIA has nothing on 80 Micro readers (as far as I know). Your cryptography programs represented nearly every cipher known to science. The ones I missed were Bacon's thinking-digital-inthe-17th-century binary cipher and the infamous Nihilist transposition.

Transpositions that mix up plaintext weren't popular at all. Steve Woicik (Turlock, CA) sent the only one, but he gets a bumper sticker anyway for the nicestlooking display.

Naturally, substitution ciphers were well represented. Your favorite method, though, was displacement. In a displacement, you put the characters you want to deal with on a wheel and, to find a character to stand for the original, spin the wheel. The trick is how you spin it. The bravest schemes, which put a different spin on each character, depend on keys, New Math, and purely arbitrary factors like the phases of the moon.

T.J. Reibold's (Superior, WI) big-league math includes multiplication by a matrix. The ciphers you liked best, however, use a key modified by the character's position in the file.

Evan Hand (Loogootee, IN) used two keys for extra security and then each character generated to make a new key for the next (see Program Listing 1). His program demonstrates XOR, another favorite device computers bring to cryptography. XOR helps hide the regularity of mathematical formulas and is naturally reversible, restoring the original the second time you apply the key. Evan also used the Model 4's System command to direct his program's output, as well as CVI and MKI\$ to process two characters at a time.

Another cipher fit for a computer uses a "non-repeating key" - a sequence like the one RND produces. Professionals consider it virtually unbreakable, and I hear the KGB likes it.

John Higgins (Davenport, IA) used this device in a nifty one-liner for Color Computers (see Program Listing 2). Color Basic lacks XOR, so John made one out of Not, And, and Or. To restore the plaintext, you must reproduce the random sequence by using the key to "seed" the pseudo-random-number generator. In Color Basic, a negative argument in the RND function plants the seed.

A good cipher considers the medium as well as the method. Gary Clark (Bethesda, MD) pointed out that killing a file deletes it from the directory but leaves it otherwise intact. He wrote over the original file by opening it for sequential input and output at the same time. It works! In random access (the ordinary way to overwrite a file), the unused portion of the last record is dangerous. If it has the simple pattern of a newly formatted disk when you apply your cipher, you leave an obvious clue.

David Gish (Memphis, TN), aware of the trap, had his program (see Program Listing 3) look for the standard end-offile marker (26) and stop. David also allowed for a long, non-numeric key, on which he used Basic's single-precision notation to apply the high-power math to get a seed for his non-repeating key. Since TRSDOS Basics do not have a function for seeding the RND routine with a predetermined value, David poked the seed directly into low memory. He avoided string manipulation and Model III garbage collection by poking the random-access buffer. Nice job.

Lost and Found

I":SYSTEM NS

I've lost something in an ordinary text file produced by a no-frills text editor-just everyday text and a few carriage returns. Help me find it. We'll trade T-shirts and bumper stickers for the cleverest search routines. Include any features you've seen in fancy word processors, such as searches by word or character, wild-card searches, search and destroy, and search and replace. Fit your solution into two lines of Basic and have fun

The Rules:

- 1. Write your solution(s) in any TRS or Tandy Basic, except Pocket Computer Basic.
- 2. This month's entries must reach us by May 15, 1987. This doesn't give everyone the same amount of time, we know, and we apologize to our overseas readers especially.
- 3. This month's winners will appear in the August 1987 issue.
- 4. Employees of CW Communications are not eligible.
- 5. Send your entry to: 80 Micro, Fine Lines, 80 Elm St., Peterborough, NH 03458. We cannot return entries.
- 6. Specify your T-shirt size. Bumper size not required.

Harry Bee is a free-lance writer, puzzle creator, programmer, and dreamer. Contact him at P.O. Box 567, Cornish, ME 04020.

Program Listing 1. Evan Hand's doubly keyed Model 4 combination.

10 CLS:DEFINT A-Z:LS=CHR\$(13):PS="link *do *pr":WHILE S\$="" OR D\$="" OR (K OR M) <1 OR (K AND M)=0:INPUT"Source file >";S\$:INPUT"Cipher file >";D\$:INPUT"Key, Cipher key (1 - 32767)>";K,M:WEND:INPUT"Copy to printer (Y/N)>";Y\$
20 PRINT LS*Processing: "S\$:OPEN"D",1,S\$,2:FIELD 1,2 AS A\$:OPEN"D",2,D\$,2:FIELD 2,2 AS B\$:WHILE LOC(1):LOF(1)-1:GET 1:V=CVI(A\$):V=V XOR M:M=(V-M) XOR K:LSET B\$= MKI\$(V):PUT 2:WEND:CLOSE:N\$="reset *do":PRINT L\$"Reading: "D\$:IF Y\$<>"Y" THEN P\$ 30 K=0:M=0:WHILE (K OR M)<1 OR (K AND M)=0:INPUT*Key, Cipher key (1 - 32767)>";K
,M:WEND:PRINT:OPEN*D",1,D\$,2:FIELD 1,2 AS A\$:SYSTEM P\$:WHILE NOT(EOF(1)):GET 1:V
=CVI(A\$):V=V XOR M:M=((V XOR M)-M) XOR K:PRINT MKI\$(V);:WEND:CLOSE:PRINT L\$*Done

Program Listing 2. John Higgins's CoCo cryptographer.

Ø CLS:INPUT"IN,OUT,KEY";I\$,O\$,K:C=RND(-ABS(K)):OPEN"D",#1,I\$,1:FIELD#1,1 AS A
\$:OPEN"O",#2,O\$:CLOSE 2:KILL O\$:OPEN"D",#2,O\$,1:FIELD#2,1 AS B\$:FOR I=1 TO LO
F(1):GET#1,I:A=ASC(A\$):C=RND(31):LSET B\$=CHR\$(NOT(AANDC)AND(AORC)):PUT#2,I:PR INT#D, B\$: : NEXT : END

Program Listing 3. David Gish's complete cryptographer for the Model III.

- 1 CLEAR500:DEFINTJ-N:CLS:PRINT"CIPHER 1.0":INPUT"File, Key";F\$,K\$:X=1:J=VARPT R(X):FORN=1TOLEN(K\$):X=X*ASC(MID\$(K\$,N,1))+N:POKEJ+3,128:NEXT:FORN=0TO2:POKEN+16554;PEEK(N+J):NEXT:OPEN"RO",1,F\$:L=LOF(1):IFL=0,CLOSE:ENDELSEPRINT"Length=""""L""coeta-1
- 2 FIELD1, lasa; J=VarPtr(A\$): J=PEEK(J+1)+256*PEEK(J+2): DEFFNX(A,B)=(AORB) ANDNO T(AANDB): FORN=1TOL: GET1,N:PRINT@192, "Sector: "N;:FORK=0T0255:M=PEEK(J+K): IFM=2 6THENPUT1, N: CLOSE: ENDELSEM=FNX (M, RND (255)): IFM=26THEN3ELSEPOKEJ+K, M 3 NEXT: PUT1, N: NEXT: CLOSE

End

Circle 397 on Reader Service card

"Dac-Easy Base Lives Up to Its Name, Sets New Low-Cost DBMS Standard."

PC Magazine March 10, 1987





A Powerful Relational Database That's Easy To Learn, Versatile, Very Affordable, And Much More.

Dac-Easy Base is indeed both powerful and easy to use. It offers a multitude of unique features to help you organize, locate, and sort all kinds of alphabetic and numeric data. Dac-Easy Base continues the low price/high performance tradition of the Dac-Easy Series. With worldwide sales of over 300,000 systems, Dac-Easy has become the new leader in software designed for small businesses.

Flexible Menu System

Dac-Easy Base is actually two systems in one. If you are a novice you will appreciate the special Beginner Menu which contains the most commonly used features for creating, editing, and printing files. The more experienced database user will find the Advanced Menu allows instant access to each and every one of the powerful routines. In both menus, you are only a keystroke away from the context-sensitive help screens. The help screens in Dac-Easy Base are so complete you may never have to consult the accompanying 200 page manual.

Easy File And Report Creation

Design professional-looking data input screens without leaving the menu structure. There is no need for complex programming. Once created, the edit screen allows you to input and edit your information in a matter of minutes. Also attach special notes to any of your records with the built-in MemoWriter. The MemoWriter is the perfect way to attach specific information to a single record. Custom reports are easy to create without using the available

programming language. Column or page-style reports can be created quickly, and viewed on your computer screen or printed to paper. As with all reports generated by Dac-Easy Base, you can select which records will be included in your report and how they will be sorted. Special headings and subtotals can be added to give you the exact information you need.

Great For Advanced Users

Yes, Dac-Easy Base is easy to use, and it is also very powerful. An unlimited number of records with up to 60 fields per record, ability to access up to three files at a time, date arithmetic capability, formula fields for calculations within files, dynamic abbreviations, and keyboard macros

are just a few of the powerful features available at your fingertips. Dac-Easy Base can read and convert dBASE Il files and can run DBASE II programs.



30 Day Money-Back Guarantee

Dac offers a 30 day unconditional guarantee on all products bought directly from Dac Software (less shipping charges). There is a \$10.00 restocking fee if the disk envelope is opened.

Minimum Hardware Requirements:

Dac Software, Inc.

IBM or other compatibles, 256K memory, MS-DOS or PC-DOS 2.0 or later, two DSDD drives, color or monochrome monitor.

IBM and PC-DOS are registered trademarks of International Business Machines. MS-DOS is a trademark of MicrosSoft Corp. dBASE II is a trademark of Ashton-Tate, Inc. Dac-Easy and Dac-Easy Base are trademarks of "Dac-Easy Base is similar to dBASE II in appearance, yet it improves upon it in ease of use, system limits, on-line and contextual help, numeric accuracy to 15 digits, security by password, storage of more and larger memory variables, and on-screen report layouts. The program can interface with dBASE II files and emulate its dot prompt, though Dac-Easy's menus are the better

Everyone will be pleasantly shocked by its \$49.95 price."

PC Magazine


To Order Call Toll Free 1-800-992-7779

(In Texas Call 1-214-458-0038)

and the second second
Mail to: 🕏 dac software, inc. 4801 Spring Valley Rd., Bldg. 110-B Dallas, TX 75244 (Ph. 214-458-0038)
Yes, please rush me copies of Dac-Easy Base today. I have enclosed \$49.95 (Texas residents add 71/4% sales tax) for each copy + \$7.50 for shipping.
Name
Company
Address
City
State Zip
Phone
Computer Brand
* * * * Method of Payment * * * * Check Money Order VISA AMEX MC
Account #
Expires
Signature
CODE 754

Introducing the Most Powerful Business Software Ever!

FOR YOUR IBM • APPLE • MAC • TRS-80 • KAYPRO • COMMODORE • MSDOS OR CP/M COMPUTER*



Each VERSABUSINESS module can be purchased and used independently, or can be linked in any combination to form a complete, coordinated business system.

VERSARECEIVABLES"

VERSARECEIVABLES" is a complete menu-driven accounts receivable, invoicing, and monthly statement-generating system. It keeps track of all information related to who owner you or your company money, and can provide automatic billing for past due accounts. VERSARECEIVABLES" prints all necessary statements, invoices, and summary reports and can be linked with VERSALEDGER II" and VERSALENENTORY."

VersaPayables™

\$99.95

VERSAPAYABLES" is designed to keep track of current and aged payables, keeping you in touch with all information regarding how much money your company owes, and to whom. VERSAPAYABLES" maintains a complete record on each vendor, prints checks, check registers, vouchers, transaction reports, aged payables reports, vendor reports, and more. With VERSAPAYABLES", you can even let your computer automatically select which vouchers are to be paid.

VERSAPAYROLL**

VERSAPAYROLL**

VERSAPAYROLL**

is a powerful and sophisticated, but easy to use payroll system that keeps track of all government-required payroll information. Complete employee records are maintained, and all necessary payroll calculations are performed automatically, with totals displayed on screen for operator approval. A payroll can be run totally, automatically, or the operator can intervene to prevent a check from being printed, or to alter information on it. If desired, totals may be posted to the VERSALEDGER IT* system.

VERSAINVENTORY"

VERSAINVENTORY" is a complete inventory control system that gives you instant access to data on any item. VERSAINVENTORY" keeps track of all information related to what items are in stock, out of stock, on backorder, etc., stores sales and pricing data, alerts you when an item falls below a preset reorder point, and allows you to enter and print invoices directly or to link with the VERSARECHVABLES" system. VERSAINVENTORY" prints all needed inventory listings, reports of items below reorder point, inventory value reports, period and year-to-date sales reports, price lists, inventory checklists, etc.

50 N. PASCACK ROAD, SPRING VALLEY, N.Y. 10977

VERSALEDGER II

VERSALEDGER II™ is a complete accounting system that grows as your business grows. VERSALEDGER II™ can be used as a simple personal checkbook register, expanded to a small business bookkeeping system or developed into a large corporate general ledger system without any additional software.

• VERSALEDGER II™ gives you almost unlimited storage capacity (300 to 10,000 entries rer month, depending on the system),

• stores all check and general ledger information forever,

• prints tractor-feed checks,

• handles multiple checkbooks and general ledgers,

• prints 17 customized accounting reports including check registers, balance sheets, income statements, transaction reports, account listings, etc.

listings, etc.

VERSALEDGER II comes with a professionally-written 160 page manual designed for first-time users. The VERSALEDGER II manual will help you become quickly familiar with VERSALEDGER II using complete sample data files supplied on diskette and more than 50 pages of sample printouts.

FOR TRS-80 MODEL OWNERS ONLY!

TRS-80 owners only may now take 50% off our listed price of any module(s) from our VersaBusiness Series. All sales are final (our normal 30-day money back guarantee does not apply to sale items).

To Order:

Write or call Toll Free Other inquiries call 914-425-1535

- add \$4.95 for shipping in UPS areas
- add \$5.95 for C.O.D. or non-UPS ar add \$6.95 to CANADA or MEXICO
- add proper postage elsewhere
 DEALER INQUIRIES WELCOME

1-800-431-2818

(Outside NY State)

1-800-331-0362

(Inside NY State)



