



T & D SUBSCRIPTION SOFTWARE

File Name	English Name	PMODE	PCLEAR	LOCATIONS
BASIC	Basic Conversions	0	1	CTR-80A CCR-81 40*194-319 20*129-265
FIN ADV	Financial Advise	0	1	57*209-331 30*142-281
CASTLE	Castle Storm	0	1	89*232-349 50*165-308
DOSCLEAN	Dos Head Cleaner	0	1	100*242-356 57*175-318
COCOTERM	Coco Terminal	0	1	107*248-362 62*181-327
CRAWLER	Crawler	3	4	117*258-369 68*191-339
WARCASTL	War Castle	0	1	127*266-376 75*200-351
SKYFIRE	Sky Fire	0	1	141*276-385 86*212-366
EZBASIC	Easy Basic	0	1	155*287-393 96*224-381
DOTS	Dots	1	2	161*291-397 101*229-389

If, while loading or running a program, you get a FC, OM, or SH error, you probably have to enter the PMODE and PCLEAR values for the program from the keyboard. The label on the tape also contains the PMODE and PCLEAR values. Locations for the programs are set for the Radio

Shack CTR80. Your locations may vary slightly. We try to put as many duplicates of the programs on tape as possible. If the first copy does not load, try the second copy, or if it has one, the third. If all three do not load, then send it back for prompt replacement.

Remember, the first program on this tape is our Intro program. 16K users should PCLEAR1 before loading. If you have anything to sell, trade, or announce please let us know for our 'CHATTER' column.

On the January 1984 issue, we left out the start, save and execute addresses of the program 'FORCFELD'. To save this program to tape or disk enter (C)SAVEM'FORCFELD',9728,11954,9728.

1. BASIC CONVERSIONS - This program will cross reference the commands of the color computer with 7 other popular computers. They are 1. Texas Instruments 99/4, 2. Tandy TRS-80C (ECB), 3. Tandy TRS Model II, 4. IBM Personal Computer, 5. Commodore Pet, 6. Atari 400/800, 7. Apple II.

2. FINANCIAL ADVISE - This program is designed to give you some financial information that you might not be aware of. The subjects talked about are consumers credit rights, establishing credit, credit tips, how to help kids learn about money, Psychologist analyze buying addicts.

3. CASTLE - Try to defeat the evil castle as it hides behind its moving wall. When the time is right, chip away at its wall and fire your energy cannon. Beware of the castle's seeking missiles.

4. DISK DRIVE HEAD CLEANING - Some disks are only recommended for 13 cleanings. With this program, the head moves over the entire area of the disk, covering all of the tracks. Your drive head won't last any longer, but the cleaning disk is good for 100 uses, not 13.

5. COCO TERMINAL - Use this terminal program to communicate with other computers through a phone modem or direct connection.

Note: Before loading the next program, please turn your computer off and on.

6. CRAWLER - Enjoy an old classic computer game with some of our own variations. Use the arrow keys to guide your randomly growing snake through various levels.

Note: The next four programs are machine language. Enter CLOADM instead of CLOAD and EXEC instead of Run.

7. WAR CASTLE - Now two players can simultaneously enjoy a fast machine language game. To block the fireball, we found it is easiest to move your joystick from the top left corner to the lower right corner. To save this program, enter (C)SAVEM"WARCASTL", 10000,15568,10000.

8. SKY FIRE - Use your joystick to aim your energy cannon at the floating "Sky Junk" up ahead. If you do not have a disk drive, you might want to enter Pokel4154,192:Pokel4155,0 to give you more sky junk to shoot at. To save this program, enter (C)SAVEM-"SKY FIRE",10000,15000,1000.

Note: Before loading the next program, please enter Clear 200, 15582.

9. EASY BASIC - This utility allows basic commands to be entered with two keystrokes. You are allowed to define 26 keys A to Z. Simply LOADM this program and exec. Hit the right arrow key and redefine any or all 26 characters. You can save your new version at any time. To reproduce the commands, hit the down arrow key and any A to Z key simultaneously. This utility can save you a lot of time in entering programs. To save this program, enter (C)SAVEM"EZBASIC",15582,16363,15582.

10. DOTS - This program lets you create interesting 3-D like patterns by plotting a Sine Wave. The following keys will change the Sine Wave pattern: The four arrow keys, the 1, 2, and 3 keys, the clear key, and the break key. To save this program, enter (C)SAVEM"DOTS",9728,13151,9728.

If you have problems loading the programs try changing the volume on your tape recorder. If you have any questions, problems, solutions or Chatter, please write to us. If you have any uncopyrighted programs that you want to show us, we will be glad to see them. Send them in and if we like them, we will make you an offer.

Until next month.....