T & D SUBSCRIPTION SOFTWARE

File Name	English Name	PMODE	PCLEAR	LOCA	
				CTR-80A	
LIGHTCYC	Light Cycle	4	4		23 - 168
PAINT		3	4		28 - 174
		1	5		41.190
GUITARN	Guitar Notes	4	4		49.201
MLDISKAN	ML Disk Analyzer	0	1	96.276	56 - 210
PERSONAL	Personal Directory	0	1	108 - 284	63.220
NAUGHINS	Personal Directory Naugha Adventure	0	1	134.303	82 - 247
EGGS	Eggs Gane	3	4	176 - 338	114.288
DIRPRINT	Disk Directory Prin	t O	1	201.358	137.316
SPEEDKEY	Speed Key	0	1	207 - 362	142 - 322
					TO SHARE THE PARTY OF THE PARTY
N. W. W.	SOUTH AND SOUTH	VICTORIES	BANKS SAME	MARCHON DES	THE PERSON NO.
DESCRIPTION COME	USERS: Insert disk and run 'DRY, CASSETT	E TAPE LIST	FRS: Beeled tax	Zeen the tape count	125276747033
DECEMBER Fast	Forward to desired program's tape counter ru white loading or running a program, you get a PRICEE and PCLEAR values from				

Welcome to our March 1985 edition of Coco-Cassette. If you have a business or home management program idea that you would like us to write a program for, please write down your idea and mail it in. If the program idea is practical, we will try to create a program for it and present it on a future issue.

1. LIGHT CYCLE - Light Cycle is a high resolution game for two players. You must force your opponent into a wall by surrounding his with the wall you create when your cycle moves. The first player to run into a wall, loses. Two joysticks are required.

2. PAINT - Paint draws eight different pictures and allows you to paint them as you wish. Pictures may be saved and loaded for later use. If you have a high resolution picture from a different program, you can paint that picture by simply loading your orig-

inal picture, loading PAINT, run and hit option five. 3. SKERT SHOOTING - Push the lovatick button and your clay pidgeons are launched. How many of the twenty five can you get? The right joystick will control your coco rifle as you attempt to make

the rank of a markaman.

4. GUITAR NOTES - This program is an aid to those who play the guitar. When playing a solo, the guitarist must play notes which are in tune with the rest of the music. This program will display all notes that fit for any major or minor key. The colored dots are places where notes are in tune with the selected key.

 ML DISK ANALYZER - This is a utility which is used to display the start, end, and execute addresses of machine language programs on disk.

6. PERSONAL DIRECTORY - This program is a quick reference name, address, and phone number indexing utility. When the program is also loaded, the data which is embedded in the program is also loaded. Thus, you do not have to spend extra time searching for and loading any extra data file.

7. MADORA ADVENTURE - Naugha is an adventure game which is consposed of three parts. The first part is an instruction program. The second part is the main adventure program. The third part is a data file which is loaded when the main program is run. Can you find the Fabled Astec Robe made from the last of the Albino Diamond Tuck Naughan?

8. EGOS GAME - In this 32K game, You must play the role as a chicken farer. You must collect eggs, clean up dropped eggs, chase the chicken thief and fox away while you protect the henhouse. You also have various tools to use such as a banket, a showel, a hammer, a club, and rock salt. Bemember, you can only hold one tool at a time.

Note: The next two programs are machine language programs. You must enter 'CLOADM' instead of 'CLOAD' and 'EXEC' instead of 'RUN'.

DISK DIRECTORY PRINT - This machine language utility will
print the directory of your diskettes on the printer. The format
for the print out is expanded and sore detailed than DIR. Insert
the disk into drive zero when prospted. To save this program to
tape or disk, enter (CISAVEMPDIRERINT".12000,13178,12000.

10. SPEED REY - This utility will speed entry of basic keywords. To load and run ifs - Enter CLEAR 200,1999, CLOADW. REEC. 32K - Enter CLEAR 200,23283. CLOADW.SPEEDREY*,16384. EXEC. Donce the utility has been executed, press the down arrow followed by an alphabetic letter. The entire keyword will be automatically typed. To are this program, enter (ClSAWWTOSEDENEY,16000,1638).

Α	ASC(В	EDIT	I	INKEY\$	м	MIDS	0	PEEK (U	POKE	Y	LINE
В	ELSE	F	GOSUB	J	INPUT	N	SET (B	RESTORE	v	VALC	Z	DIR
C	CHRS	G	GOTO	K	JOYSTE	0	RESET	8	RETURN	W	SAVE		

If you have any problems loading the programs try changing the volume on your tape recorder. If you have any questions, problems, solutions or chatter, please write to us. If you have any uncopyrighted programs that you want to show us, we will be glad to see them. Send them is and if we like them, we will have you an offer.